CYBIL I/O Reference Manual

06/22/84 REV: 2

PEV. 2

CYBILIO

REFERENCE MANUAL

06/22/84 REV: 2

CYBIL I/O Reference Manual

REVISION DEFINITION SHEET

		+
REV	DATE	DESCRIPTION
	+	
1	12/13/83	Preliminary manual released.
2	06/22/84	Updated preliminary manual.

c 1983 by Control Data Corporation

CYBIL I/O Reference Manual

REV: 2

1.0 INTRODUCTION

1.0 <u>INTRODUCTION</u>

The CYBILIO package (CYBILIO) is a collection of procedures and data types which provide an Input/Output system that interfaces a CYBIL program to the NOS & NOS/BE I/O system.

1.1 <u>APPLICABLE DOCUMENTS</u>

60455280	CYBIL Reference Manual
60457280	Language Specification for CDC CYBER IMPLEMENTATION LANGUAGE
60457250	SES User's Handbook
60459660	NOS Version 2 Reference Manual (Volume 1)
60459670	NOS Version 2 Reference Manual (Volume 2)
60459680	NOS Version 2 Reference Manual (Volume 3)
60459690	NOS Version 2 Reference Manual (Volume 4)
60450100	NOS Version 1 Modify Reference Manual
60493800	NOS/BE Version 1 Reference Manual
60494100	NOS/BE Version 1 System Programmer's Reference Manual
60499900	Update Version 1 Reference Manual

CYBIL I/O Reference Manual

1.0 INTRODUCTION

1.2 FILE TYPES

1.2 FILE TYPES

CYBILIO deals with a (small) number of distinct types of files. The properties of the various file types are described in the subsections which follow.

1.2.1 BINARY FILES

Binary files have only sequential access. Data appears on such files in the order in which it was written, and can only be read in that same order. These files may be positioned at the beginning or end of information. Note that positioning at the beginning and then writing a binary file implies that all data which was previously on the file is lost.

Binary files may be structured using record/file marks, and detection of the structure is possible.

1.2.2 DIRECT FILES

Direct files are like binary files except that data may be transferred to/from them at "random addresses" known as $\underline{\text{keys}}$. Note that writing (from the beginning of) a direct file does not necessarily imply that existing data (which follows the data being written) will be lost (c.f., binary files).

In addition to the positioning facilities provided for binary files, direct files may be positioned via a $\underline{\text{key}}$ to any location.

1.2.3 LEGIBLE FILES

Legible files are sequentially accessed and are assumed to contain character data in NOS 6/12 or in NOS/BE 8/12 representation. Legible I/O procedures provide for the conversion between the external (on the file) data format and the internal format (CYBIL strings). The basic entity on a legible file is a $\frac{1 \text{ ine}}{1}$ which can be transferred to/from the file in whole or in part. In addition, there is a facility to $\frac{1}{1}$ to a specified 60460300 02

CYBIL I/O Reference Manual

1.0 INTRODUCTION

1.2.3 LEGIBLE FILES

column in an output line.

The same structuring and positioning facilities provided for binary files are also available for legible files.

1.2.4 PRINT FILES

Print files are legible files which have additional facilities for (vertical) format control. It is possible to limit the number of lines on a page, insert a given number of empty lines, overprint lines, position the next line at a specified line number or at the top of the next page. Several procedures are provided to change and interrogate certain items of control information for print files.

The user may associate with each print file, a procedure to be called when a "page overflow condition" occurs for that file. Such a procedure can perform page heading (titling) and footing operations.

CYBIL I/O Reference Manual

REV: 2

- 1.0 INTRODUCTION
- 1.3 CYBILIO DATA TYPES

1.3 CYBILIO DATA TYPES

This section defines the CYBIL "types" required to interface to CYBILIO.

TYPE file = ^CELL;

This type is used when calling any of the CYBILIO procedures. A variable of this type is defined when passed to one of the file open procedures, and remains defined until the corresponding close procedure is called.

TYPE file_status = (new#, old#);

This type is used when opening a file to designate whether the file already exists or needs to be "created".

TYPE file mode = (input#, output#, concurrent#);

This type is used when opening a file to designate the "direction" of data transfers.

TYPE file position = (first#, asis#, last#, null#);

This type is used when opening a file to designate where the file should be initially positioned (at its beginning, where ever it happens to be, at its end, or where ever it happens to be). Please note that usage of asis# or null# will yield the same result.

This type is used when closing a file to designate at what "position" (or with which "disposition") the file should be left (at its beginning, where ever it happens to be, or "return" it to the operating system).

60460300 02

CYBIL I/O Reference Manual

REV: Z

1. 0. TATED ODITION

1.0 INTRODUCTION

1.3 CYBILIO DATA TYPES

TYPE file encoding = (ascii64#, ascii612#, ascii#);

This type is used to define the (external) character set for a legible or print file. The default on NOS, when the file is opened, is ascii612# which designates the NOS 6/12 character set. The default on NOS/BE is ascii#. The user can select the 6-bit display code character set designated by ascii64#, or the "8 out of 12 bit" ASCII character set designated by ascii#.

TYPE file mark = (data#, eor#, eof#, eoi#);

This type is used to designate the file structure marks. A value of this type can be obtained for a file subsequent to a performing an input (read, get) request on the file. Thus, data# means "no mark encountered"; eor# means "a (logical) End Of Record was encountered"; eof# means "a (logical) End Of File was encountered"; and eoi# means "the End of Information was encountered".

CYBIL I/O Reference Manual

1.0 INTRODUCTION

1.4 USING CYBILIO

1.4 USING CYBILIO

1.4.1 SOURCE CODE INTERFACE TO CYBILIO ON NOS

To interface to CYBILIO a CYBIL program module must include the relevant type and procedure declarations. These can be *CALLed from a MODIFY program library (PL). The name of this program library is CYBCCMN, which is accessible by including the CYBCCMN parameter in the SES.GENCOMP call or can be made local by SES.GETCCMN. The CYBILIO type declarations are on common deck PXIOTYP and each procedure declaration is on its own common deck (see the section on naming conventions and the individual procedure descriptions to determine the common deck names).

1.4.2 SOURCE CODE INTERFACE TO CYBILIO ON NOS/BE

To interface to CYBILIO a CYBIL program module must include the relevant type and procedure declarations. These can be *CALLed from an UPDATE program library (PL). The name of this program library is CYBCCMN. The CYBILIO type declarations are on common deck PXIOTYP and each procedure declaration is on its own common deck (see the section on naming conventions and the individual procedure descriptions to determine the common deck names).

1.4.3 OBJECT CODE INTERFACE TO CYBILIO

Before a program (which uses CYBILIO) can be executed, it must be linked with the CYBILIO object modules which are located on The CYBIL-CC run-time library, which is accessible by including the CYBCLIB parameter on the loader directives. On NOS this could be via the SES.LINK170 or on NOS & NOS/BE by having CYBCLIB as a local file at program load time.

1.4.4 NAMING CONVENTIONS

The identifiers for all CYBILIO procedures adhere to the following naming convention:

60460300 02

CYBIL I/O Reference Manual

1.0 INTRODUCTION

1.4.4 NAMING CONVENTIONS

- all BINARY file procedure identifiers begin with bi# - all DIRECT file procedure identifiers begin with di# - all LEGIBLE file procedures identifiers begin with 1g#
- all PRINT file procedure identifiers begin with pr#
 identifiers for procedures which are applicable to all file types begin with **f#**

The names of the common decks which contain the CYBILIO procedure declarations are derived by taking (up to) the first seven characters of the procedure name and changing the $\underline{\#}$ character in the procedure name to a \mathbf{Z} for the common deck name.

 $\underline{\text{Note:}}$ that all common decks required for a particular file type can be included with MODIFY's *CALLALL directive. For example, a program that uses legible and print files could bring in all the relevant declarations as follows:

- *CALL pxiotyp
- *CALLALL lqz
- *CALLALL prz
- *CALLALL fz

1.4.5 FILE VARIABLE USAGE

CYBILIO considers a variable of type ${\bf file}$ to be undefined until one of the open procedures has been called; and to become undefined once one of the close procedures has been called. The consequences of using an undefined file variable to call any CYBILIO procedure (except one of the open procedures) is unpredictable.

1.4.6 FILE NAMES

File names (which are passed as adaptable CYBIL strings to the open procedures) must be from one to seven alphanumeric characters (i.e., letters or digits). The open procedures will convert any lower case letters in a file name to the corresponding upper case letters.

CYBIL I/O Reference Manual

1.0 INTRODUCTION

1.4.7 FILE STRUCTURE CREATION / DETECTION

1.4.7 FILE STRUCTURE CREATION / DETECTION

CYBILIO supports both the creation and detection of file structuring "marks". There are two such marks: End Of (logical) Record; and End Of (logical) File. The End Of Information can only be implicitly created (i.e., the End Of Information follows the physically last item written on a file); but it can be explicitly detected.

Note that detection of a file structure mark can only be meaningfully attempted after an \underline{input} request on the file.

When performing input operations on binary and direct files, it is possible to have an incomplete transfer. This can result from reading a file not created by CYBILIO, or not reading a file in a manner which mimics the way in which the file was written. In order to handle these incomplete transfers, a procedure is provided to return the last transfer length for a file. The value returned by this procedure is only meaningfull if the immediately preceding operation on the file was one of bi#get, bi#put, di#get, di#getdir, lg#get, lg#getpart, lg#put, lg#putpart, lg#tab, or lg#weol.

1.4.8 CIO BUFFER SIZE CONTROL

The size of the CIO circular buffer can be selected for files used with CYBILIO by setting the INTEGER variable **px#iobs** to the desired size. The value of this variable is used by the file open procedures in order to create a CIO circular buffer with the designated size. The declaration for this variable is contained on common deck PXZIOBS.

1.4.9 LONG STRING OF BLANK (SPACE) CHARACTERS

CYBILIO needs a long (256) string of blank characters in order to efficiently perform the **lg#tab** and **pr#tab** operations. This string is made available to the user in the variable **px#blnk**. The declaration for this variable is located on common deck PXZBLNK.

CYBIL I/O Reference Manual REV: 2

2.0 I/O PROCEDURES

2.0 <u>I/O PROCEDURES</u>

```
2.1 BINARY FILES
```

{ PXIOTYP

2.1.1 OPENING AND CLOSING BINARY FILES

2.1.1.1 BI#OPEN - Open Binary File

Opens binary_file as local file_name.

```
TYPE
    file = ^cell,
    file_status = (new#, old#),
    file_mode = (input#, output#, concurrent#),
file_encoding = (ascii64#, ascii612#, ascii#),
    file_mark = (data#, eor#, eof#, eoi#),
file_position = (first#, asis#, last#, null#);
  CONST
    return# = last#;
  TYPE
    file_disposition = first# .. return#;
  { i.e. (first#, asis#, return#) }
               Opens binary file as local file. }
{ BIZOPEN
  PROCEDURE [XREF] bi#open (VAR binary_file: file;
    file name: string ( * );
    status: file status;
    mode: file mode;
    position: file position);
```

Contains CYBIL type declarations. }

CYBIL I/O Reference Manual

2.0 I/O PROCEDURES

2.1.1.2 BI#CLOSE - Close Binary File

2.1.1.2 BI#CLOSE - Close Binary File

Closes binary file.

{ BIZCLOS Closes binary file. }

PROCEDURE [XREF] bi#close (binary_file: file;
 disposition: file_disposition);

CYBIL I/O Reference Manual

2.0 I/O PROCEDURES

2.1.2 POSITIONING BINARY FILES

2.1.2 POSITIONING BINARY FILES

2.1.2.1 BI#FIRST - Position Binary File at BOI

Positions binary_file at its beginning of information.

```
Positions binary file at its beginning of information. }
PROCEDURE [XREF] bi#first (binary_file: file);
```

2.1.2.2 BI#LAST - Position Binary File at EOI

Positions binary file at its end of information.

```
{ BIZLAST
            Positions binary file at its end of information. }
  PROCEDURE [XREF] bi#last (binary_file: file);
```

CYBIL I/O Reference Manual

2.0 I/O PROCEDURES

2.1.3 BINARY FILE STRUCTURE CREATION / DETECTION

2.1.3 BINARY FILE STRUCTURE CREATION / DETECTION

2.1.3.1 BI#WEOR - Write End Of Record on Binary File

Writes an End Of Record mark on binary file.

```
Writes and End of Record mark on binary file. }
PROCEDURE [XREF] bi#weor (binary_file: file);
```

2.1.3.2 BI#WEOF - Write End Of File on Binary File

Writes an End Of File mark on binary file.

```
{ BIZWEOF
            Writes an End of File mark on binary file. }
  PROCEDURE [XREF] bi#weof (binary_file: file);
```

2.1.3.3 F#MARK - Check Structure Mark on File

Returns the "file structure mark" last encountered on any_file.

```
{ FZMARK
           Returns the file structure mark last encountered on file. }
 PROCEDURE [XREF] f#mark (any file: file;
   VAR mark: file_mark);
```

CYBIL I/O Reference Manual

2.0 I/O PROCEDURES

2.1.3.4 F#WORDS - Last Transfer Length on File

2.1.3.4 <u>F#WORDS - Last Transfer Length on File</u>

Returns the length of the last transfer to/from any file.

{ FZWORDS Returns length of last transfer to/from file. }

PROCEDURE [XREF] f#words (any_file: file; VAR last_transfer_length: integer);

CYBIL I/O Reference Manual

REV: 2

2.0 I/O PROCEDURES

2.1.4 READING AND WRITING BINARY FILES

2.1.4 READING AND WRITING BINARY FILES

Transfer of data to and from binary files is performed in groups of words (cells). Since the data transfer procedures for binary files (like all other programmer defined procedures in CYBIL) must have parameters of a specific type, and since we want to be able to transfer items of any data type to/from a binary file, the objects of transfer are passed to the procedures in two parts: address (usually via the #loc function); and length (usually via the #size function). CYBILIO has no way to insure that the address and length parameters refer to the same object, therefore be warned: "you're on your own" as far as checking parameter correctness is concerned.

2.1.4.1 BI#PUT - Write to Binary File

Writes length_of_source words (cells) beginning at the address specified by pointer to source to binary file.

```
{ BIZPUT Writes specified information to binary file. }

PROCEDURE [XREF] bi#put (binary_file: file;
   pointer_to_source: ^cell;
   length of source: integer);
```

2.1.4.2 BI#GET - Read from Binary File

Reads up to $length_of_target$ words (cells) from $binary_file$ to the address specified by $pointer_to_target$. Note that an "incomplete transfer" can result from this request (see the section on "File Structure Creation / Detection" for more information on this subject).

```
{ BIZGET Reads info from binary file to address specified. }

PROCEDURE [XREF] bi#get (binary_file: file;
   pointer_to_target: ^cell;
   length of target: integer);
```

```
CYBIL I/O Reference Manual REV: 2
2.0 I/O PROCEDURES
2.1.5 EXAMPLE - COPY BINARY FILE
```

2.1.5 EXAMPLE - COPY BINARY FILE

The following example illustrates the use of the binary file procedures to make a copy of a file (without knowing beforehand the structure or length of the file).

```
MODULE copy ALIAS 'zpxmcop';
{ PXIOTYP
             Contains CYBIL type declarations. }
  TYPE
    file = ^cell,
    file_status = (new#, old#),
file_mode = (input#, output#, concurrent#)
    file_encoding = (ascii64#, ascii612#, ascii#),
    file_mark = (data#, eor#, eof#, eoi#),
file_position = (first#, asis#, last#, null#);
  CONST
    return# = last#;
    file disposition = first# .. return#;
  { i.e. (first#, asis#, return#) }
{ BIZOPEN
              Opens binary file as local file. }
  PROCEDURE [XREF] bi#open (VAR binary_file: file;
    file_name: string ( * );
    status: file_status;
    mode: file_mode;
position: file_position);
{ BIZCLOS
              Closes binary file. }
  PROCEDURE [XREF] bi#close (binary_file: file;
    disposition: file disposition);
{ BIZGET
             Reads info from binary file to address specified. }
  PROCEDURE [XREF] bi#get (binary_file: file;
```

```
06/22/84
```

```
CYBIL I/O Reference Manual
______
2.0 I/O PROCEDURES
2.1.5 EXAMPLE - COPY BINARY FILE
   pointer_to_target: ^cell;
   length_of_target: integer);
           Writes specified information to binary file. }
{ BIZPUT
 PROCEDURE [XREF] bi#put (binary file: file;
   pointer to source: ^cell;
   length of source: integer);
{ BIZWEOR
            Writes and End of Record mark on binary file. }
 PROCEDURE [XREF] bi#weor (binary_file: file);
            Writes an End of File mark on binary file. }
{ BIZWEOF
 PROCEDURE [XREF] bi#weof (binary file: file);
{ FZMARK
           Returns the file structure mark last encountered on file. }
 PROCEDURE [XREF] f#mark (any_file: file;
   VAR mark: file mark);
{ FZWORDS
            Returns length of last transfer to/from file. }
 PROCEDURE [XREF] f#words (any_file: file;
   VAR last_transfer_length: integer);
 PROGRAM copy ALIAS 'zpxpcop';
   CONST
     in name = 'OLD',
     out name = 'NEW'
     buf\overline{f}er length = 64;
   VAR
     in file : file,
     ou\bar{t} file : file,
     buffer : ARRAY [1 .. buffer_length] of CELL,
     transfer_length : INTEGER,
mark : file_mark;
   bi#open (in file, in name, old#, input#, first#);
   bi#open (out file, out name, new#, output#, first#);
  /main_loop/
   WHILE TRUE DO
     bi#get (in_file, #LOC(buffer), #SIZE(buffer));
```

```
06/22/84
```

```
CYBIL I/O Reference Manual

2.0 I/O PROCEDURES
2.1.5 EXAMPLE - COPY BINARY FILE

f#mark (in_file, mark);
CASE mark OF

=eoi#=
    EXIT /main_loop/;
=eof#=
    bi#weof (out_file);
=eor#=
    f#words (in_file, transfer_length);
    IF transfer_length > 0 THEN
        bi#put (out_file, #LOC(buffer), transfer_length);
    IFEND;
    bi#weor (out_file);
=data#=
```

bi#put (out file, #LOC(buffer), #SIZE(buffer));

PROCEND copy;

CASEND;

WHILEND /main_loop/; bi#close (in_file, first#); bi#close (out_file, first#);

MODEND copy;

CYBIL I/O Reference Manual REV: 2

2.0 I/O PROCEDURES

2.2 DIRECT FILES

2.2 DIRECT FILES

2.2.1 OPENING AND CLOSING DIRECT FILES

2.2.1.1 DI#OPEN - Open Direct File

Opens $direct_file$ as local $file_name$. Note: that a direct file cannot be opened at position asis#.

```
{ DIZOPEN Opens direct file as local file. }

PROCEDURE [XREF] di#open (VAR direct_file: file; file_name: string ( * ); status: file_status; mode: file_mode; position: file_position);
```

2.2.1.2 <u>DI#CLOSE - Close Direct File</u>

```
Closes direct file.
```

```
{ DIZCLOS Closes direct file. }

PROCEDURE [XREF] di#close (direct_file: file;
    disposition: file disposition);
```

CYBIL I/O Reference Manual

REV: 2

2 0 T/O DROGERUIDEG

2.0 I/O PROCEDURES

2.2.2 POSITIONING DIRECT FILES

2.2.2 POSITIONING DIRECT FILES

2.2.2.1 <u>DI#FIRST - Position Direct File at BOI</u>

Positions direct file at its beginning of information.

```
{ DIZFIRS Positions direct file at its beginning of information. } 
PROCEDURE [XREF] di#first (direct_file: file);
```

2.2.2.2 <u>DI#LAST - Position Direct File at EOI</u>

Positions direct file at its end of information.

```
{ DIZLAST Positions direct file at its End of Information. }

PROCEDURE [XREF] di#last (direct_file: file);
```

2.2.2.3 <u>DI#LOCATE - Position Direct File via Key</u>

Positions $direct_file$ at the location specified by key. If key specifies a position outside the bounds of the file, then the program is in error.

```
{ DIZLOCA Positions direct file at location specified. }

PROCEDURE [XREF] di#locate (direct_file: file;
   key: integer);
```

CYBIL I/O Reference Manual REV: 2

2.0 I/O PROCEDURES

2.2.3 DIRECT FILE STRUCTURE CREATION / DETECTION

2.2.3 DIRECT FILE STRUCTURE CREATION / DETECTION

2.2.3.1 DI#WEOR - Write End Of Record on Direct File

Writes an End Of Record mark on direct file.

```
{ DIZWEOR Writes an End of Record mark on direct file. }

PROCEDURE [XREF] di#weor (direct_file: file);
```

2.2.3.2 DI#WEOF - Write End Of File on Direct File

Writes an End Of File mark on direct file.

```
{ DIZWEOF Writes an End of File mark on direct file. }

PROCEDURE [XREF] di#weof (direct_file: file);
```

2.2.3.3 F#MARK - Check Structure Mark on File

Returns the "file structure mark" last encountered on any_file.

```
{ FZMARK Returns the file structure mark last encountered on file. }
PROCEDURE [XREF] f#mark (any_file: file;
   VAR mark: file_mark);
```

CYBIL I/O Reference Manual

REV: 2

2. A. T./O. DDOGEDBURG

2.0 I/O PROCEDURES

2.2.3.4 F#WORDS - Last Transfer Length on File

2.2.3.4 <u>F#WORDS - Last Transfer Length on File</u>

Returns the length of the last transfer from any file.

{ FZWORDS Returns length of last transfer to/from file. }

PROCEDURE [XREF] f#words (any_file: file; VAR last_transfer_length: integer);

CYBIL I/O Reference Manual

2.0 I/O PROCEDURES

2.2.4 READING AND WRITING DIRECT FILES

2.2.4 READING AND WRITING DIRECT FILES

Transfer of data to and from direct files is performed in groups of words (cells). Since the data transfer procedures for direct files (like all other programmer defined procedures in CYBIL) must have parameters of a specific type, and since we want to be able to transfer items of any data type to/from a direct file, the objects of transfer are passed to the procedures in two parts : address (usually via the #loc function); and length (usually via the #size function). CYBILIO has no way to insure that the address and length parameters refer to the same object, therefore be warned: "you're on your own" as far as checking parameter correctness is concerned.

2.2.4.1 DI#PUT - Sequential Write to Direct File

Writes length_of_source words (cells) from the address specified by
pointer_to_source to direct_file at its current position. The "random
file address" of the data written is returned in key.

```
{ DIZPUT Writes info from address spec. to direct file's current pos. }

PROCEDURE [XREF] di#put (direct_file: file;

VAR key: integer;

pointer_to_source: ^cell;
length_of_source: integer);
```

2.2.4.2 <u>DI#PUTDIR - Random Write to Direct FIle</u>

Writes length_of_source words (cells) from the address specified by pointer_to_source to direct_file at the "random file address" specified by key.

```
{ DIZPUTD Writes info to direct file at random address specified. }

PROCEDURE [XREF] di#putdir (direct_file: file;
   key: integer;
```

60460300 02

CYBIL I/O Reference Manual

REV: 2

```
2.0 I/O PROCEDURES
```

2.2.4.2 DI#PUTDIR - Random Write to Direct FIle

```
pointer_to_source: ^cell;
length_of_source: integer);
```

2.2.4.3 <u>DI#GET - Sequential Read from Direct File</u>

Reads up to <code>length_of_target</code> words (cells) from <code>direct_file</code> at its current position to the address specified by <code>pointer_to_target</code>. The "random file address" of the data read is returned in <code>key</code>. Note that an "incomplete transfer" can result from this request (see the section on "File Structure Creation / Detection" for more information on this subject).

```
{ DIZGET Reads info from direct file's current position to add. spec. }

PROCEDURE [XREF] di#get (direct_file: file;
   VAR key: integer;
   pointer_to_target: ^cell;
   length_of_target: integer);
```

2.2.4.4 <u>DI#GETDIR - Random Read from Direct File</u>

Reads up to length_of_target words (cells) from direct_file at the "random file address" specified by key to the address specified by pointer_to_target. Note that an "incomplete transfer" can result from this request (see the section on "File Structure Creation / Detection" for more information on this subject).

```
{ DIZGETD Reads info from direct file's random file address. }

PROCEDURE [XREF] di#getdir (direct_file: file;
   key: integer;
   pointer_to_target: ^cell;
   length_of_target: integer);
```

CYBIL I/O Reference Manual

._____

2.0 I/O PROCEDURES

2.2.5 DIRECT FILE STATUS INTERROGATION

2.2.5 DIRECT FILE STATUS INTERROGATION

2.2.5.1 <u>DI#LENGTH - Direct File Length?</u>

```
Returns the file length in words of direct file.
```

```
{ DIZLENG Returns length in words of direct file. }

PROCEDURE [XREF] di#length (direct_file: file;
   VAR file_length_in_words: integer);
```

2.2.5.2 <u>DI#KEY - Direct File Current Position?</u>

Returns the ${\tt current_position_key}$ designating the current position of ${\tt direct\ file}$.

```
{ DIZKEY Returns the KEY designating direct file's current position. }

PROCEDURE [XREF] di#key (direct_file: file;
   VAR current_position_key: integer);
```

CYBIL I/O Reference Manual REV:

2.0 I/O PROCEDURES

2.2.6 EXAMPLES OF DIRECT FILE USAGE

2.2.6 EXAMPLES OF DIRECT FILE USAGE

The examples which follow illustrate the use of direct file procedures. The first example creates a "library" of "text modules" from a legible file. The modules on the source (legible) file are represented as NOS records whose first line contains the module name (and nothing else). The second example extracts from the library one of the modules and copies it to a file whose name is that of the module.

2.2.6.1 Create Text Library

```
MODULE create text_library ALIAS 'zpxmcre';
{ PXIOTYP
            Contains CYBIL type declarations. }
  TYPE
    file = ^cell,
    file_status = (new#, old#),
    file_mode = (input#, output#, concurrent#),
    file_encoding = (ascii64#, ascii612#, ascii#),
    file_mark = (data#, eor#, eof#, eoi#),
file_position = (first#, asis#, last#, null#);
  CONST
    return# = last#;
  TYPE
    file disposition = first# .. return#;
  { i.e. (first#, asis#, return#) }
{ LGZOPEN
              Opens legible file as local file. }
  PROCEDURE [XREF] lg#open (VAR legible file: file;
    file name: string ( * );
    status: file status;
    mode: file mode;
    position: Tile position);
            Closes legible file. }
{ LGZCLOS
```

```
06/22/84
CYBIL I/O Reference Manual
2.0 I/O PROCEDURES
2.2.6.1 Create Text Library
  PROCEDURE [XREF] lg#close (legible file: file;
    disposition: file disposition);
{ LGZGET
            Reads next complete line from legible file. }
  PROCEDURE [XREF] lq#qet (legible file: file;
    VAR number_of_characters_read: integer;
    VAR line: string ( * ));
{ FZMARK
            Returns the file structure mark last encountered on file. }
  PROCEDURE [XREF] f#mark (any_file: file;
    VAR mark: file mark);
             Opens direct file as local file. }
  PROCEDURE [XREF] di#open (VAR direct_file: file;
    file name: string ( * );
    status: file status;
    mode: file mode;
    position: file_position);
{ DIZCLOS
             Closes direct file. }
  PROCEDURE [XREF] di#close (direct file: file;
    disposition: file_disposition);
            Writes info from address spec. to direct file's current pos. }
{ DIZPUT
  PROCEDURE [XREF] di#put (direct file: file;
    VAR key: integer;
    pointer_to_source: ^cell;
    length_of_source: integer);
{ DIZPUTD
             Writes info to direct file at random address specified. }
  PROCEDURE [XREF] di#putdir (direct_file: file;
    key: integer;
    pointer_to_source: ^cell;
length_of_source: integer);
             Opens binary file as local file. }
{ BIZOPEN
  PROCEDURE [XREF] bi#open (VAR binary_file: file;
    file_name: string ( * );
    status: file_status;
```

```
06/22/84
```

```
REV: 2
CYBIL I/O Reference Manual
______
2.0 I/O PROCEDURES
2.2.6.1 Create Text Library
    mode: file_mode;
    position: Tile position);
             Closes binary file. }
{ BIZCLOS
  PROCEDURE [XREF] bi#close (binary_file: file;
    disposition: file disposition);
{ BIZPUT
            Writes specified information to binary file. }
  PROCEDURE [XREF] bi#put (binary_file: file;
    pointer_to_source: ^cell;
    length_of_source: integer);
{ BIZGET
            Reads info from binary file to address specified. }
  PROCEDURE [XREF] bi#get (binary_file: file;
  pointer_to_target: ^cell;
    length of target: integer);
  TYPE
    directory_descriptor = RECORD
  key : INTEGER,
      length : INTEGER,
    RECEND,
    directory_entry = RECORD
  name : STRING (7),
      length : INTEGER,
      key : INTEGER,
    RECEND;
  CONST
    source name = 'SOURCE',
    lib_name = 'LIBRARY',
    dir_name = 'SCRATCH';
  PROGRAM create ALIAS 'zpxpcre';
    VAR
      source : file,
      library : file,
dir_file : file,
      directory : directory_descriptor,
      current_module : directory_entry,
line : STRING (256),
```

```
. / . . . / . .
```

```
06/22/84
                                                            REV: 2
CYBIL I/O Reference Manual
_____
2.0 I/O PROCEDURES
2.2.6.1 Create Text Library
     line_length : INTEGER,
     module index : INTEGER,
     first \overline{k}ey : INTEGER,
     dummy_key : INTEGER,
     mark : file mark;
   lg#open (source, source_name, old#, input#, first#);
   bi#open (dir_file, dir_name, new#, output#, first#);
   di#open (library, lib_name, new#, output#, first#);
directory.length := 0;
   di#put (library, first_key,
           #LOC(directory), #SIZE(directory));
 /copy_module_loop/
   WHILE TRUE DO
     lg#get (source, line_length, line);
     f#mark (source, mark);
     CASE mark OF
     =eoi#=
       EXIT /copy_module_loop/;
     =eof#, eor#=
       CYCLE /copy_module_loop/;
     =data#=
       directory.length := directory.length + 1;
       current module.name := line(1, line length);
       current_module.length := 1;
       di#put (library, current_module.key,
               #LOC(current module.name)
               #SIZE(current module.name));
     /copy text loop/
       WHILE TRUE DO
         lg#get (source, line_length, line);
f#mark (source, mark);
         IF mark <> data# THEN
           EXIT /copy_text_loop/;
         IFEND;
         current module.length := current module.length + 1;
         di#put (library, dummy_key,
                 #LOC(line length), #SIZE(line length));
         WHILEND /copy text loop/;
       bi#put (dir_file, #LOC(current_module),
                         #SIZE(current_module));
     CASEND;
   WHILEND /copy_module_loop/;
   lq#close (source, first#);
```

```
c /22 /0/
```

```
06/22/84
CYBIL I/O Reference Manual
2.0 I/O PROCEDURES
2.2.6.1 Create Text Library
     IF directory.length > 0 THEN
       bi#close (dir_file, asis#);
bi#open (dir_file, dir_name, old#, input#, first#);
bi#get (dir_file, #LOCC(current_module),
                              #SIZE(current module));
       di#put (library, directory.key,
       #LOC(current_module), #SIZE(current_module));
FOR module_index := 2 TO directory.length DO
  bi#get (dir_file, #LOC(current_module),
                                #SIZE(current_module));
          di#put (library, dummy_key,
                    #LOC(current_module), #SIZE(current_module));
       FOREND;
       di#putdir (library, first key,
                     #LOC(directory), #SIZE(directory));
     IFEND;
     bi#close (dir file, return#);
     di#close (library, first#);
  PROCEND create;
MODEND create_text_library;
2.2.6.2 Extract from Text Library
MODULE extract from text library ALIAS 'zpxmefl';
{ PXIOTYP
             Contains CYBIL type declarations. }
  TYPE
     file = ^cell,
     file_status = (new#, old#),
file_mode = (input#, output#, concurrent#),
     file_encoding = (ascii64#, ascii612#, ascii#),
     file_mark = (data#, eor#, eof#, eoi#),
file_position = (first#, asis#, last#, null#);
  CONST
     return# = last#;
  TYPE
     file_disposition = first# .. return#;
```

```
CYBIL I/O Reference Manual
______
2.0 I/O PROCEDURES
2.2.6.2 Extract from Text Library
 { i.e. (first#, asis#, return#) }
            Opens direct file as local file. }
{ DIZOPEN
 PROCEDURE [XREF] di#open (VAR direct file: file;
   file name: string ( * );
   status: file status;
   mode: file mode;
   position: file_position);
{ DIZCLOS
            Closes direct file. }
 PROCEDURE [XREF] di#close (direct file: file;
   disposition: file disposition);
{ DIZLOCA
            Positions direct file at location specified. }
 PROCEDURE [XREF] di#locate (direct file: file;
   key: integer);
{ DIZGETD
            Reads info from direct file's random file address. }
 PROCEDURE [XREF] di#getdir (direct file: file;
   key: integer;
   pointer_to_target: ^cell;
   length_of_target: integer);
           Reads info from direct file's current position to add. spec. }
{ DIZGET
 PROCEDURE [XREF] di#get (direct file: file;
   VAR key: integer; pointer_to_target: ^cell;
   length_of_target: integer);
{ LGZOPEN
            Opens legible file as local file. }
 PROCEDURE [XREF] lg#open (VAR legible_file: file;
   file name: string ( * );
   status: file_status;
   mode: file_mode;
position: file_position);
{ LGZCLOS
            Closes legible file. }
 PROCEDURE [XREF] lg#close (legible file: file;
   disposition: file_disposition);
```

{ ERROR - module not found }

di#locate (library, directory.key);

RETURN; IFEND;

BEGIN

/search directory/

```
CYBER IMPLEMENTATION LANGUAGE
                                                                         06/22/84
                                                                   REV: 2
CYBIL I/O Reference Manual
2.0 I/O PROCEDURES
2.2.6.2 Extract from Text Library
{ LGZPUT
            Writes source string as complete line to legible file. }
  PROCEDURE [XREF] lg#put (legible_file: file;
    line: string ( * ));
  TYPE
    directory_descriptor = RECORD
      key : INTEGER,
      length : INTEGER,
    RECEND,
    directory_entry = RECORD
  name : STRING (7),
      length : INTEGER,
    key : INTEGER,
RECEND;
  CONST
    lib_name = 'LIBRARY';
  CONST
    name of module = 'TEXTMOD';
  PROGRAM extract ALIAS 'zpxpefl';
    VAR
      library : file,
      out file : file,
      directory : directory_descriptor,
      current module : directory entry,
      line: \overline{S}TRING (256),
      line_length : INTEGER,
      module_index : INTEGER,
      dummy_key : INTEGER;
    di#open (library, lib_name, old#, input#, first#);
    di#get (library, dummy_key,
    #LOC(directory), #SIZE(directory));
IF directory.length = 0 THEN
```

```
06/22/84
                                                                 REV: 2
CYBIL I/O Reference Manual
2.0 I/O PROCEDURES
2.2.6.2 Extract from Text Library
      FOR module index := 1 TO directory.length DO
        di#get (library, dummy_key,
                #LOC(current module), #SIZE(current module));
        IF current module.name = name_of_module THE\overline{N}
          EXIT /search directory/;
        IFEND;
      FOREND;
      { ERROR - module not found }
      RETURN;
    END /search_directory/;
    lg#open (out_file, name_of_module, new#, output#, first#);
    di#getdir (library, current module.key,
               #LOC(current_module.name),
    #SIZE(current_module.name));
lg#put (out_file, current_module.name);
    WHILE current module.length > 1 DO
      di#get (library, dummy_key,
      lg#put (out_file, line(1, line_length));
current_module.length := current_module.length - 1;
    WHILEND;
    di#close (library, first#);
    lg#close (out file, first#);
  PROCEND extract;
MODEND extract from text library;
```

CYBIL I/O Reference Manual

2.0 I/O PROCEDURES 2.3 LEGIBLE FILES

2.3 <u>LEGIBLE FILES</u>

2.3.1 OPENING AND CLOSING LEGIBLE FILES

2.3.1.1 LG#OPEN - Open Legible File

Opens legible_file as local file_name.

```
{ LGZOPEN Opens legible file as local file. }

PROCEDURE [XREF] lg#open (VAR legible_file: file;
  file_name: string ( * );
  status: file_status;
  mode: file_mode;
  position: file_position);
```

2.3.1.2 F#SABF - Setup File for Automatic Buffer Flushing

Sets up **any_file** so that its CIO buffer will automatically be flushed (if necessary) whenever the program is rolled out. This facility is useful when a program issues prompts to a terminal user and then requests input, since normally to insure the prompt reaches the user before the input request, the program would write an End Of Record (causing the buffer to be flushed). On NOS this mechanism is described in the NOS Reference Manual in the section on "Program Writing Techniques".

```
{ FZSABF Sets up file for automatic buffer flushing. }
PROCEDURE [XREF] f#sabf (any file: file);
```

```
06/22/84
```

CYBIL I/O Reference Manual REV: 2

```
2.0 I/O PROCEDURES
```

2.3.1.3 LG#CODESET - Set Legible File Character Set

2.3.1.3 <u>LG#CODESET - Set Legible File Character Set</u>

Sets the external character set for $legible_file$ to codeset (default, on open, is ascii612# on NOS and is ascii# on NOS/BE).

```
{ LGZCODE Sets external character set for legible file. }
```

PROCEDURE [XREF] lg#codeset (legible_file: file;
 codeset: file encoding);

2.3.1.4 <u>LG#CLOSE - Close Legible File</u>

Closes legible file.

```
{ LGZCLOS Closes legible file. }
```

PROCEDURE [XREF] lg#close (legible_file: file;
 disposition: file_disposition);

CYBIL I/O Reference Manual REV: 2

2.0 I/O PROCEDURES

2.3.2 POSITIONING LEGIBLE FILES

2.3.2 POSITIONING LEGIBLE FILES

2.3.2.1 LG#FIRST - Position Legible File at BOI

Positions legible file at its beginning of information.

```
{ LGZFIRS Positions legible file at its Beginning Of Information. }

PROCEDURE [XREF] lg#first (legible_file: file);
```

2.3.2.2 LG#LAST - Position Legible File at EOI

Positions legible file at its end of information.

```
{ LGZLAST Positions legible file at its End Of Information. }

PROCEDURE [XREF] lg#last (legible file: file);
```

2.3.2.3 LG#TAB - Position Legible File at Column

If <code>column_number</code> is less than or equal to <code>legible_file</code>'s current column or if it is greater than 256, this procedure does nothing. Otherwise, sufficient space characters are written to <code>legible_file</code> so that the next (partial) write to <code>legible_file</code> will begin at the specified <code>column_number</code>.

```
{ LGZTAB Positions column of next partial write to legible file. }

PROCEDURE [XREF] lg#tab (legible_file: file;
column number: integer);
```

CYBIL I/O Reference Manual REV: 2

2.0 I/O PROCEDURES

2.3.3 LEGIBLE FILE STRUCTURE CREATION / DETECTION

2.3.3 LEGIBLE FILE STRUCTURE CREATION / DETECTION

2.3.3.1 LG#WEOR - Write End Of Record on Legible File

Writes an End Of Record mark on legible file.

```
{ LGZWEOR Writes an End Of Record mark on legible file. }

PROCEDURE [XREF] lg#weor (legible_file: file);
```

2.3.3.2 LG#WEOF - Write End Of File on Legible File

Writes an End Of File mark on legible file.

```
{ LGZWEOF Writes an End Of File mark on legible file. }

PROCEDURE [XREF] lg#weof (legible_file: file);
```

2.3.3.3 F#MARK - Check Structure Mark on File

Returns the "file structure mark" last encountered on any_file.

```
{ FZMARK Returns the file structure mark last encountered on file. }
PROCEDURE [XREF] f#mark (any_file: file;
   VAR mark: file_mark);
```

CYBIL I/O Reference Manual

.

2.0 I/O PROCEDURES

2.3.3.4 F#WORDS - Last Transfer Length on File

2.3.3.4 <u>F#WORDS - Last Transfer Length on File</u>

Returns the last transfer length of the last transfer to/from any file.

{ FZWORDS Returns length of last transfer to/from file. }

PROCEDURE [XREF] f#words (any_file: file; VAR last_transfer_length: integer);

CYBIL I/O Reference Manual

2.0 I/O PROCEDURES

2.3.4 READING AND WRITING LEGIBLE FILES

2.3.4 READING AND WRITING LEGIBLE FILES

Data is transferred to and from legible files in terms of lines or partial lines. Internally these (partial) lines are represented by CYBIL strings of characters. Externally (on the file) lines are represented in 6-bit display code, NOS 6/12-bit ASCII, or "8 out of 12 bit" ASCII. Thus, data transfers involving legible files imply a translation between these character sets (unlike binary and direct file transfers in which the data are not modified).

Note: that when reading from a legible file assigned to an interactive terminal, the only **file mark** possible is <u>data#</u>. Any eor# or eof# marks returned to CYBILIO by the operating system after a read from a "terminal file" are discarded by CYBILIO (eoi# is never possible from a terminal). A line (entered at a terminal) containing zero characters (i.e., the carriage return key was "hit" in the first position of the line) is returned to the CYBILIO user as an empty line.

2.3.4.1 LG#PUT - Write Line to Legible File

Writes the line string as a complete line to legible_file. If the last write to legible_file was a partial line, that line is first completed, and then the line is written.

```
{ LGZPUT Writes source string as complete line to legible file. }

PROCEDURE [XREF] lg#put (legible_file: file;
  line: string ( * ));
```

2.3.4.2 LG#PUTPART - Write Partial Line to Legible File

Writes the partial_line string to legible_file. If last_part_of_line is TRUE, then the line is completed after partial_line is written by writing an End Of Line to legible file.

```
{ LGZPUTP Writes source string as partial line to legible file. }
```

60460300 02

CYBIL I/O Reference Manual

REV: 2

```
2.0 I/O PROCEDURES
```

2.3.4.2 LG#PUTPART - Write Partial Line to Legible File

```
PROCEDURE [XREF] lg#putpart (legible_file: file;
  last_part_of_line: boolean;
  partial_line: string ( * ));
```

2.3.4.3 <u>LG#WEOL - Write End Of Line on Legible File</u>

Writes an End Of Line to legible_file. If the last write to legible_file was partial, that line is completed; otherwise an empty line results.

```
{ LGZWEOL Writes an End Of Line to legible file. }

PROCEDURE [XREF] lg#weol (legible_file: file);
```

2.3.4.4 LG#GET - Read Line from Legible File

Reads the next complete line from <code>legible_file</code> into line. The actual number of characters transferred to <code>line</code> is returned in <code>number_of_characters_read</code>. If the previous transfer was partial, a skip to the end of that line is performed prior to the transfer to <code>line</code> being done. If the line from <code>legible_file</code> is too long to fit into <code>line</code>, the line is truncated by skipping to the end of the line after the transfer is complete.

```
{ LGZGET Reads next complete line from legible file. }

PROCEDURE [XREF] lg#get (legible_file: file;
   VAR number_of_characters_read: integer;
   VAR line: string ( * ));
```

CYBIL I/O Reference Manual

REV: 2

2.0 I/O PROCEDURES

2.3.4.5 LG#GETPART - Read Partial Line from Legible File

2.3.4.5 <u>LG#GETPART - Read Partial Line from Legible File</u>

Reads the next partial line from legible_file into partial_line.
last_part_of_line will be set to TRUE if the end of the line was encountered, and set to FALSE otherwise. The actual number of characters transferred will be returned in number_of_characters_read.

{ LGZGETP Reads next partial line from legible file. }

PROCEDURE [XREF] lg#getpart (legible_file: file;
 VAR last_part_of_line: boolean;
 VAR number_of_characters_read: integer;
 VAR partial_line: string (*));

CYBIL I/O Reference Manual

REV: 2

```
2.0 I/O PROCEDURES
```

2.3.5 LEGIBLE FILE STATUS INTERROGATION

2.3.5 LEGIBLE FILE STATUS INTERROGATION

2.3.5.1 F#TERMINAL - File is a Terminal?

Returns in file_is_a_terminal TRUE if any_file is connected to a terminal, and FALSE otherwise.

```
{ FZTERMI Returns boolean if file is connected to a terminal. }

PROCEDURE [XREF] f#terminal (any_file: file;
   VAR file_is_a_terminal: boolean);
```

2.3.5.2 <u>LG#OLDCODESET - Legible File Character Set?</u>

Returns the designator for the external character set associated with $\ensuremath{\mathsf{legible}}$ file.

```
{ LGZOLDC Returns designator for ext. char. set of legible file. }

PROCEDURE [XREF] lg#oldcodeset (legible_file: file;
   VAR codeset: file encoding);
```

2.3.5.3 LG#COLNO - Legible File Column Number?

Returns the number of the column within the current line of legible_file that was last transferred to/from legible_file. Put another way, column_number is set to the number of characters so far transferred to/from the current line of legible file.

```
{ LGZCOLN Returns col. no. in line of legible file last transferred. }

PROCEDURE [XREF] lg#colno (legible_file: file;

VAR column number: integer);
```

60460300 02

CYBIL I/O Reference Manual REV: 2

2.0 I/O PROCEDURES

2.3.6 EXAMPLE - COPY COLUMN RANGE OF LEGIBLE FILE

2.3.6 EXAMPLE - COPY COLUMN RANGE OF LEGIBLE FILE

The following example illustrates the use of legible file procedures to copy one legible file to another. Only data between selected columns on the old file is written to the new file, and within those columns, trailing space characters are deleted.

```
MODULE truncate ALIAS 'zpxmtru';
{ PXIOTYP
             Contains CYBIL type declarations. }
  TYPE
    file = ^cell,
    file_status = (new#, old#),
file_mode = (input#, output#, concurrent#),
    file_encoding = (ascii64#, ascii612#, ascii#),
file_mark = (data#, eor#, eof#, eoi#),
file_position = (first#, asis#, last#, null#);
  CONST
    return# = last#;
  TYPE
    file disposition = first# .. return#;
  { i.e. (first#, asis#, return#) }
{ LGZOPEN
               Opens legible file as local file. }
  PROCEDURE [XREF] lg#open (VAR legible_file: file;
    file name: string ( * );
    status: file status;
    mode: file_mode;
    position: Tile_position);
{ LGZCLOS
            Closes legible file. }
  PROCEDURE [XREF] lq#close (legible file: file;
    disposition: file disposition);
              Reads next complete line from legible file. }
```

```
06/22/84
```

```
CYBIL I/O Reference Manual
2.0 I/O PROCEDURES
2.3.6 EXAMPLE - COPY COLUMN RANGE OF LEGIBLE FILE
  PROCEDURE [XREF] lg#get (legible_file: file;
    VAR number of characters read: integer;
    VAR line: string ( * ));
{ LGZPUT
            Writes source string as complete line to legible file. }
  PROCEDURE [XREF] lg#put (legible file: file;
    line: string ( * ));
{ LGZWEOL
             Writes an End Of Line to legible file. }
  PROCEDURE [XREF] lg#weol (legible file: file);
             Writes an End Of Record mark on legible file. }
{ LGZWEOR
  PROCEDURE [XREF] lg#weor (legible file: file);
{ LGZWEOF
             Writes an End Of File mark on legible file. }
  PROCEDURE [XREF] lg#weof (legible file: file);
            Returns the file structure mark last encountered on file. }
{ FZMARK
  PROCEDURE [XREF] f#mark (any_file: file;
    VAR mark: file mark);
  PROGRAM truncate ALIAS 'zpxptru';
    CONST
      in name = 'OLD',
      out name = 'NEW',
      leftmost_column_# = 11,
      rightmost column \# = 72;
    VAR
      in file : file,
      out_file : file,
line_ptr : ^STRING (*),
      line_length : INTEGER,
mark : file_mark;
    ALLOCATE line_ptr : [rightmost_column #];
    lg#open (in file, in name, old#, input#, first#);
    lg#open (out file, out name, new#, output#, first#);
  /main loop/
    WHILE TRUE DO
```

```
06/22/84
```

```
CYBIL I/O Reference Manual REV: 2
```

2.0 I/O PROCEDURES 2.3.6 EXAMPLE - COPY COLUMN RANGE OF LEGIBLE FILE

```
lg#get (in_file, line_length, line_ptr^);
    f#mark (in file, mark);
    CASE mark OF
    =eoi#=
      EXIT /main loop/;
    =eof#=
      lg#weof (out file);
    =eor#=
      lg#weor (out file);
    =data#=
      WHILE (line_length > leftmost_column_#) AND
        (line_ptr*(line_length) = ' ') DO
line_length := line_length - 1;
      WHILEND;
      line_length := line_length - leftmost_column_# + 1;
IF line_length > 0 THEN
        lg#put (out_file, line_ptr^(leftmost_column_#,
                                        line length));
      ELSE
        lg#weol (out file);
      IFEND;
    CASEND;
  WHILEND /main_loop/;
  lg#close (in_file, first#);
  lg#close (out_file, first#);
  FREE line_ptr;
PROCEND truncate;
```

MODEND truncate;

CYBIL I/O Reference Manual

·

2.0 I/O PROCEDURES 2.4 PRINT FILES

2.4 PRINT FILES

2.4.1 OPENING AND CLOSING PRINT FILES

2.4.1.1 PR#OPEN - Open Print File

Opens print_file as local file_name (note the lack of a file_mode parameter for this procedure, since print files can only be written).

```
{ PRZOPEN Opens print file as local file. }

PROCEDURE [XREF] pr#open (VAR print_file: file;
  file_name: string ( * );
  status: file_status;
  position: file_position);
```

2.4.1.2 PR#PGOV - Define Page Overflow Procedure

Associates with **print_file**, the procedure designated by **page_overflow_proc** which will be called whenever the page size of **print_file** is exceeded. Page size is set by **PR#LIMIT**, default is 60 lines. The procedure designated by **page_overflow_proc** should <u>not</u> be called directly by the user. If the user wishes to explicitly advance to the next page, a call to the <u>pr#page</u> procedure should be used.

If there is no user supplied page overflow procedure for a print file, then CYBILIO simply performs a page eject for the file when the page overflow condition occurs. If NIL is specified for <code>page_overflow_proc</code>, any user supplied page overflow procedure currently associated with the file is disassociated from the file.

```
{ PRZPGOV Calls procedure needed to advance file to next page. }

PROCEDURE [XREF] pr#pgov (print_file: file;
   page_overflow_proc: ^procedure (print_file: file;
   next_page_#: integer));
```

```
CYBER IMPLEMENTATION LANGUAGE
                                                           REV: 2
CYBIL I/O Reference Manual
     __________
2.0 I/O PROCEDURES
2.4.1.3 PR#CODESET - Set Print File Character Set
2.4.1.3 PR#CODESET - Set Print File Character Set
Sets the external character set for print_file to codeset (default, on open, is ascii612\# on NOS and is ascii\# on NOS/BE).
{ PRZCODE
           Sets ext. char. set for print file. }
  PROCEDURE [XREF] pr#codeset (print_file: file;
   codeset: file encoding);
2.4.1.4 PR#LIMIT - Set Print File Page Size
   Sets the page size (line limit) for print file to lines per page
(default, on open, is 60).
```

2.4.1.5 PR#SETPGNO - Set Print File Page Number

PROCEDURE [XREF] pr#limit (print_file: file;

lines_per_page: integer);

{ PRZLIMI

Sets the current page number for print file to current page number (default, on open, is 0).

Sets page size (line limit) for print file. }

```
Sets current page number for print file. }
PROCEDURE [XREF] pr#setpgno (print_file: file;
 current page number: integer);
```

CYBIL I/O Reference Manual REV: 2

2.0 I/O PROCEDURES

2.4.1.6 PR#CLOSE - Close Print File

2.4.1.6 PR#CLOSE - Close Print File

Closes print file.

{ PRZCLOS Closes print file. }

PROCEDURE [XREF] pr#close (print_file: file;
 disposition: file_disposition);

CYBIL I/O Reference Manual

2.0 I/O PROCEDURES

2.4.2 POSITIONING PRINT FILES

2.4.2 POSITIONING PRINT FILES

2.4.2.1 PR#FIRST - Position Print File at BOI

Positions print file at its beginning of information.

```
{ PRZFIRS Positions print file at its Beginning Of Information. }

PROCEDURE [XREF] pr#first (print_file: file);
```

2.4.2.2 PR#LAST - Position Print File at EOI

Positions print file at its end of information.

```
{ PRZLAST Positions print file at its End Of Information. }

PROCEDURE [XREF] pr#last (print_file: file);
```

2.4.2.3 PR#TAB - Position Print File at Column

If <code>column_number</code> is less than or equal to <code>print_file</code>'s current column or if it is greater than 136, this procedure does nothing. Otherwise, sufficient space characters are written to <code>print_file</code> so that the next (partial) write to <code>print_file</code> will begin at the specified <code>column_number</code>.

```
{ PRZTAB Positions print file at column for next partial write. }

PROCEDURE [XREF] pr#tab (print_file: file;
   column number: integer);
```

CYBIL I/O Reference Manual

KEV: Z

a a t/a programme

2.0 I/O PROCEDURES

2.4.2.4 PR#LINE - Position Print File at Line

2.4.2.4 PR#LINE - Position Print File at Line

Positions print_file at the specified line_number. This will be on the current page if line_number is greater than the current line number and less than or equal to page size; or on the next page (after invoking the page overflow mechanism) if line_number is less than or equal to the current line number. If line_number is greater than the page size, the file will be positioned at the top of the next page.

```
{ PRZLINE Positions print file at specified line. }

PROCEDURE [XREF] pr#line (print_file: file;
   line_number: integer);
```

2.4.2.5 PR#SKIP - Skip Lines on Print File

If number_of_lines = -1, the next line written to print_file will
overprint the current line. If number_of_lines + print_file's current
line number is greater than the page size, the page overflow mechanism is
invoked. Otherwise, number_of_lines empty lines will be written to
print_file.

```
{ PRZSKIP Skips lines on print file from current position. }

PROCEDURE [XREF] pr#skip (print_file: file;
number of lines: integer);
```

2.4.2.6 PR#EJECT - Position Print File at Top of Page

Positions $print_file$ at the first line (top) of the next page. This procedure should only be called by the routine that processes page overflow conditions: pr#pgov (see the section on "Print Files" under "File Types").

CYBIL I/O Reference Manual

REV: 2

2.0 I/O PROCEDURES

2.4.2.6 PR#EJECT - Position Print File at Top of Page

{ PRZEJEC Positions print file to first line (top) of next page. } PROCEDURE [XREF] pr#eject (print file: file);

2.4.2.7 PR#PAGE - Start New Page on Print File

Increments print_file's page number and calls the routine that processes page overflow conditions: pr#pgov (see the section on "Print Files" under "File Types").

{ PRZPAGE Increments print file's page number. } PROCEDURE [XREF] pr#page (print_file: file);

CYBIL I/O Reference Manual

REV: 2

2.0 I/O PROCEDURES

2.4.3 PRINT FILE STRUCTURE CREATION

2.4.3 PRINT FILE STRUCTURE CREATION

2.4.3.1 PR#WEOR - Write End Of Record on Print File

Writes an End Of Record mark on print_file.

```
{ PRZWEOR Writes an End Of Record mark on print file. }

PROCEDURE [XREF] pr#weor (print_file: file);
```

2.4.3.2 PR#WEOF - Write End Of File on Print File

Writes an End Of File mark on print file.

```
{ PRZWEOF Writes an End Of File mark on print file. }

PROCEDURE [XREF] pr#weof (print file: file);
```

CYBIL I/O Reference Manual

1111 . 2

2 2 7/2 PROGRAMME

2.0 I/O PROCEDURES

2.4.4 WRITING PRINT FILES

2.4.4 WRITING PRINT FILES

Print files are a special form of legible files used only for output. In addition to the (partial) line writes similar to those for legible files, print files also have "format" control procedures to handle page overflow processing and vertical spacing and tabbing (see the section on "Positioning Print Files" for more information).

2.4.4.1 PR#PUT - Write Line to Print File

Writes the line string as a complete line to **print_file**. If the last write to **print_file** was a partial line, that line is first completed, and then the line for **line** is written.

```
{ PRZPUT Writes source string as a complete line to print file. }

PROCEDURE [XREF] pr#put (print_file: file;
   line: string ( * ));
```

2.4.4.2 PR#PUTPART - Write Partial Line to Print File

Writes the partial_line string to print_file. If last_part_of_line is TRUE, then the line is completed after partial_line is written by writing an End Of Line to print file.

```
{ PRZPUTP Writes source string as a partial line to print file. }

PROCEDURE [XREF] pr#putpart (print_file: file;
   last_part_of_line: boolean;
   partial line: string ( * ));
```

CYBIL I/O Reference Manual

REV: 2

2.0 I/O PROCEDURES

2.4.4.3 PR#WEOL - Write End Of Line on Print File

2.4.4.3 PR#WEOL - Write End Of Line on Print File

Writes an End Of Line to **print_file**. If the last write to **print_file** was partial, that line is completed; otherwise an empty line results.

{ PRZWEOL Writes an End Of Line to print file. }

PROCEDURE [XREF] pr#weol (print_file: file);

CYBIL I/O Reference Manual

2.0 I/O PROCEDURES

2.4.5 PRINT FILE STATUS INTERROGATION

2.4.5 PRINT FILE STATUS INTERROGATION

2.4.5.1 PR#OLDCODESET - Print File Character Set?

Returns the designator for the external character set associated with print file.

```
{ PRZOLDC
             Returns designator for ext. char. set of print file. }
  PROCEDURE [XREF] pr#oldcodeset (print file: file;
   VAR codeset: file encoding);
```

2.4.5.2 PR#COLNO - Print File Column Number?

Returns the number of the column within the current line of print file that was last transferred to/from print_file. Put another way, column number is set to the number of characters so far transferred to/from the current line of **print file**.

```
{ PRZCOLN
            Returns current line col. no. of print file last transferred. }
  PROCEDURE [XREF] pr#colno (print_file: file;
   VAR column number: integer);
```

2.4.5.3 PR#LINO - Print File Line Number?

Returns the number of the current line within the current page of print_file. After any repositioning command (skip, eject, set_line_number) the line_number returned is the next line to be printed. After a print command (put, putpart, weol), the line_number is the line just printed.

Before doing any I/O, the line number is 500.

```
06/22/84
```

```
CYBIL I/O Reference Manual REV: 2
```

```
2.0 I/O PROCEDURES
```

```
2.4.5.3 PR#LINO - Print File Line Number?
```

```
{ PRZLINO Returns no. of lines within current page of print file. }

PROCEDURE [XREF] pr#lino (print_file: file;

VAR line number: integer);
```

2.4.5.4 PR#PGNO - Print File Page Number?

```
Returns the number of the current page for print_file.
```

```
{ PRZPGNO Returns number of current page for print file. }

PROCEDURE [XREF] pr#pgno (print_file: file;
   VAR page_number: integer);
```

2.4.5.5 PR#OLDLIMIT - Print File Page Size?

```
Returns print file's page size (line limit).
```

```
{ PRZOLDL Returns print file's page size (line limit). }
PROCEDURE [XREF] pr#oldlimit (print_file: file;
    VAR lines_per_page: integer);
```

```
CYBIL I/O Reference Manual REV: 2
2.0 I/O PROCEDURES
2.4.6 EXAMPLE - LIST LEGIBLE FILE
```

2.4.6 EXAMPLE - LIST LEGIBLE FILE

The following example illustrates the use of print file procedures (and legible file procedures). Note particularly the page overflow processing procedure.

```
MODULE list ALIAS 'zpxmlis';
{ PXIOTYP
             Contains CYBIL type declarations. }
  TYPE
    file = ^cell,
    file_status = (new#, old#),
file_mode = (input#, output#, concurrent#)
    file_encoding = (ascii64#, ascii612#, ascii#),
    file_mark = (data#, eor#, eof#, eoi#),
file_position = (first#, asis#, last#, null#);
  CONST
    return# = last#;
  TYPE
    file disposition = first# .. return#;
  { i.e. (first#, asis#, return#) }
{ LGZOPEN
              Opens legible file as local file. }
  PROCEDURE [XREF] lg#open (VAR legible_file: file;
    file_name: string ( * );
    status: file_status;
    mode: file_mode;
position: file_position);
{ LGZCLOS
              Closes legible file. }
  PROCEDURE [XREF] lg#close (legible_file: file;
    disposition: file disposition);
{ LGZGETP
              Reads next partial line from legible file. }
  PROCEDURE [XREF] lg#getpart (legible_file: file;
```

```
06/22/84
                                                            REV: 2
CYBIL I/O Reference Manual
______
2.0 I/O PROCEDURES
2.4.6 EXAMPLE - LIST LEGIBLE FILE
   VAR last_part_of_line: boolean;
   VAR number_of_characters_read: integer;
   VAR partial line: string ( * ));
{ FZMARK
           Returns the file structure mark last encountered on file. }
 PROCEDURE [XREF] f#mark (any file: file;
   VAR mark: file mark);
            Opens print file as local file. }
{ PRZOPEN
 PROCEDURE [XREF] pr#open (VAR print file: file;
   file_name: string ( * );
   status: file status;
   position: file position);
{ PRZPGOV
            Calls procedure needed to advance file to next page. }
 PROCEDURE [XREF] pr#pgov (print file: file;
   page_overflow_proc: ^procedure (print_file: file;
next_page_#: integer));
{ PRZCLOS
          Closes print file. }
 PROCEDURE [XREF] pr#close (print_file: file;
   disposition: file_disposition);
{ PRZEJEC
            Positions print file to first line (top) of next page. }
 PROCEDURE [XREF] pr#eject (print file: file);
{ PRZSKIP
            Skips lines on print file from current position. }
 PROCEDURE [XREF] pr#skip (print_file: file;
   number_of_lines: integer);
{ PRZLINE
            Positions print file at specified line. }
 PROCEDURE [XREF] pr#line (print file: file;
   line number: integer);
{ PRZLIMI
            Sets page size (line limit) for print file. }
 PROCEDURE [XREF] pr#limit (print file: file;
   lines per page: integer);
            Returns print file's page size (line limit). }
{ PRZOLDL
```

```
06/22/84
```

```
CYBIL I/O Reference Manual
______
2.0 I/O PROCEDURES
2.4.6 EXAMPLE - LIST LEGIBLE FILE
 PROCEDURE [XREF] pr#oldlimit (print file: file;
   VAR lines per page: integer);
{ PRZPGNO
            Returns number of current page for print file. }
 PROCEDURE [XREF] pr#pqno (print file: file;
   VAR page number: integer);
{ PRZTAB
           Positions print file at column for next partial write. }
 PROCEDURE [XREF] pr#tab (print file: file;
   column_number: integer);
{ PRZPUTP
            Writes source string as a partial line to print file. }
 PROCEDURE [XREF] pr#putpart (print_file: file;
   last_part_of_line: boolean;
partial_line: string ( * ));
{ PRZWEOL
            Writes an End Of Line to print file. }
 PROCEDURE [XREF] pr#weol (print file: file);
 CONST
   in_name = 'LEGFILE';
 VAR
   file # : INTEGER := 1,
   record # : INTEGER := 1;
 PROCEDURE page_overflow_handler
     (f:file;
          next_page_# : INTEGER);
   VAR
     conv holder : STRING (10),
     conv_length : INTEGER,
     old page size : INTEGER;
   IF next_page_# > 1 THEN
     pr#oldlimit (f, old page size);
     pr#limit (f, old_page_size + 2);
     pr#line (f, old_page_size + 2);
pr#tab (f, 70);
```

```
c / 2 2 / 2 .
```

```
06/22/84
                                                                        REV: 2
CYBIL I/O Reference Manual
______
2.0 I/O PROCEDURES
2.4.6 EXAMPLE - LIST LEGIBLE FILE
      pr#putpart (f, FALSE, 'PAGE ');
      STRINGREP (conv_holder, conv_length, next_page_# - 1);
      pr#putpart (f, TRUE, conv holder(1, conv length));
      pr#limit (f, old page size);
    IFEND;
    pr#eject (f);
    pr#putpart (f, FALSE, 'LISTING OF ');
    pr#putpart (f, FALSE, in_name);
    pr#tab (f, 50);
pr#putpart (f, FALSE, 'FILE ');
    STRINGREP (conv holder, conv_length, file_#);
    pr#putpart (f, FALSE, conv_holder(1, conv_length));
pr#putpart (f, FALSE, ', RECORD ');
STRINGREP (conv_holder, conv_length, record_#);
pr#putpart (f, TRUE, conv_holder(1, conv_length));
    pr#skip (f, 2);
  PROCEND page overflow handler;
  PROGRAM list ALIAS 'zpxplis';
    CONST
      out name = 'OUTPUT';
      in_file : file,
      out file : file,
      original_page_size : INTEGER,
      page # : INTEGER,
      line : STRING (80),
line_length : INTEGER,
      eol : BOOLEAN,
      mark : file mark;
    lg#open (in_file, in_name, old#, input#, first#);
    pr#open (out_file, out_name, new#, asis#);
pr#pgov (out_file, ^page_overflow_handler);
    pr#oldlimit (out_file, original_page_size);
    pr#limit (out_file, original_page size - 2);
  /main loop/
    WHILE TRUE DO
       lg#getpart (in_file, eol, line length, line);
       f#mark (in file, mark);
      CASE mark \overline{\text{O}}\text{F}
       =eoi#=
         pr#limit (out_file, original_page_size);
```

```
CYBIL I/O Reference Manual REV: 2
```

2.0 I/O PROCEDURES 2.4.6 EXAMPLE - LIST LEGIBLE FILE

MODEND list;

```
pr#line (out_file, original_page_size);
pr#tab (out_file, 70);
      pr#putpart (out file, FALSE, 'PAGE ');
      pr#pgno (out_file, page_#);
      STRINGREP (line, line_length, page_#);
pr#putpart (out_file, TRUE, line(1, line_length));
      EXIT /main loop7;
    =eof#=
      file # := file_# + 1;
      record_# := 1;
      pr#line (out_file, original_page_size - 2);
      pr#weol (out_file);
    =eor#=
      record # := record # + 1;
      pr#line (out_file, original_page_size - 2);
      pr#weol (out_file);
    =data#=
      IF line length > 0 THEN
        pr#putpart (out file, eol, line(1, line length));
        pr#weol (out file);
      IFEND;
    CASEND;
  WHILEND /main_loop/;
  lg#close (in_file, first#);
pr#close (out_file, asis#);
PROCEND list;
```

CYBIL I/O Reference Manual

3.0 CYBILIO ERROR MESSAGES

3.0 CYBILIO ERROR MESSAGES

This section describes the error messages that may be received as a result of improper use of CYBILIO. If a condition described by one of these messages arises:

- the I/O error message will be sent to the dayfile
- the message <u>- INTERNAL ERROR IN prognam</u> will be sent to the dayfile (where **prognam** is the name of the program as extracted from the job communication area)
- the program is aborted.

In the message prototypes that follow <u>filenam</u> will be replaced by the name of the file in question when the message appears in the dayfile. The reason that some of the messages do not have the file name in them is that, in those conditions, the file name is not known.

-IO ERR- NO MEM TO OPEN FILE filenam

This message means that there was insufficient space to allocate the descriptor and/or cio buffer for the file.

-IO ERR- ILLEGAL FILE NAME

This message means that an attempt was made to open a file with a $\$ name that did not consist of from 1 to 7 letters and/or digits.

-IO ERR- ILLEGAL OPEN REQ filenam

This message means that an invalid combination of parameters was given to an open procedure (e.g., "new#, input#" is illegal).

-IO ERR- FILE NOT OPEN

This message indicates that an undefined variable of type $\underline{\text{file}}$ was 60460300 02

CYBIL I/O Reference Manual

REV: 2

3.0 CYBILIO ERROR MESSAGES

passed to a CYBILIO procedure other than one of the open procedures.

-IO ERR- ILLEGAL INPUT REQ filenam

This message means that an attempt was made to read from a file that was opened only for output.

-IO ERR- ILLEGAL OUTPUT REQ filenam

This message means that an attempt was made to write to a file that was opened only for input.

-IO ERR- KEY BEYOND E-O-I filenam

This message indicates that an attempt was made to perform a direct file operation with a key that was outside the bounds of the file (i.e., the key did not specify a "random address" that is in the file).

-IO ERR- ILLEGAL LINE NUM filenam

This message means that the pr#line procedure was passed a line number less than 1.

-IO ERR- ILLEGAL SKIP COUNT filenam

This message indicates that the pr#skip procedure was passed a skip count less than -1.

CYBIL I/O Reference Manual REV: 2

Table of Contents

1.	0 INTRODUCTION	1-1
1.	1 APPLICABLE DOCUMENTS	1-1
1	2 FILE TYPES	1-2
	1.2.1 BINARY FILES	1-2
	1.2.2 DIRECT FILES	1-2
	1.2.2 DIRECT FILES	
	1.2.3 LEGIBLE FILES	1-2
	1.2.4 PRINT FILES	1-3
1.	3 CYBILIO DATA TYPES	1-4
1.	4 USING CYBILIO	1-6
	1.4.1 SOURCE CODE INTERFACE TO CYBILIO ON NOS	1-6
	1.4.2 SOURCE CODE INTERFACE TO CYBILIO ON NOS/BE	1-6
	1.4.3 OBJECT CODE INTERFACE TO CYBILIO	
		1-6
	1.4.4 NAMING CONVENTIONS	1-6
	1.4.5 FILE VARIABLE USAGE	1-7
	1.4.6 FILE NAMES	1-7
	1.4.7 FILE STRUCTURE CREATION / DETECTION	1-8
	1 4 9 CTO DIFFERD CITE CONTROL	1-8
	1.4.8 CIO BUFFER SIZE CONTROL	
	1.4.9 LONG STRING OF BLANK (SPACE) CHARACTERS	1-8
2.	0 I/O PROCEDURES	2-1
2.	1 BINARY FILES	2-1
	2.1.1 OPENING AND CLOSING BINARY FILES	2-1
	2.1.1.1 BI#OPEN - Open Binary File	2-1
	2.1.1.1 BI#OFEN - Open Binary File	2-1
	2.1.1.2 BI#CLOSE - Close Binary File	
	2.1.2 POSITIONING BINARY FILES	2-3
	2.1.2.1 BI#FIRST - Position Binary File at BOI	2-3
	2.1.2.2 BI#LAST - Position Binary File at EOI	2-3
	2.1.3 BINARY FILE STRUCTURE CREATION / DETECTION	2-4
	2.1.3.1 BI#WEOR - Write End Of Record on Binary File	2-4
	2.1.3.2 BI#WEOF - Write End Of File on Binary File	2-4
	2.1.3.2 BI#WEOF - WITCHE BIRD OF FITE OIL BIRDLY FITE	
	2.1.3.3 F#MARK - Check Structure Mark on File	2 - 4
	2.1.3.4 F#WORDS - Last Transfer Length on File	2-5
	2.1.4 READING AND WRITING BINARY FILES	2-6
	2.1.4.1 BI#PUT - Write to Binary File	2-6
	2.1.4.2 BI#GET - Read from Binary File	2-6
	2.1.5 EXAMPLE - COPY BINARY FILE	2-7
2	2 DIRECT FILES	
۷.	Z DIRECT FILES	2-10
	2.2.1 OPENING AND CLOSING DIRECT FILES	2-10
	2.2.1.1 DI#OPEN - Open Direct File	2-10
	2.2.1.2 DI#CLOSE - Close Direct File	2-10
	2.2.2 POSITIONING DIRECT FILES	2-11
	2.2.2.1 DI#FIRST - Position Direct File at BOI	2-11
	2.2.2.2 DI#LAST - Position Direct FIle at EOI	2-11
	2.2.2.3 DI#LOCATE - Position Direct File via Key	2-11
	2.2.3 DIRECT FILE STRUCTURE CREATION / DETECTION	2-12
	2.2.3.1 DI#WEOR - Write End Of Record on Direct File	2-12
	2.2.3.2 DI#WEOF - Write End Of File on Direct File	2-12
	2 2 3 3 F#MARK - Check Structure Mark on File	2-12

60460300 02

<u> </u>				06/22/84		
C٦	ľΒΙ	IL I/O Reference Manual	REV:			
,						
		2.2.3.4 F#WORDS - Last Transfer Length on File				
	2.	.2.4 READING AND WRITING DIRECT FILES		2-14		
		2.2.4.1 DI#PUT - Sequential Write to Direct File		2-14		
		2.2.4.2 DI#PUTDIR - Random Write to Direct File		2-14		
		2.2.4.3 DI#GET - Sequential Read from Direct File		2-15		
		2.2.4.4 DI#GETDIR - Random Read from Direct File		2-15		
	2.	.2.5 DIRECT FILE STATUS INTERROGATION		2-16		
		2.2.5.1 DI#LENGTH - Direct File Length?		2-16		
		2.2.5.2 DI#KEY - Direct File Current Position?		2-16		
	2.	2.6 EXAMPLES OF DIRECT FILE USAGE		2-17		
		2.2.6.1 Create Text Library		2-17		
		2.2.6.2 Extract from Text Library		2-21		
2.	. 3	LEGIBLE FILES		2-25		
	2.	LEGIBLE FILES		2-25		
		2.3.1.1 LG#OPEN - Open Legible File		2-25		
		2.3.1.2 F#SABF - Setup File for Automatic Buffer Flushing		2-25		
		2.3.1.3 LG#CODESET - Set Legible File Character Set		2-26		
		2.3.1.4 LG#CLOSE - Close Legible File		2-26		
	2.	3.2 POSITIONING LEGIBLE FILES		2-27		
		2.3.2.1 LG#FIRST - Position Legible File at BOI		2-27		
		2.3.2.2 LG#LAST - Position Legible File at EOI		2-27		
		2.3.2.3 LG#TAB - Position Legible File at Column		2-27		
	2.	.3.3 LEGIBLE FILE STRUCTURE CREATION / DETECTION		2-28		
		2.3.3.1 LG#WEOR - Write End Of Record on Legible File				
		2.3.3.2 LG#WEOF - Write End Of File on Legible File				
		2.3.3.3 F#MARK - Check Structure Mark on File				
		2.3.3.4 F#WORDS - Last Transfer Length on File				
	2.	3.4 READING AND WRITING LEGIBLE FILES		2-30		
		2.3.4.1 LG#PUT - Write Line to Legible File		2-30		
		2.3.4.2 LG#PUTPART - Write Partial Line to Legible File		2-30		
		2.3.4.3 LG#WEOL - Write End Of Line on Legible File				
		2.3.4.4 LG#GET - Read Line from Legible File		2-31		
		2.3.4.5 LG#GETPART - Read Partial Line from Legible File		2-32		
	2.	3.5 LEGIBLE FILE STATUS INTERROGATION		2-33		
		2.3.5.1 F#TERMINAL - File is a Terminal?		2-33		
		2.3.5.2 LG#OLDCODESET - Legible File Character Set?		2-33		
		2.3.5.3 LG#COLNO - Legible File Column Number?		2-33		
	2.	2.3.5.3 LG#COLNO - Legible File Column Number?		2-34		
2.	. 4	PRINT FILES		2-37		
	2.	4.1 OPENING AND CLOSING PRINT FILES		2-37		
		2.4.1.1 PR#OPEN - Open Print File		2-37		
		2.4.1.2 PR#PGOV - Define Page Overflow Procedure		2-37		
		2.4.1.3 PR#CODESET - Set Print File Character Set		2-38		
		2.4.1.4 PR#LIMIT - Set Print File Page Size		2-38		
		2.4.1.5 PR#SETPGNO - Set Print File Page Number		2-38		
		2.4.1.6 PR#CLOSE - Close Print File		2-39		
	2.	4.2 POSITIONING PRINT FILES		2-40		
		2.4.2.1 PR#FIRST - Position Print File at BOI		2-40		
		2.4.2.2 PR#LAST - Position Print File at EOI		2-40		
		2.4.2.3 PR#TAB - Position Print File at Column		2-40		
		2.4.2.4 PR#LINE - Position Print File at Line		2-41		

CYBER IMPLEMENTATION LANGUAGE

0.5.4	00/04
06/ CYBIL I/O Reference Manual REV: 2	22/84
2.4.2.6 PR#EJECT - Position Print File at Top of Page 2.4.2.7 PR#PAGE - Start New Page on Print File	2-41 2-41 2-42 2-43
2.4.3.1 PR#WEOR - Write End Of Record on Print File	2-43
2.4.4 WRITING PRINT FILES	2-43 2-44
	2-44 2-44
2.4.4.3 PR#WEOL - Write End Of Line on Print File	2-45 2-46
2.4.5.1 PR#OLDCODESET - Print File Character Set?	2-46
2.4.5.3 PR#LINO - Print File Line Number?	2-46 2-46
	2-47 2-47
	2-48
3.0 CYBILIO ERROR MESSAGES	3-1