

# How to move HP SIM SQL 2005 database

From local to remote



Introduction.....	2
Moving HP SIM SQL 2005 database from a local to a remote machine.....	2
Machine 2 HP SIM Installation Directory.....	13
For more information.....	14
Call to action .....	14


# Introduction

This document details how to move an HP SIM SQL 2005 database from a local machine to a remote machine.

## Moving HP SIM SQL 2005 database from a local to a remote machine

1. Stop and disable the HP SIM service running on Machine 1.
2. Open SQL Server Management Studio in Machine 1  
(Programs → Microsoft SQL server 2005 → SQL Server Management Studio)


Figure 1. SQL Server Management Studio



3. With default settings in the Connect to Server window, click **“Connect”**.
4. Write down the database name. For example, **Insight\_v50\_XXXXXXXXXX**.
5. Create a new SQL Database on the target machine (Machine 2).
  - a) Open SQL Server Management Studio in Machine 2.  
(Programs → Microsoft SQL server 2005 → SQL Server Management Studio)
  - b) Right click **Database**.


c) Enter the name of the database you wrote down in step 4, and then click **OK**.

Figure 2. **Export Data**




6. In Machine 1, right-click the name of the Insight database. For example, **Insight\_v50\_xxxxxxxxx**.
7. Select **Tasks**→**Export data**.

Figure 3. Import and Export Wizard




8. In the **Welcome to SQL Server Import and Export Wizard** window, click **Next**.

Figure 4. Choose a Data Source




9. In the **Choose a Data Source** window, use the default settings **Windows Authentication** or choose the authentication method you used for your database, and then click **Next**.

Figure 5. Choose a Destination




10. In the **Choose a Destination** window, select the Machine 2 database server from the list. Select the database created in Step 5 from the **Database** list at the bottom of the window.

Figure 6. Specify Table Copy or Query




11. In the **Specify Table Copy or Query** dialog window, select the **Copy data from one or more tables or views**, and then click **Next**.

Figure 7. Select Source Tables and Views




12. In the **Select Source Tables and Views** window, select the **All** box and then click **Next**. A pop-up window appears.

Figure 8. Pop-up Window




13. Click **Yes**.

Figure 9. Save and Execute Package




14. In the **Save and Execute Package** window, keep the default setting (**Execute immediately**) and then click **Next**.

Figure 10. Complete the Wizard



15. In the **Complete the Wizard** window, click **Finish**.

Figure 11. Performing Operation



16. Once all tasks have completed successfully, stop and disable the SQL Service.

Figure 12. Source database before migration





Figure 12. Source database after migration



## Machine 2 HP SIM Installation Directory

1. Create a backup of DATABASE.PROPS and DATABASE.ADMIN files located in `<installation directory>\HP\System Insight Manager\config`.
2. Some settings for the new database changes in HP SIM need to be modified in DATABASE.PROPS and DATABASE.ADMIN files. Update these files with the following information and save the files.
  - Change the `hp.Database.hostName` to `machine 2`
  - Change the `hp.Database.instance name` to `machine 2\\Database_server name`
  - Change the `hp.Database.username` to `machine 2\\username`

Start the HP SIM service.

## For more information

For more information on HP SIM, visit the HP website (<http://www.hp.com/go/hpsim>).

## Call to action

Please send comments about this paper to [TechCom@HP.com](mailto:TechCom@HP.com).

© 2008 Hewlett-Packard Development Company, L.P. The information contained herein is subject to change without notice. The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical or editorial errors or omissions contained herein.

Microsoft and Windows are U.S. registered trademarks of Microsoft Corporation.

492087-001, May 2008

