

# **ADVANCED COMPUTER PROGRAMMING**

**A Case Study of a Classroom Assembly Program**

F. J. Corbató

J. W. Poduska

J. H. Saltzer

**The M.I.T. Press**

Massachusetts Institute of Technology  
Cambridge, Massachusetts, 1963



Copyright © 1963  
by  
The Massachusetts Institute of Technology

All Rights Reserved

Library of Congress Catalog Card Number: 63-20529

Printed in the United States of America

## PREFACE

The present book is a case study of an assembler-compiler program. It is intended to be an advanced programming text for college students, system programmer trainees, and anyone trying to acquire a general understanding of system programming techniques. We feel that laboratory exercise is an important vehicle for teaching the techniques discussed in this volume. Therefore, the translator program example used must be written in an existing language of an existing computer. We consequently have chosen the FAP language of the IBM 7090 computer to describe the translator program. Other reasons for this particular choice are given in Chapter 1. Any loss of generality is partially offset by the fact that the 7090 is currently the most widely used large-scale computer in the world and one to which many colleges and universities have access.

The motivation for the present work began with the large gap between the usual beginning digital computer programming course and the sophisticated system programming techniques of interest in programming research and development. It was felt that too many students were uncritically using the existing programming systems and were overawed by the apparent complexities in such programs as the original FØRTRAN compiler.

In order to serve as an introduction to system programming and to convince the student that the principles of translators are relatively few and basically simple, a Classroom Assembly Program named CAP was written. It was first used in November 1960, in the M.I.T. course 6.251, Digital Computer Programming Systems. Since then, an execution monitor program has been added for the convenience of both students and instructors.

Course 6.251, where CAP has been used, is a one-semester introductory course of 12 units (3 contact hours per week, 9 hours preparation.) The course begins with study of an algebraic language such as FØRTRAN or MAD. The next section covers a machine language such as FAP. The third section is devoted to the study of the CAP assembler-compiler. During the semester, the course attempts to present most important contemporary ideas about computer programming. Many of these ideas are then illustrated in the CAP exercise.

Specifically, CAP has been used as follows: Students after studying the translator have been expected to make specified improvements and changes to it, using 6 to 8 computer runs for debugging purposes. (More ambitiously, the students could have written CAP from the specifications, but insufficient computer access prevented this for even the better students.)

For each of the eight semesters that CAP has been taught, the student enrollment, which has been gradually increasing, has been a cross section of the more than twenty departments at M.I.T. Thus we conclude that the average student is able to grasp and enjoy the basic principles of a translator program when it is appropriately presented.

The reader is assumed to be able to program in the FAP machine language sufficiently well to know how to look up features of the FAP assembler or of the 7090 computer in the

IBM published reference manuals.<sup>\*</sup><sup>†</sup> He is assumed also to be acquainted with the Binary Symbolic Subroutine (BSS) linkage and relocation used in the IBM FØRTRAN Monitor System (described in the FAP Reference Manual).<sup>\*</sup>

The book is organized into two major divisions, the description of CAP (five chapters) and the appendices containing listings of the CAP assembler. The compiler part of the program is considered to be advanced material, and the text advises the beginning reader which parts may be safely skipped over.

The appendices include listings of both the assembler-compiler program and of the execution monitor program. The listing of the assembler-compiler is essential to an understanding of the text. The execution monitor listing, while not so important, is included for two reasons. First, an advanced student may make the execution monitor a further case study in advanced programming techniques. Second, it is included for completeness, for the instructor who may wish to adapt it to his needs. It should be noted that the execution monitor program does make use of a few specific features of the current M.I.T. FØRTRAN Monitor System and 7090 computer.

Acknowledgment should be given to the efforts of the many teaching assistants who have labored to make the use of CAP effective. Particular mention is made of Neil Haller for his work on the early stages of CAP and introducing the first version of the execution monitor program, and of Neil Barta for his preliminary description of the UPDATE feature of FAP, from which a major part of Chapter 5 is adapted. We also are especially appreciative of the useful comments on the present manuscript made by Neil Barta and Thomas Hastings.

The programs described in this book were developed at the M.I.T. Computation Center, Cambridge, Massachusetts.

Cambridge, Mass.  
May, 1963

F. J. Corbató  
J. W. Poduska  
J. H. Saltzer

---

<sup>\*</sup> Reference Manual, FØRTRAN Assembly Program (FAP), IBM Publication C28-6235 (September, 1962).

<sup>†</sup> Reference Manual, IBM 7090 Data Processing System, IBM Publication A22-6528-4 (March, 1962).

## CONTENTS

<u>Chapter</u>		<u>Page</u>
1. INTRODUCTION		1
2. CAP USER'S REFERENCE MANUAL		3
2.1 The CAP Language		3
2.2 Card Format		3
Symbolic Location Field		3
Operation Field		4
Variable Field		4
Sequence Number Field		4
2.3 Pseudo-Operations		4
2.4 Use of CAP		5
2.5 Output of CAP		5
2.6 Restrictions and Error Indications		6
3. THE CAP ASSEMBLER		7
3.1 How Does an Assembler Work?		7
3.2 Pass One, Symbolic Definitions		8
3.3 The Collation Tape		11
3.4 Pass Two, Symbolic Evaluation		11
3.5 VAREVL, Evaluation of the Symbolic Variable Field		12
How EVAL is Called		16
3.6 Subprogram Calling Sequences and Definitions		17
Primary Subroutines		17
Input and Output Subroutines		18
Symbol Table Subroutines		19
Utility Subroutines		20
4. THE COMPILER OF CØMP PSEUDO-OPERATIONS		22
4.1 Why A Compiler?		22
4.2 What Does a Compiler Do?		22
4.3 Relation of CØMP to CAP		23
4.4 Precedence		23
4.5 The Spread Field; CØMPØP		23
4.6 Compilation of Individual Instructions		28
4.7 Compilation of Simple Expressions; EXPR		28
4.8 Temporary Storage and Subroutine GNSTØ		31
4.9 The Compilation of Terms; TERM		31
4.10 Review		33
4.11 Calling Sequence of Compiler Subroutines		34
5. CAP AS A LABORATORY EXERCISE		36
5.1 The CAP Laboratory		36
Extent of Laboratory Assignment		36

	How CAP is Modified	37
5.2	UPDATE	37
	The Use of UPDATE	37
	The UPDATE Pseudo-Operation	38
	Adding and Replacing Cards	38
	Deleting Cards from Programs on the UPDATE Input Tape	38
	The Necessary END Card	39
	Bypassing Assembly of Subprograms	39
5.3	How CAP Is Tested	42
5.4	Tactics for Modifying CAP	44
5.5	The Instructor's Point of View	44
	The Execution Monitor	44
	Miscellaneous Details About the Laboratory	45
	Making an UPDATE Input Tape	45
Appendix A	Listing of the Classroom Assembly Program	47
	Index to Appendix A	47
Appendix B	Programs to Allow Use of CAP in the Laboratory	103
	Index to Appendix B	103
Appendix C	Suggested Additions to CAP	167
C.1	Symbols	167
C.2	Operation Field	167
C.3	Variable Field	168
C.4	Assembly Listing	168
C.5	Compiler	169

## Chapter 1

### INTRODUCTION

In an age of increasing complexity, the reader may reasonably ask why he should want to learn the innermost structure of a digital computer programming system. For the day of the renaissance man is indeed past; the intricacies of present-day knowledge as well as the limitation on time for comprehension, of necessity, allow a person to be a specialist in but a limited number of areas. The answers will vary, but it is inescapable that digital computers have already during their short presence become an immensely important device in modern society. As for the future implications, the only issue of debate is whether or not computers are bringing a second industrial revolution as the steam engine heralded the first. Examples of the penetration of computers into our daily activities abound; to name but a few: banking, payroll processing, production and inventory control, income tax processing, satellite orbit computation and tracking, numerically controlled machine tools, airline reservation systems, and military defense communication networks.

Because digital computers have become important, it is inevitable that the accompanying system programs will grow in importance too. For computers reach a high level of effectiveness only when the programming systems allow the ultimate user of the system to program directly—albeit often unknowingly by that name—and thereby avoid intermediary programmers. The development of these direct usage languages is presently limited by the ease and rapidity that suitable translation programs can be written. These translation programs, are variously named problem oriented language processors, compilers, or assembly programs, depending on the language level at which they meet the user. Today, more and more, a computer is incomplete without an accompanying programming system of considerable sophistication.

Moreover, computer systems are still rapidly evolving in many directions: The detailed circuit technology is still making great strides, the logical design is changing to include multiconsoles and multiprocessors, and the programming systems are being enlarged to include larger roles such as the time-shared operation of the computer. It is important in this highly fluid state of affairs that others in addition to the system programming specialists have an understanding of programming systems. What is needed for the optimum use of computers in the future is that responsible individuals within computer-affected organizations understand the problems and general techniques of programming systems to the same extent that the problems and techniques of computer hardware are now understood. For without knowledgeable and critical guidance there will be not only many costly abuses of computers but there will be little vision and few ideas for new computer applications.

To give the reader insight into contemporary programming systems, the following chapters will present a case study of the inner structure of a combination assembler-compiler program. The program is called CAP, an acronym for Classroom Assembly Program, and it contains many of the typical features of present-day translators. The case study technique will prove helpful since there are many interrelated factors to consider and

discuss. As well as acquiring an inner knowledge of a translator, the reader of CAP will acquire three additional benefits, namely:

1. The study of detailed programming techniques.
2. How to read and study a large program.
3. How to organize a large program.

For several reasons the CAP program has been written in the FAP symbolic machine language of the IBM 7090 computer. A machine language representation has been specifically chosen because of its concreteness and lack of ambiguity for the reader. This reason is especially pertinent when one considers that one of the principal objectives of the study of CAP is to remove the mystery of system programming and to establish a feet-on-the-ground attitude in the reader. Finally, the FAP language, rather than SØS, for example, has been used in order to have its powerful subprogram feature which allows separate translation and rigid independence of program segments—a feature which greatly assists the initial understanding of a large program.

CAP is weaker than the usual translators, such as FAP, in that it has only subsets and examples of various special features and does not have the machinery for separately translatable subprograms. CAP differs from FAP in style, too, in that it is more elegantly written (that is, in terms of simplicity, brevity, and clarity) and highly organized with many subprograms. The CAP style is in contrast to that of many translator programs in active use where extreme short-cuts have been used in the interest of minimizing operating speed. (Often the short-cuts used are analogous to those for reducing the cost of commercial television receiver and frequently shortsighted from a maintenance point of view.) The basic techniques used in translators remain the same, however, so that CAP is a valid program from which to learn. One feature of CAP that merits comment is that although intermediate tapes are simulated, the program fits entirely in core memory and is independent of intermediate storage devices. Present-day translation programs have frequently overlooked the speed advantages of remaining entirely in core memory particularly while translating short subprograms which should be the major use when a translator allowing subprograms is utilized.

Finally, before proceeding with the remaining chapters, discussion is in order on how to study CAP. Past experience with many students indicates that the following advice is useful:

1. Obtain an understanding of what CAP does from the point of view of a user.
2. Determine the specifications of CAP as a program.
3. Determine the specifications of subroutines PASS1, and PASS2.
4. Starting in PASS1, study the specifications of the successive programs in the hierarchy of subprogram usage. (Omit the compiler.)
5. Starting at the top of the hierarchy, study how each subprogram meets its specifications. Review steps 2 to 4 sufficiently often that you are always sure of what a program is supposed to do before considering how it does it.
6. Remember that all subprograms can only communicate by means of their calling sequences because they are separately translated.
7. When studying, it is a great advantage to know that a program has been debugged. Nevertheless, there will always be sections of program which appear not to work correctly. After spending a reasonable amount of time, if no progress is made, avoid getting bogged down by jotting down on a pad the uncertain point for later discussion with others.
8. The compiler can be studied easily after the basic CAP is understood.
9. The advanced student can improve his program analysis abilities, by studying the execution monitor program, although it is given largely for reference purposes.

## Chapter 2

### CAP USER'S REFERENCE MANUAL

#### 2.1 The CAP Language

Before we begin to study how the CAP assembly program works, we should pause to determine exactly what job it is intended to do. We can perhaps get the best picture of this job if we examine the user's reference manual for the CAP language. This reference manual is the subject of the present chapter. The brevity of the reference manual is at once an indication of the simplicity of the CAP language and of the assembly program itself.

#### 2.2 Card Format

CAP instructions are typed one to a card as shown in Figure 2.1. Columns 1 to 6 are known as the symbolic location field and may contain a symbol or blanks. Columns 7 and 12 are always blank, leaving room for a three or four letter operation code in the operation field, columns 8 to 11. The variable field begins in column 13 and terminates at the




Figure 2.1. Format of CAP symbolic cards.

first blank column, or column 73. An arbitrary comment may follow this first blank column. This comment will be ignored by the assembly program as will the sequence number field, columns 73 to 80.

#### Symbolic Location Field

This field may contain a symbol, a string of one to six characters, at least one of which is nonnumeric, and none of which are the following eleven special characters:

+      -      \*      /      ,      =      .      '      (      )      \$

A symbol may be defined only by its appearance in the symbolic location field of some instruction card.

### Operation Field

This field may contain a mnemonic associated either with one of thirty-four 7090 instructions or one of five pseudo-operations. The allowed 7090 instruction mnemonics are

ACL	ANA	CAL	CHS	CLA	CLS	CØM	FAD
FDP	FMP	FSB	LAC	LAS	LBT	LDQ	LGL
LGR	LXA	ØRA	PBT	RQL	SLW	STØ	STQ
SXA	TIX	TMI	TPL	TQP	TRA	TSX	TZE
XCA	XCL						

The instructions LAC, LXA, SXA, and TSX are assembled with a tag of 4. The instruction TIX is assembled with a tag of 4 and a decrement of 1.

The allowed pseudo-operation mnemonics are

REM      INT      ØCTL      CØMP      END

The effect of these pseudo-operations is explained in a later section.

### Variable Field (Operations)

The variable field specifies the address of an operation. It may contain an expression consisting of a string of symbols and decimal integers connected by the break and grouping characters:

+      -      \*      (      )

All multiplications must be made explicit by the use of the asterisk even if one of the operands is a parenthetical expression. The variable field is evaluated in signed 35 bit integer arithmetic. If the result is negative, it is two's complemented before the final step in which the answer is taken modulo  $2^{15}$ . The result is combined with the specified operation code by a logical "OR".

### Sequence Number Field

Columns 73 to 80 may be used for labeling and sequence numbering and are ignored by the CAP assembly program.

### 2.3 Pseudo-Operations

**REM** The REM pseudo-operation is used to introduce an arbitrary remark into the assembly listing. Card columns 1 to 80 will be printed and the card will be otherwise ignored by the assembler. If a symbol appears in columns 1 to 6, it will be ignored.

**INT** INT is a data-generating pseudo-operation. The variable field of the INT pseudo-op consists of signed decimal integers separated by commas and terminating at the first blank column. For each decimal integer, a word is assembled with the decimal integer

inserted in the left half of the word. A comma with no integer following it will cause a word of all zeros to be assembled. A decimal integer may be preceded by a minus sign and must be of absolute value less than  $2^{17}$ . A symbol, if any, appearing in the symbolic location field will be defined to be the location of the first integer assembled. Succeeding integers will be placed in succeeding locations in core storage.

**ØCTL** The twelve characters in card columns 13 to 24 are taken to be octal digits and are used to form a 12 digit octal word in core storage in the next location to be assigned by the assembler. If the characters appearing in columns 13 to 24 are not octal digits, an incorrect word will be generated and no error indication will be made. A symbol in the symbolic location field will be defined to be the location of the generated word.

**CØMP** The CØMP pseudo-op specifies that the entire variable field, columns 13 to 72, is taken to be an arithmetic statement which is to be compiled, in much the same manner as in FØRTRAN or MAD. Blanks are ignored and commas may be used to indicate tagging. The arithmetic statement must consist of a symbol followed by an equal sign and followed by an arithmetic expression. This expression may consist of symbols connected by the break and grouping characters:

+      -      \*      /      (      )

Numbers in the expression will be taken as symbols referring to memory locations. The indicated arithmetic expression will be compiled in floating point arithmetic, and a list of the instructions compiled will appear on the CAP assembly listing. If a symbol appears in the symbolic location field of the CØMP card, its value will be the location of the first compiled instruction.

**END** This pseudo-op marks the physical end of the program and defines the entry point to the program to be the value of the expression in the variable field. If a symbol appears in the symbolic location field, it is given the value of the first location not used by the program.

#### 2.4 Use of CAP

CAP is a package of subroutines which is called by

```
.
.
.
TSX      $CAP,4
.
.
```

The AC should contain the location in core storage into which the first instruction of the symbolic program is to be assembled. When CAP is finished it will leave in the AC the entry point to the program. The sense register (SI) will be nonzero if any assembly errors were noted by CAP.

#### 2.5 Output of CAP

The CAP assembler has two outputs, a printed assembly listing, and a binary machine program. The listing consists of one or more printed lines for each instruction card in the symbolic input deck. This line contains the 80 columns of the original card, the

12 digit octal word which CAP has assembled as well as the octal location in which the instruction has been placed, and pertinent coded error indications. In the case of CØMP pseudo-ops, the CØMP card will be printed and followed by a list of the instructions generated by the compiler in the format described earlier. The assembly listing is written on an output tape for later printing. The binary machine program is left in core storage beginning at the location specified by the program which called CAP.

## 2.6 Restrictions and Error Indications

1. No more than 100 symbols may be defined. If this restriction is exceeded, further symbols are ignored and a comment is printed at the beginning of the assembly listing, and SI bit 17 will be turned on.
  2. All operation codes must be among those listed earlier in this chapter. If an illegal operation code is encountered, it will be treated as zero, SI bit 34 will be turned on, and the letter "O" will be printed on the assembly listing next to the offending instruction.
  3. All symbols appearing in variable fields and CØMP statements must be defined. If an undefined symbol is encountered, it will be given value zero, SI bit 35 will be turn on, and the letter "U" will be printed next to the offending instruction.
  4. The variable field of an INT pseudo-operation must contain only decimal integers, preceded by plus or minus signs and commas. If an illegal character is encountered, that word will be assembled as zero, SI bit 33 will be turned on, and the letter "E" will be printed on the assembly listing next to the offending pseudo-op.
  5. No more than 200 separate elements and break characters may appear in a CØMP statement. If this restriction is exceeded, the CØMP statement is skipped, and SI bit 14 will be turned on.
  6. No more than 125 nested parentheses may appear in an arithmetic expression in a variable field. If this restriction is exceeded, an incorrect value may be computed and SI bit 15 or 16 will be turned on, depending on the nature of the parentheses count.
- The following two restrictions occur when CAP is run under the Classroom Execution Monitor described in Chapter 5:
7. No more than 150 cards may appear in the symbolic program.
  8. The symbolic program must not assemble into more than 256 binary machine instructions or require more than 300 card images to be written on the collation tape.

## Chapter 3

### THE CAP ASSEMBLER

#### 3.1. How Does an Assembler Work?

In this chapter we shall examine in detail the workings of CAP and of assembly programs in general. While references to the exact coding of CAP are specific to this assembly program, the general discussion and flow charts are common to most assembly programs for most computers.

The purpose of any assembly program is to translate the symbolic cards describing a machine language program into that machine language program. For convenience, this translation can be considered to consist of two operations: First, the mnemonic codes representing machine operations must be replaced by the binary machine codes representing those same operations; and these binary codes must be assigned locations in core storage. Second, the symbolic variable field of each instruction must be evaluated in terms of the symbols appearing in the symbolic location fields of other instructions, and the resulting address must be inserted in the instruction. Consider the following program, written in the CAP language:

CAL	BITS	GET CØUNT.
SLW	WØRD	SAVE.
HERE	TRA HERE	STØP.
BITS	INT 6	BIT CØUNT.
WØRD	INT 0	STØORAGE FØR BIT CØUNT.

In order to translate the first instruction, CAL BITS, we need to know two things. First, what is the binary machine code corresponding to the mnemonic CAL? Second, what is the value of the address part of the instruction, that is, what is the value of the symbol BITS? The first question can be answered by reference to a table of operation mnemonics and machine codes, an essential part of any assembler. The second question, however, requires knowledge of which symbolic card has the label BITS. This knowledge can be gained only by going completely through the symbolic deck once to determine the location value of each symbol.

We see, then, that the assembly program must go through the symbolic cards twice. The first pass through the symbolic cards is required to assign each instruction to a place in core storage and thereby to define the value of the symbol, if any, appearing in its symbolic location field. Then, on the second pass through the cards, it is possible to evaluate the variable field of each instruction on the basis of the symbols defined on the first pass.

We may expect, therefore, that CAP will exhibit a basic structure consisting of two passes through the input symbolic card deck. In fact, since CAP is coded in the form of independent subroutines, we shall find that this two-pass structure is handled by two subroutines, named, conveniently, PASS1 and PASS2. These two subroutines are called by




Figure 3.1. Flow diagram of subroutine CAP.

another single subroutine named CAP. (The reader should note that the name CAP will hereafter be used both for the entire assembly program and for the subroutine which calls PASS1 and PASS2. The meaning of any particular usage should be clear from context.) Let us examine a flow diagram of the subroutine CAP, in Figure 3.1.

The CAP subroutine is called by the sequence

```

    . . .
    CAL    ØRG
    TSX    $CAP, 4
    . . .
  
```

in the main subprogram. (See listings of MAIN and CAP in Appendix 1.) ØRG specifies the location in core storage at which the machine language program assembled by CAP is to start.

Subroutine CAP then gives this information as an argument to subroutines PASS1 and PASS2, which perform the two passes through the symbolic card deck mentioned earlier.

Note that subroutines PASS1 and PASS2 upon encountering errors turn on bits in the sense register (SI); subroutine CAP therefore clears the SI before calling each subroutine, and saves its contents upon return. The main program, upon return from CAP, could determine if the assembly was successful by examining the SI, although it does not do this.

### 3.2 Pass One, Symbolic Definitions

It is stated earlier that the purpose of the first pass is to assign each instruction a place in core storage and thereby define all symbols appearing in location fields of the symbolic program. The procedure involved in doing this is, as might be expected, quite straightforward. First, an instruction location counter (ILC) is set to contain the location where the first instruction is to be assembled, which is the origin of the machine language program being generated by CAP. Then, a card is read. If it is not a pseudo-operation, the symbol, if any, appearing in the symbolic location field is defined, the card is put away in a place at which it can be found by pass two, and the ILC is incremented by one. The process is then repeated for the next card. If a pseudo-operation is encountered, some special processing may have to occur. For example, when the END card is encountered, pass one should terminate rather than continue reading cards. A flow diagram of pass one is shown in Figure 3.2.

If we examine the coding of the loop in subroutine PASS1, we find that it takes very few instructions, primarily because the difficult jobs are relegated to subroutines. For example, the box labeled "Read card" is handled by a subroutine named READ1. The entire operation, of determining whether there is a symbol to define and defining it to be the value of the ILC, is handled by another subroutine SYMSTØ. Similarly subroutine WCT1 handles the problem of saving the card for the second pass. If we believe that these subroutines work as their calling sequences specify, the understanding of pass one is greatly simplified.

In fact, the physically largest section of subroutine PASS1 is devoted to processing the pseudo-operations, even though this processing is perhaps the least important function of pass one. Let us examine what must be done when pseudo-operations are encountered. Perhaps the simplest procedure occurs for the pseudo-operation REM. In this case the loop is re-entered after skipping the operations of symbol definition and increasing the




Figure 3.2. Flow diagram of the first assembly pass.

ILC. The only procedure of interest is saving the REM card for pass two. (See Figure 3.3, a flow diagram including pseudo-op processing.)

In the case of the ØCTL pseudo-operation during pass one, the only concern is the number of words of storage required (one in this case) and the definition of any symbol appearing in its symbolic location field. Therefore, it can be handled exactly like the ordinary operation codes, that is, by defining the symbol and increasing the ILC by one.

If an INT pseudo-operation appears, the same considerations apply as before. However, the variable field of the INT may specify that several words be generated. (See INT description in Chapter 2.) The variable field always specifies that at least one word should be generated. If there are to be additional words, for each extra word there will be a comma in the variable field. Therefore, the assembler may learn how many words will be generated simply by counting the number of commas in the variable field and adding one. Remember that the only concern of pass one is counting the number of registers used by the source program and defining symbols. The procedure used when an INT is encountered is, then, to test for and define the symbol in its symbolic location field, and to count the number of commas in its variable field. The subroutine CØMMA performs this last step, and also adds one plus the number of commas to the ILC. The loop is then re-entered for the next card.

The operation of the CØMP pseudo-operation will not be explained in detail here except to say that the symbol, if any, in columns 1 to 6 is defined, the card is saved for pass two, and a subroutine CØMPØP is called to process the pseudo-operation variable field. CØMPØP causes the generation of the instruction sequence required to carry out the computation indicated in the variable field and increases the ILC appropriately. The operation of subroutine CØMPØP is not essential to an understanding of pass one or the rest of CAP. A full discussion of the subroutine may be found in Chapter 4.

We come finally to the END pseudo-operation. When this card is encountered, pass one is complete except for certain simple terminal procedures. The subroutine ENDØP must first be called to finish off the work of the CØMPØP subroutine by making space at the end of the program for the temporary storage locations required by all the compiled




Figure 3.3. Flow diagram of subroutine PASS1.

instruction sequences. Then, the symbol, if any, in columns 1 to 6 of the END card is defined and the card saved for pass two. Since pass one is now finished the value of the ILC, which is now equal to the first location not used by the object program being assembled, is placed in the AC, and subroutine PASS1 returns to the program which called it.

### 3.3 The Collation Tape

It has been mentioned several times earlier that pass one must put the symbolic card images away in a place where pass two will be able to find and process them. While in principle it would be possible for pass two to backspace the input tape (or the operator to reload the card reader with the symbolic program), in practice it is much simpler for pass one to write the card images on a second tape, the collation tape. Pass one then ends by rewinding this collation tape, and pass two can begin again with the first card in the symbolic input program.

It is worthwhile noting, also, that when small symbolic programs (say, less than 150 cards) are being assembled, there is no reason why a collation tape is necessary, as there is enough room in the core storage of a 7090 to hold all the card images at once.

A common alternate procedure for larger programs is to collect a buffer of, say, 150 cards, then write the entire buffer on a collation tape at once. While the tape write takes place, the assembly program can be processing more input cards and storing them in a second buffer.

Still another method uses two collation tapes, collating half the input cards on one, then starting a rewind so that when pass two begins there will be no wait for tape positioning. The second half of the program is collated on the second tape, which is rewound at the end of pass one, and which will be properly positioned about halfway through pass two when it is needed.

If no collation tape is used, it is still convenient for pass one to call a subroutine to store the cards; the subroutine simply inserts them into a core memory buffer rather than writing a collation tape. Similarly, pass two uses a complementary subroutine which locates and transmits the core buffer rather than reading back from a collation tape.

### 3.4 Pass Two, Symbolic Evaluation

When all symbols have been defined by pass one, it is possible to finish the assembly by processing each card image in order, and determining values for its operation code and for its variable field. The purpose of pass two, it will be remembered, is to evaluate the operation code and variable field of each card, to assemble the binary machine word required to represent the instruction, and to print an assembly listing containing the original card and the octal equivalent of the machine word generated. Again, the basic procedure is straightforward, although pass two is a little more complicated than pass one. The ILC is again set to start at the origin specified by the program which called CAP.

The main loop of pass two then operates as follows: First, a card is read from the collation tape. If the card does not refer to a pseudo-operation, the operation code is evaluated by comparing it to entries in the operation table. The numeric code of the machine instruction corresponding to the given mnemonic is obtained from this table. Then, the variable field is evaluated. These two results are combined by a logical "OR" and inserted in core storage at the location specified by the ILC. (An alternate procedure might be to store the instruction in an output buffer for punching.) A line is printed

on the assembly listing containing the card image and the octal equivalent of the word that was inserted in core storage. Finally, the ILC is increased, and the loop repeated for the next card.

The main loop of subroutine PASS2 takes but a few instructions, as most of the difficult jobs are handed down to subroutines to perform. The cards are read from the collation tape by subroutine READ2, and the assembly listing is printed by an internal subroutine PRNT1. The most difficult job, evaluation of the variable field on the basis of the symbols defined in pass one, is handled by subroutine VAREVL.

As in pass one, the physically largest section of coding in pass two is that involved in processes not strictly important for an understanding of how pass two works, that is, processing the pseudo-operations, and printing the assembly listing. The pseudo-operations are handled as special cases as they were in pass one, by performing some simple operations and re-entering the main loop at a strategic point. Let us examine them again, one at a time, to learn how they each fit into pass two.

The REM Pseudo-operation again is the simplest of the pseudo-ops. The REM card is printed on the assembly listing, and the loop re-entered at the point where the next card is read. (See Figure 3.4). A slightly different print subroutine is used, as no octal word was generated for the REM pseudo-op and nothing need be printed in the columns normally used for printing the octal word.

The CØMP pseudo-operation is handled exactly like the REM pseudo-operation in pass two, since all compilation operations were finished in pass one. (See Chapter 4 for details on the CØMP pseudo-operation.)

The INT pseudo-operation is taken care of very simply by calling a subroutine INTØP to evaluate the variable subfields and to insert the results in core storage. The INT card is printed on the assembly listing along with the first machine word generated.

The ØCTL pseudo-operation is handled on the spot by PASS2 as an example of in-line coding. A BCD-binary conversion is performed, the result inserted in core storage, and the ØCTL card printed on the assembly listing.

As a last step for each of the above pseudo-operations, the pass two loop is re-entered at an appropriate place. In the case of the END pseudo-operation, however, the loop terminates. The variable field of the END card is evaluated by subroutine VAREVL, and this value is saved (and printed) as the entry point to the assembled machine program. Pass two is now complete. The error flags, if any, are placed in the SI, and PASS2 returns to the program which called it.

A comment on the error flags in subroutine PASS2 is in order at this point. Whenever an undefined symbol is encountered in a variable field by subroutine VAREVL, or an illegal operation code by PASS2, or an INT error by subroutine INTØP, an appropriate bit in the sense indicator register is turned on. The subroutine used to print out the assembly listing examines the SI and prints any error flags next to the instruction being processed. The SI is then set to zero before the next instruction is processed. In addition, one cell is kept throughout pass two which contains the logical combination ("OR") of all the error bits of individual instructions. It is this last cell that is placed in the SI when pass two is finished.

### 3.5 VAREVL, Evaluation of the Symbolic Variable Field

We now come to the problem of evaluating the symbolic variable field of each instruction; a problem often considered to be the essence of the assembly process. At first glance, given that the values of the symbols which might appear in a variable field have been defined during pass one, we might think that this evaluation would be quite easy. In fact, if we were asked to carry out such an evaluation we would have no difficulty working out the answer in a short time. However, the algorithm needed for the evaluation is




Figure 3.4. Flow diagram of subroutine PASS2.

surprisingly complicated, because of the existence of an implied order of operations in the mind of the person writing the expression. Consider, for example the following CAP symbolic instruction:

```
X CAL ALPHA+4*BETA
```

where ALPHA and BETA are symbols which appear in the symbolic location fields of cards elsewhere in the program. In evaluating the expression "ALPHA+4\*BETA", the multiplication must be carried out before the addition operation, or else an answer will be obtained which is different than the one intended by the writer of the expression. Although this order of precedence is a usual convention in mathematical notation, it must be systematically observed by the assembler when evaluating the expression.

Let us examine a moderately complicated expression and see what sort of combinations of symbols may appear. After figuring out what procedure is used in each of these cases, a general procedure will begin to emerge which can be formalized into an algorithm for the evaluation procedure.

Let us take, as an example, the symbolic expression

```
+4*ABC-ALPHA+S*2
```

and assume that ABC, ALPHA, and S are defined symbols. We first observe that a symbolic expression can be characterized as a string of elements (symbols or decimal integers) separated by break characters and terminated by a blank column. The allowed break characters represent the binary operations of addition (+), subtraction (-), and multiplication (\*), and the unary plus and minus sign. For the moment, the ability to handle parenthetical expressions will be ignored. The unary plus at the beginning of the expression, if not provided by the programmer, is automatically inserted as a first step of evaluation.

To formalize the scan of this expression, let us create three windows which can be moved across the expression in such a way that the center window always shows us an element, and the left and right windows show us the break characters on the corresponding left and right sides of that element. For example, if the windows were placed on the above expression as far to the left as possible, we would obtain:

```
[+] [4] [*] ABC-ALPHA+S*2
```

What does this combination of operands imply? First, the plus sign on the left signals that we are starting to evaluate a term. The asterisk on the right signals that there are more things to come in this term, so the saving of the element in the center for a future multiplication is all we can do. The element is saved in a location named "term" ready for reference later.

Now, move the windows to the right until the next element falls in the center. We obtain

```
+4 [*] [ABC] [-] ALPHA+S*2
```

Again examining the left and right break characters to decide what should be done, we argue as follows: The asterisk on the left tells us to multiply the old value of the term by the value of the present element. This result may be returned to the storage location "term". The minus sign on the right signals that the term has come to an end, and that the value stored away in "term" should be added into the "sum" register for this expression.

Now, move the window to the right again. This time, we obtain

```
+4*ABC [-] [ALPHA] [+ S*2
```

The left window exhibits a minus sign signaling the start of a new term, a negative one at that. Therefore, we may store away the negative of the value of the present element in the location "term". The plus sign on the right again signals the end of the term, and that the value of the term should be added to the "sum" register.

Moving the window once more, we obtain

+4\* ABC-ALPHA  $\boxed{+}$   $\boxed{S}$   $\boxed{*}$  2

This combination of operators is identical to that found at the beginning of the expression so that we may follow the same procedure. First, on the basis of the plus sign we store away the value of the present element since we are starting a new term. Second, since the \* indicates that there is more to come in this term, we must wait until later elements are brought into consideration.

Finally, with the window in its next and last position, we have

+4\* ABC-ALPHA+S  $\boxed{*}$   $\boxed{2}$   $\square$

This time the situation is similar to one encountered before, except for the lack of an operator in the right window. The left break character again requires us to multiply the value of the term collected so far by the value of the present element. The blank appearing in the right window tells us to add the term into the "sum" register and stop, as the evaluation of the symbolic expression is complete.

Although, this procedure seems complicated, let us see if we can develop a flow diagram describing the algorithm. The procedure has the following characteristics: After moving the window, we first examine the break character in the left window, do something about it, then examine the break character on the right. After processing on the basis of this right break character, we move the window and repeat the same series of steps. This procedure is formalized in the flow diagram in Figure 3.5. If we follow the




Figure 3.5. Flow diagram of subroutine EVAL.

flow diagram through for the expression examined previously, we see that it carries out each of the operations described. This flow diagram describes the operation of the subroutine EVAL, which is internal to the subprogram VAREVL. An important procedure which is implicit in this flow diagram is that of evaluating the item appearing in the center window. If the element is a decimal integer, a decimal-to-binary conversion must be made. On the other hand, if the element is a symbol, its value must be looked up. This lookup procedure is done by the subroutine SYMGET which acts as a complement to the subroutine SYMST $\emptyset$  used during pass one.

#### How EVAL is Called

EVAL is an internal subroutine of the subprogram VAREVL. The subprogram VAREVL itself simply sets up EVAL and calls it properly; when EVAL has finished evaluating the expression, VAREVL handles the operation of reducing the answer to a core memory location. (See Figure 3.6, a flow diagram of VAREVL.)




Figure 3.6. Flow diagram of VAREVL.

Making EVAL an internal subroutine of VAREVL allows EVAL to be defined recursively. That is, if the occasion should arise that EVAL needs to have a subexpression evaluated, it can call on subroutine EVAL to do the job. One might expect to get into difficulty with this procedure, since when EVAL is called recursively, it will change many registers and temporary results. We will see that this difficulty is circumscribed by picking out critical temporary results and saving them in a special way.

In terms of the picture described above, a parenthetical expression may be considered to be an element which appears in the center window. Whenever the center window is determined to contain a parenthetical expression as an element, the element is evaluated by calling the subroutine most able to handle the evaluation of an expression, namely subroutine EVAL. In order to call EVAL, it is necessary to save away temporary results, such as the values of the "term" and "sum" registers that have been collected so that those registers may be used by EVAL for the subexpression evaluation. Then, when EVAL is finished evaluating the subexpression, the "term" and "sum" registers are restored; the evaluation of the original expression continues, using for the value of the element in the center window the answer obtained by EVAL on the recursive call.

Since the parenthetical expression may itself contain another nested parenthetical expression, EVAL

must be very careful how it saves away its temporary results, as a second saving of temporary results might destroy the first set.

To handle this problem, two subroutines named SAVE and UNSAVE are used by EVAL. These two subroutines manipulate a last-in, first-out storage array called a push-down list. Each time subroutine SAVE is called, an item or block of items is stored in the list. When subroutine UNSAVE is called, the last item or block stored in the list is retrieved. Successive calls to UNSAVE retrieve items stored by earlier calls to SAVE.

EVAL, then, saves temporary results in the push-down list before calling itself, and retrieves the results later. If the expression requires repeated recursion, the pushdown list will save and restore the temporary variables in the proper order.




Figure 3.7. Flow diagram of EVAL with recursive capabilities.

Figure 3.7 is a flow diagram of EVAL with the ability to handle parenthetical expressions added. The recursive ability of EVAL is not essential to the understanding of the general expression evaluation procedure; it should be ignored in early study by assuming that no parentheses are encountered.

### 3.6 Subprogram Calling Sequences and Definitions

In this section, the calling sequences and a thumbnail description of each of the utility subroutines used in CAP are described. For reference, the same information about subroutines CAP, PASS1, PASS2, and VAREVL is reproduced here.

#### Primary Subroutines

CAP CAP is called by

```

    ..
    CAL      ØRG
    TSX      $CAP, 4
    ..
  
```

Subroutine CAP causes the symbolic program written on cards and appearing on the input tape to be assembled in core storage starting at the location specified by the address portion of the accumulator.

PASS1 PASS1 is called by

```

    ..
    CAL      ØRG
    TSX      $PASS1, 4
    ..
  
```

Subroutine PASS1 performs the first pass of an assembly program over the symbolic cards on the input tape, writes them on a pseudo-collation tape, and defines symbols; assuming that the symbolic program is to start at the location specified by the address portion of the accumulator. If errors are found they are noted in the SI. PASS1 uses index register one to contain the complement of the ILC.

PASS2 PASS2 is called by

```
..  
CAL      ØRG  
TSX      $PASS2, 4  
..
```

Subroutine PASS2 performs the second pass of an assembly program by reading the symbolic cards appearing on the collation tape. The program is assembled in core storage starting at the location specified by the address portion of the AC, and an assembly listing is prepared on the output tape. PASS2 uses index register one to contain the complement of the ILC. If errors are found they are noted in the SI.

VAREVL subroutine VAREVL is called by

```
..  
TSX      $VAREVL, 4  
PZE      BUFF  
..
```

where BUFF is the location of a 14 word buffer containing a symbolic card image. VAREVL will evaluate the variable field starting with the first character of BUFF+2 and continuing to the first blank, comma, or column 73. If any undefined symbols are encountered, SI bit 35 will be turned on.

#### Input and Output Subroutines

Both PASS1 and PASS2 call several input-output routines to handle tape manipulations. These I/O subroutines are

READ1 Read Input Tape, called by

```
..  
TSX      $READ1, 4  
PZE      BUFF  
  
.  
  
BUFF BSS      14  
..
```

The 80 columns of a symbolic card are read from the input tape into the fourteen word buffer at BUFF. Note that 80 characters do not quite completely fill the buffer; the last 4 positions may contain arbitrary characters.

WCTL1 Write Collation Tape, called by

```
..  
TSX      $WCTL1, 4  
PZE      BUFF  
  
.  
  
BUFF BSS      14  
..
```

The fourteen word BCI buffer is written on the intermediate tape.

REWIND Rewind Collation Tape, called by

```
..  
TSX      $REWIND, 4  
..
```

The intermediate tape is marked with an end of file and rewound.

READ2 Read collation tape, called by

```
..  
TSX      $READ2, 4  
PZE      BUFF  
. .  
BUFF BSS    14  
..
```

Fourteen words of the intermediate tape are read into the buffer at BUFF. READ2 checks that the collation tape has been rewound.

PRINT Write on output tape for off-line printing, called by

```
..  
TSX      $PRINT, 4  
PZE      A, 0, n  
..
```

The n word line image starting in location A is written on the output tape (tape A3). The first character of A (normally blank) is used for carriage control. PRINT counts the lines of output and stops after 300.

#### Symbol Table Subroutines

For forming and searching a symbol table a subroutine package with entries **SYMSTØ** and **SYMGET** is used.

SYMSTØ The sequence

```
..  
TSX      $SYMSTØ, 4  
..
```

will cause the BCD characters in the AC to be scanned (blanks removed), right justified, and inserted in a symbol table together with its value, the complement of IR1. If the symbol is blank, it is ignored and no entry is made in the table.

SYMGET The sequence

```
..  
TSX      $SYMGET, 4  
..
```

will cause the value of the symbol in the AC (assumed to be scanned and right justified) to be looked up in the symbol table. If the symbol is defined, the value is returned in the AC. If undefined, zero is returned in the AC and SI bit 35 is set on.

### Utility Subroutines

CAP also uses a package of utility programs which includes SCAN, CØMMA, SAVE, and UNSAVE.

SCAN SCAN is called by

```
..  
TSX      $SCAN, 4  
..
```

on return, the BCD word in the AC is compressed to the right, with blanks removed and leading positions filled with zeros.

CØMMA Subroutine CØMMA is called by

```
..  
TSX      $CØMMA, 4  
PZE      BUFF  
..
```

CØMMA counts the number of commas plus one starting with the first character in BUFF+2 and ending with the first blank or column 73. The count is subtracted from index register one. SAVE and UNSAVE manipulate items in a pushdown list.

SAVE SAVE is called by

```
..  
TSX      $SAVE, 4  
PZE      A, 0, n  
..
```

the n words in registers, A, A + 1, ..., A + n - 1 are placed at the top of the pushdown list and the other items in the list are pushed down n places. (Note that the pushdown effect is achieved by pointers, not by actually moving all the previous entries in the list down in core memory.)

UNSAVE UNSAVE is called by

```
..  
TSX      $UNSAVE, 4  
PZE      A, 0, n  
..
```

The top n items in the pushdown list are read into locations A, A + 1, ..., A + n - 1 and the other items in the list are pushed up n places.

The pushdown list has a maximum depth of 500 locations. Any attempt to exceed this depth is ignored and SI bit 15 is set. Attempts to retrieve more items than have been stored are ignored and SI bit 16 is set.

Subroutine INTØP is used to evaluate variable fields of the INT pseudo-op during pass two.

INTØP INTØP is called by

TSX	\$INTØP, 4
PZE	BUFF

where BUFF+2 is the address of the first location of the buffer containing the variable field. INTØP scans the variable field and converts each decimal subfield (as delineated by commas) to a binary number; shifts the number obtained into the decrement; and stores it in the next location in the program being assembled, assuming that index register one contains the complement of the ILC. INTØP then increments the ILC and repeats the operation for the next subfield.

Subroutine ENDØP is used at the end of pass one to reserve temporary storage for CØMP pseudo-ops.

ENDØP ENDØP is called by

TSX	\$ENDØP, 4
-----	------------

Control returns to the caller after ENDØP changes the C(IR1) by the proper amount and enters the symbol TEM into the symbol table.

ØPTBL The first word in \$ØPTBL is a control word containing in its address the location of the first item in the operation table and in its decrement the length of the operation table; the rest of ØPTBL consists of pairs of entries, a right-justified BCD mnemonic paired with the binary machine code for that mnemonic.

Subroutine CØMPØP and the subroutines it calls are described in Chapter 4.

## Chapter 4

### THE COMPILER OF CØMP PSEUDO-OPERATIONS

In this chapter we will examine in detail the operation of the set of subprograms which compile arithmetic for CØMP pseudo-operations. The material under discussion is of an advanced nature and not essential to an understanding of the CAP assembly program. A beginning reader may skip this chapter, as the material in the sequel will not make reference to the compiler. The reader is assumed to be familiar with an algebraic language such as FØRTRAN, ALGØL, or MAD.

#### 4.1 Why a Compiler?

Compilers exist to free the programmer from worry about coding details while working with algebraic calculations. The compiler can take care of the coding details, and the programmer need only concentrate on setting up the proper equations.

The primary reason for including a compiler in CAP is educational. We shall see the close similarity between the internal processes of assemblers and compilers; some of the mystery as to how compilers work will thereby disappear.

Another reason for including a compiler is to provide a contrast with the macro-operation processors found in many present-day assembly programs. A compiler is an often overlooked alternative and provides a flexibility of expression which the macro-processor cannot obtain.

#### 4.2 What Does a Compiler Do?

The point of the compiler is very simple. If the programmer writes on a card a statement

CØMP      Y = ALPHA + BETA

the program which results is identical to that which would have resulted if the programmer had instead given the instructions

CLA	ALPHA
FAD	BETA
STØ	Y

We see, then, that the purpose of the compiler is to generate a program to perform the algebraic computation indicated by the symbols and break characters in the variable field of the CØMP statement.

There are several algorithms available to perform the compilation. In the CAP compiler, a nonrecursive procedure contrasts with the recursive procedure used for evaluating expressions in subroutine VAREVL, discussed in Chapter 3. We will see that the algorithm is a collection of simple, straightforward ideas combined in such a way as to produce a sophisticated result.

#### 4.3 Relation of CØMP to CAP

We recall that when the CAP assembler encounters a CØMP pseudo-operation during pass one, it calls a subroutine named CØMPØP.

CØMPØP and the collection of subroutines which it calls compile the symbolic machine instructions in the CAP language required to carry out the computation called for by the CØMP statement. The compiler writes these symbolic instructions on the collation tape in the same format as CAP language symbolic instructions which the programmer writes and the order in which they are to be performed. The compiler increases the ILC by by the number of instructions compiled, and returns control to subroutine PASS1 to continue the first assembly pass. By writing symbolic cards on the collation tape during pass one, the compiler thereby discharges its responsibility; the symbolic instructions on the collation tape will be assembled by the second assembly pass as would instructions provided by the programmer himself.

#### 4.4 Precedence

The language available to the CØMP programmer allows the use of addition, subtraction, multiplication, and division—with parentheses as grouping characters. Since the programmer will wish to attach an order of precedence to these operations, the compiler must take that order into account when creating the symbolic program. The order of precedence used is the following:

- parenthetical expressions
- multiplication and division
- addition and subtraction

This precedence table corresponds to the table commonly assumed by mathematicians. It states, for example, that in the expression

$$A + B/C$$

the division is to be carried out before the addition.

#### 4.5 The Spread Field; CØMPØP

The subroutine called to compile CØMP pseudo-operations is CØMPØP. CØMPØP operates in two passes. In the first pass, it scans the variable field of the CØMP card, ignoring blanks, and separates the symbols and break characters one to a word in a buffer known as the spread field. For example, if the variable field contains

$$\text{SUM} = G1 + G2 + G3/\text{SIX}$$

pass one of CØMPØP would produce a spread field containing in successive locations

```

SUM
=
G1
+
G2
+
G3
/
SIX

```

Later scans may now search the spread field for break characters with a simple search loop. Symbols which are longer than six characters are permissible. They will be broken up and stored in successive words in the spread field. Since the comma is not a break character, the sequence of characters ABC,1 will be considered to be a single symbol and stored appropriately. When compiled as the address of an instruction, this symbol could represent a tagged address.

All scans of the spread field will ignore a zero appearing within the spread field. The value of this property will become clear later when we see how the spread field is modified as the expression is compiled. An alternative procedure with similar flexibility is to place successive items of the spread field in a string pointer list.

Having re-expressed the arithmetic statement to be compiled in a form easier to work with, subroutine CØMPØP proceeds with the actual compilation. A scan is made for a parenthetical expression which is in some sense "innermost." That is, it is to contain no parenthetical expressions. The procedure for finding such an "innermost" expression is as follows: Scan the spread field starting at the top for left and right parentheses, leaving markers behind at the left parentheses, and stopping at the first right parenthesis. The last left parenthesis marker and the position of the right parenthesis define an "innermost" parenthetical expression. A subroutine named EXPR is now called, with arguments consisting of the pointers to the left and right ends of the parenthetical expression, and the location of the beginning of the spread field. Subroutine EXPR will compile the symbolic CAP language program necessary to compute the expression within the parentheses and will write this symbolic program on the collation tape. EXPR will then modify the spread field by replacing the left parenthesis, the entire expression within the parentheses, and the right parenthesis with zeros. The last instruction in the symbolic CAP language program generated by EXPR will be an instruction to store the result of the computation in a temporary storage location. The symbolic name of this temporary storage location is inserted directly in the spread field by EXPR in one of the locations formerly occupied by the parenthetical expression. The symbol TEM+nn will always fit into the space vacated by the original expression. This is one of the reasons for choosing to spread out the original expression into a spread field.

At this point, the "innermost" parenthetical expression is compiled. CØMPØP now starts over again, looking for a new "innermost" parenthetical expression in the modified spread field. Since the old expression, along with its parentheses, was replaced by a single symbol in the spread field, CØMPØP can scan for a new "innermost" parenthetical expression exactly as it did before. It is now clear why zero words are ignored within the spread field. Whenever the compiler writes instructions on the collation tape, it replaces the symbols and operators within the spread field leading to the compilation

of these instructions by zeros. Later scans of the spread field ignore the presence of the zero positions, as nothing more is to be compiled from the information that was once contained there.

CØMPØP iterates in the manner described; first locating an innermost parenthetical expression, and then calling upon EXPR to compile the expression. EXPR removes the expression from further consideration by modifying the spread field.

Eventually, CØMPØP will reach a situation in which the spread field contains no parenthetical expressions. Instead, it will contain a simple expression preceded by a symbol and an equal sign. In this case, subroutine EXPR is again called with parameters indicating the beginning and end of the simple expression and with an additional parameter specifying that the program compiled is to leave its result in the AC rather than in temporary storage. EXPR again generates symbolic instructions, writes them on the collation tape, and modifies the spread field by replacing all elements compiled by zeros. Upon returning to CØMPØP the compilation is nearly completed except for storage of the final result. Subroutine CØMPØP then generates the necessary STØ instruction to complete the compilation. Let us follow this procedure through for a moderately complicated expression. Consider the following CØMP pseudo-operation

CØMP Y = ((A+B)\*(E-C\*DL)+END)\*F+L1

Figure 4.1 shows the spread field and instructions compiled in succeeding steps. Figure 4.2 is a flow diagram of CØMPØP.

Step 1. CØMPØP places the variable field in the spread field (Figure 4.1a) and scans for left and right parentheses, starting at the top, ending with the first right parenthesis. (See Figure 4.1b.) It then calls EXPR to compile this "innermost" expression. EXPR will write the instructions indicated as "step one" in Figure 4.1f, on the collation tape and modify the spread field to that shown in Figure 4.1c.

Step 2. CØMPØP scans again for left and right parentheses and calls EXPR to compile the expression found. EXPR writes on the collation tape the instructions indicated as "step two" in Figure 4.1f, and modifies the spread field to that shown in Figure 4.1d.

Step 3. One more scan for parenthetical expressions results in a call to EXPR and compilation of instructions indicated as "step three" in Figure 4.1f. EXPR modifies the spread field to appear as in Figure 4.1e.

Step 4. The scan for parentheses fails this time. CØMPØP calls EXPR to compile the remaining simple expression and specifies that the result of the computation be left in the AC. EXPR compiles the instructions labeled "step four."

Step 5. CØMPØP compiles an STØ instruction with a symbolic address consisting of that variable to the left of the equal sign. The compilation is now complete.

CØMPØP keeps track of parenthetical expressions by means of pointers to positions in the spread field. An alternative procedure is to push successive field items down in a push-down list searching for a right parenthesis. Then, the subroutine compiling the expression can retrieve items back to the last left parenthesis.

Note that we have not yet learned how EXPR compiles the symbolic arithmetic instructions and places them on the collation tape. We are analyzing the compiler from the "outside in" and are still at a stage where the organization of the compiler is the most important thing to be learned. Having established the procedure by which parentheses are handled, we are now ready to begin studying the details of instruction creation.

Y	Y	Y	Y	Y		
=	=	=	=	=	Step 1	
(	lp → (	lp → (	lp → (	TEM+4		{ CLA A
(	lp → (	TEM	TEM	0		FAD B
A	A	0	0	0		STØ TEM
+	+	0	0	0	Step 2	LDQ C
B	B	0	0	0		FMP DL
)	rp → )	0	0	0		STØ TEM+1
*	*	*	*	0		CLA E
(	(	lp → (	TEM+2	0		FSB TEM+1
E	E	E	0	0		STØ TEM+2
-	-	-	0	0	Step 3	LDQ TEM
C	C	C	0	0		FMP TEM+2
*	*	*	0	0		STØ TEM+3
DL	DL	DL	0	0		CLA TEM+3
)	)	rp → )	0	0		FAD END
+	+	+	+	0		STØ TEM+4
END	END	END	END	0	Step 4	LDQ TEM+4
)	)	)	rp → )	0		FMP F
*	*	*	*	*		STØ TEM+5
F	F	F	F	F	Step 5	CLA TEM+5
+	+	+	+	+		FAD L1
L1	L1	L1	L1	L1		{ STØ Y

(a)

(b)

(c)

(d)

(e)

(f)

Figure 4.1. Successive spread fields and resulting compilation for  
 $CØMP \quad Y = ((A+B)*(E-C*DL)+END)*F+L1.$




Figure 4.2. Flow diagram of subroutine CØMPØP.

#### 4.6 Compilation of Individual Instructions

In the fifth step in the example above, subroutine CØMPØP had to compile the instruction STØ Y. To write this instruction on the collation tape, a package of subroutines is used which manipulate a collation tape buffer and write on the collation tape. The collation tape buffer is a 14-word buffer which is used to collect a symbolic card image.

The first subroutine in this package is PIVAR. (Place in variable field.) Its calling sequence is

```
TSX    $PIVAR,4
```

PIVAR takes the contents of the AC as a BCD word, and inserts that BCD word in the next available space in the variable field of the collation tape buffer. Columns 13 to 18 are filled in by the first call to PIVAR, columns 19 to 24 on the next, etc.

The last piece of information known about any instruction is always the operation code. Subroutine GENØP inserts the operation code and writes the collation tape buffer on the collation tape. Its calling sequence is

```
.  
. .  
TSX    $GENØP,4  
BCI    1,   opr
```

where "opr" is the operation mnemonic to be inserted in the operation field. GENØP inserts the instruction code into the operation field (columns 7 to 12) writes the entire collation tape buffer on the collation tape, and clears out the buffer with blanks, resetting PIVAR to store in columns 13 to 18. Thus the sequence required to generate the STØ Y instruction in step five, above, is

```
.  
. .  
CAL    FLD,1      GET SYMBØL FRØM SPREAD FIELD.  
TSX    $PIVAR,4    INSERT IN VAR FIELD.  
TSX    $GENØP,4    GENERATE STØ ØP.  
BCI    1,   STØ    ..
```

When it compiles instructions, subroutine EXPR also uses the subroutines PIVAR and GENØP.

#### 4.7 Compilation of Simple Expressions; EXPR

Subroutine EXPR has the responsibility of compiling parentheses-free expressions. This responsibility includes the proper handling of precedence below the level of parenthetical expressions. EXPR handles precedence by making two passes over the symbolic expression; during the first pass, all terms (symbols connected by asterisks and slashes) are compiled leaving the expression in the form of a summation of individual elements (subroutine TERM compiles the terms). In the second pass over the expression, EXPR

compiles the necessary add and subtract instructions to complete the summation. Let us consider a typical spread field expression that EXPR is to compile. The expression comes from Step 2 of the previous example.

```

E
-
C
*
DL

```

In the first pass, EXPR locates terms containing more than one symbol. In the given expression, the second term falls into this category. Therefore, EXPR calls subroutine TERM with parameters pointing to the upper and lower boundaries of the term C\*DL. Subroutine TERM compiles a program which computes the value of the term and inserts the answer into temporary storage. In this case the program written on the collation tape is

```

LDQ    C
FMP    DL
STØ    TEM

```

TERM will also modify the spread field by replacing the elements of the term with zeros, and inserting the name of the temporary storage location into the spread field in an appropriate place. When TERM finishes, the spread field will appear as follows:

```

E
-
TEM
0
0

```

Since there are no more terms in our sample expression, pass one of EXPR is complete, and pass two begins. In pass two, EXPR compiles and writes on the collation tape a program to perform the summation of the elements in the expression.

The second pass consists of the following steps, indicated in the flow diagram in Figure 4.3.

1. Scan the spread field from the top, looking for the end of the first symbol. If an initial minus sign is passed, set a switch.
2. Compile the instruction CLA or CLS (on the basis of the switch set in Step 1) with a symbolic address consisting of the symbol obtained in Step 1, using PIVAR and GENØP. Replace the operator and the symbol in the spread field with a zero.
3. Continue scanning the spread field for the end of the next symbol. Again, if an initial minus sign is passed, set a switch.
4. Compile the instruction FAD or FSB (on the basis of the switch set in Step 3) with a symbolic address consisting of the symbol obtained in Step 3, using PIVAR and GENØP. Replace the symbol and the operator in the spread field with a zero.
5. Repeat Steps 3 and 4 until the end of the expression is reached. Now, if requested, compile an instruction to store the result in a temporary location. The second pass is now complete, and the expression has been compiled.




Figure 4.3. Flow diagram of subroutine EXPR.

#### 4.8 Temporary Storage and Subroutine GNSTØ

The last step in subroutine EXPR was compilation of an instruction to store the AC in a temporary location. What symbolic address should be placed in the STØ instruction, and how can temporary storage be reserved? Subroutine GNSTØ provides this service. The calling sequence

```
TSX    $GNSTØ,4
```

will bring into the accumulator the symbol TEM+n where n is one less than the number of times GNSTØ has been called. Subroutine GNSTØ will also keep track of the total number of temporary locations used so that subroutine ENDØP can reserve space at the end of assembly pass one. The first call to GNSTØ brings back the symbol TEM; later calls produce symbols such as TEM+1, etc. The instruction

```
STZ*    $NSTØ
```

resets GNSTØ so that the next call starts again with the symbol TEM. Since separate CØMP statements are independent, they can use the same temporary storage locations, and CØMPØP resets NSTØ at the beginning of each new CØMP statement.

The sequence used by EXPR to compile the store instruction is, then,

```
.
.
.
TSX    $GNSTØ,4      GET TEMPØRARY SYMBØL.
SLW    FLD,1      INSERT IN SPREAD FIELD.
TSX    $PIVAR,4      PLACE IN VARIABLE FIELD.
TSX    $GENØP,4      GENERATE STØ ØP.
BCI    1,  STØ
.
.
```

#### 4.9 The Compilation of Terms; TERM

When EXPR encounters a term consisting of symbols connected by asterisks and slashes, it calls subroutine TERM to compile instructions which compute the value of the term and leave the result in temporary storage. Subroutine TERM performs this compilation by scanning the term in much the same manner as subroutine VAREVL (see Chapter 3) noting for each symbol the break character on its left and on its right. The break character on the left may be the beginning of the term, an asterisk, or a slash. The one on the right may be the end of the term, an asterisk or a slash. Thus a symbol may have one of nine pairs of break characters associated with it. Since the instructions compiled in each of the nine cases is different, a nine-way branch must be made for each symbol. The flow diagram in Figure 4.4 illustrates this nine-way branch. The scan of the term begins at the left (or top, in terms of the spread field).

Let us consider a simple term, and follow the operation of TERM through the flow diagram. Suppose TERM is to compile the following spread field:

```
C
*
D
*
E
/
F
```




Figure 4.4. Flow diagram of subroutine TERM.

Upon scanning for the first symbol, we find that the left break is the beginning of the term, the right break an asterisk. Following the flow diagram, we see that the instruction LDQ C is compiled in preparation for the multiply operation. We may note that in this case, the compilation leaves the result in the proper register so that the next instruction FMP will operate correctly. If the right break character had been a slash, the instruction CLA C would have been compiled instead. We will see that the algorithm leaves the result in the proper register in all cases.

The scan now resumes. The next symbol has an asterisk on the left and an asterisk on the right. The asterisk on the left signals that we should compile the instruction FMP D; the asterisk on the right warns of a coming multiplication, so the result must be returned to the MQ with an XCA instruction.

Resuming the scan once more, we find that the third symbol has on the left an asterisk, on the right a slash. Again, the asterisk on the left signals that the instruction FMP should be compiled; however, the slash on the right indicates that the next operation will be division. Therefore, the result is left in the AC in proper position for the FDP instruction.

Returning to the scan for the fourth and final time, we find the symbol F surrounded by a slash on the left and the end of the term on the right. The slash calls for a division operation, so the instruction FDP F is compiled. The end-of-term break indicates that we are almost finished. A temporary storage location is generated by GNSTØ and the instruction STQ TEM is compiled. Note that if the last operation had been a multiplication, the last instruction would have been STØ TEM instead.

Now, compilation of the term is finished. Although it has not been mentioned before, the spread field was reset to zero during the scan, and, at the end, symbol TEM was placed back into the spread field. The final result of the compilation by TERM is as follows:

Spread field	Collation tape
TEM	LDQ C
0	FMP D
0	XCA
0	FMP E
0	FDP F
0	STQ TEM

#### 4.10 Review

With the study of subroutine TERM, we have completed our examination of the compiler. A brief review of the essential points covered may help place those points in the proper perspective.

The compiler operates during the first assembly pass of CAP. The compiler places the instructions generated on the collation tape for processing by the second assembly pass just as though the programmer had provided them.

Subroutine CØMPØP coordinates the compilation. CØMPØP goes over the symbolic expression in two passes. During the first pass, it places the symbolic expression in the spread field — one symbol or break character to a memory location.

In the second pass it evaluates the expression from the innermost set of parentheses outward with the help of subroutine EXPR. Subroutine EXPR also operates in two passes. In the first pass, EXPR reduces the expression to a summation by calling on subroutine TERM to compile the instructions to compute the individual terms. The second pass of EXPR compiles the instructions needed to compute the resulting summation.

During all phases of the compilation, the compiler modifies the spread field as it generates instructions and places them on the collation tape. Subroutines GENØP, PIVAR, GNSTØ, and ERASE help put together symbolic instructions and write them on the collation tape.

When the compilation is finished, control returns to CAP to continue assembly pass one.

#### 4.11 Calling Sequence of Compiler Subroutines

This section describes the calling sequences of each of the subroutines of the compiler and presents for easy reference a thumbnail sketch of the external characteristics of each subroutine.

CØMPØP Subroutine CØMPØP is called by

```
TSX      $CØMPØP,4
PZE      BUFF
```

where BUFF is the first location of a 14-word buffer containing the symbolic CØMP card. CØMPØP compiles the instructions necessary to perform the arithmetic specified by the variable field of the card in the buffer, writes these instructions on the collation tape, and increases the value of the ILC (assumed to be stored in complement form in index register one) by the number of instructions compiled.

EXPR Subroutine EXPR is called by

```
TSX      $EXPR,4
PZE      LI, T, RI
PZE      FLD
```

where FLD-LI is the address of the left break and FLD-RI is the address of the right break. EXPR takes a string of symbols connected by + - \* or / and compiles the result in floating point. If T = 0, the result is placed in temporary storage. Otherwise, the result is in the AC. The spread field is modified accordingly.

TERM Subroutine TERM is called by

```
TSX      $TERM,4
PZE      LI, 0, RI
PZE      FLD
```

where FLD-LI is the address of the left break, and FLD-RI is the address of the right break. TERM takes a string of symbols connected by \* or / and compiles the result in floating point. The compiled program places its result in temporary storage, and TERM modifies the spread field accordingly.

The following subroutines are used to form symbolic instructions:

PIVAR Subroutine PIVAR (place in variable field) is called by

```
TSX      $PIVAR,4
```

PIVAR takes the C(AC)<sub>p, 1-35</sub> as a BCD word and stores that word in the next available location in the collation tape buffer. On the first call to PIVAR, the next available location is the first word in the variable field position of the buffer.

ERASE Subroutine ERASE is called by

```
TSX      $ERASE,4
```

Subroutine ERASE clears the collation tape buffer, replacing all words with blanks, and resetting PIVAR so that on the next call it will start at the beginning of the variable field.

GENØP Subroutine GENØP is called by

```
TSX    $GENØP,4  
BCI    1,   opr
```

where the letters "opr" are the symbolic operation code desired. GENØP will take the symbolic operation code in location 1,4 and insert it into the operation field of the collation tape buffer. It will then write the buffer on the collation tape and call subroutine ERASE to clear the buffer so that it may be used again.

GNSTØ Subroutine GNSTØ is called by

```
TSX    $GNSTØ,4
```

Subroutine GNSTØ returns to the caller after placing in the AC p,<sub>1-35</sub> a symbol of the form TEM+n where n is one less than the number of times that GNSTØ has been called. Entry point NSTØ will contain this number; and if NSTØ is reset to zero, n will be reset to zero for the next call to GNSTØ. GNSTØ keeps track of the largest n ever encountered and leaves it in a location where it is accessible to subroutine ENDØP for purposes of assigning temporary storage at the end of the first assembly pass of CAP.

## Chapter 5

### CAP AS A LABORATORY EXERCISE

CAP finds application both in the classroom and in the laboratory. In the laboratory the student modifies or improves the assembler, for example, by adding pseudo-operations to make the CAP language more flexible or by improving the internal operations of the assembler. Appendix C contains a list of suggested modifications.

This chapter is divided into two parts to correspond, roughly, to material of greater interest to the student and to his instructor, respectively. No clear line can be drawn between these interests, of course, as the instructor will wish to read the entire chapter and an advanced student will find much of interest in the second part.

#### 5.1 The CAP Laboratory

The CAP assembly program was written with expansion in mind. Thus, although there might be simpler ways to perform some of the operations called for in the original CAP language, extension of these operations might be difficult if a simpler, less general, approach had been used in the original coding. There are also several examples throughout CAP of points onto which additional coding may be easily attached. An analogy would be the complicated highway interchange with one blocked exit at a point where a new highway is to be built someday.

The suggested modifications represent changes which are at once useful, educational, and not too difficult, when the operation of the original assembler is well understood.

When CAP is used in the laboratory, the main program which calls CAP is replaced by an execution monitor program to aid in debugging the modifications. This execution monitor provides aid in case the modified assembly program gets into a loop or comes to a stop, and it provides a postmortem when the CAP assembly is finished.

Also, in the laboratory, the input-output subroutines are replaced with an I/ $\emptyset$  simulator package to speed up testing; this simulator provides as CAP input a symbolic test program for assembly and simulates the collation tape with a core buffer.

#### Extent of Laboratory Assignment

A typical laboratory assignment might be the following: The instructor selects a set of modifications totaling in value about 200 "points" as required modifications. (See Appendix C for point values.) The student then selects additional modifications worth about 100 points. The student is permitted eight or nine computer "runs" to attempt to get all 300 points of modifications working correctly.

Evaluation of the student's work is done on the basis of a brief written report describing the modifications attempted and the degree of success in achieving modification. Printed computer output should accompany the report as evidence of correct operation of the modified assembly program.

### How CAP Is Modified

Two different procedures have been used to allow the modification of CAP. In the first and simpler procedure, the student makes a copy of the symbolic decks of all the subroutines basic to the assembler and, if desired, the compiler. He then makes changes to this deck of 1000 to 2000 cards and submits it for assembly by FAP and testing under the execution monitor.

If this procedure is used, the reader may wish to skip the next sections and proceed immediately with the discussion of testing of the modified assembly program (Section 5.3).

## 5.2 UPDATE

If a large class uses CAP as a laboratory exercise, the above procedure can lead to the processing of a very large number of cards. An alternate procedure involving the UPDATE feature of FAP can significantly cut down on the number of cards used. Under this procedure, the unmodified CAP subprograms are placed in symbolic form on a single UPDATE input tape for all students, and each student need only submit cards corresponding to the changes he wishes to make in the subprograms. The UPDATE pseudo-operations of the FAP language control the merging of the student's changes with the original symbolic programs and the assembly of the merged programs.

The UPDATE procedure has the disadvantage that the student must learn the UPDATE language in order to modify CAP. However, the advantages of a small input deck are significant both in time saved preparing input tapes for the computer and in added reliability of a smaller deck of cards.

All features of the UPDATE language necessary for the successful modification of CAP will be discussed here. The FAP Reference Manual contains additional information.\*

### The Use of UPDATE

Images of the cards submitted for a run are written ahead of run time on the System Input Tape by off-line card-to-tape equipment. When programs are assembled normally on the 7090 (without UPDATE), FAP reads the card images from the System Input Tape and processes them one at a time. When UPDATE is used, two more tapes are involved: the UPDATE Input Tape and the UPDATE Output Tape. In CAP, only the UPDATE Input Tape is used.

The UPDATE Input Tape contains the unaltered symbolic versions of the CAP subroutines as shown in the listings in Appendix A. The serialization in columns 73 to 80 on the lists is also on the UPDATE Input Tape and is used by FAP to determine the order of processing card images from the System Input Tape and the UPDATE Input Tape.

Because the UPDATE facility is a part of FAP the first card of any deck submitted using UPDATE must be

\* FAP

This card causes control to be transferred to FAP. FAP retains control until an END card is processed. It is important to keep in mind that the program assembled begins at the \* FAP card on the System Input Tape and terminates with the first END card processed; this END card may be on either the System Input Tape or the UPDATE Input Tape. Assembly of another subprogram requires another \* FAP card.

---

\* Reference Manual, FØRTRAN Assembly Program (FAP), IBM Publication C28-6235 (September, 1962).

The use of four UPDATE pseudo-operations (UPDATE, DELETE, DELETE THRU, and SKIPTØ) will be described. UPDATE operations are FAP pseudo-operations and, as such, begin in column 8 of the card.

#### The UPDATE Pseudo-Operation

The UPDATE pseudo-operation specifies the use of the UPDATE feature of FAP. A card with UPDATE punched in the operation field follows the \* FAP card. The variable field, beginning in column 16, specifies the details of the UPDATE run. The first subfield, beginning in column 16, specifies the logical tape number of the tape unit on which the UPDATE Input Tape has been mounted. In the following examples we will assume that the UPDATE Input Tape is mounted on logical tape drive 11. The other subfields of the UPDATE card specify features not used in CAP and should be left blank. Hence the first two cards in each CAP UPDATE assembly are

```
*    FAP
      UPDATE  11
```

#### Adding and Replacing Cards

Assembly, initiated by the \* FAP and UPDATE cards, continues as card images of FAP instructions are read from the normal System Input Tape and the UPDATE Input Tape one at a time in serial order. A serialized card image on the System Input Tape is assembled before a card of equal or higher serialization but after a card of lower serialization on the UPDATE Input Tape. Whenever FAP encounters card images of equal serialization on the two tapes, the card image on the System Input Tape is assembled in place of the card image on the UPDATE Input Tape. If there is no serialization on the card image on the System Input Tape, the card image is immediately assembled. (See Figure 5.1, a flow diagram of UPDATE.)

More than nine cards can be inserted between two consecutive cards already on the UPDATE Input Tape by giving the first card to be inserted a serial number between the two cards on the UPDATE Input Tape. The remaining cards to be inserted at this point in the subprogram are not serialized.

Changes can be made in increasing order of serialization only.

#### Deleting Cards from Programs on the UPDATE Input Tape

To remove a card from a program on the UPDATE Input Tape, the DELETE pseudo-operation is used. When FAP reads a card from the System Input Tape that has DELETE in its operation field, cards are assembled from the UPDATE Input Tape until a card image with serialization equal to that of the DELETE card is found. FAP does not assemble this card image from the UPDATE Input Tape; normal updating and assembly continue with the next card from each tape.

If many consecutive cards are to be deleted from programs on the UPDATE Input Tape, the DELETE THRU pseudo-operation may be used. When FAP reads a card that has DELETE in its operation field and the letters THRU in the variable field, no more card images from the UPDATE Input Tape are assembled until a card of serialization higher than that of the DELETE THRU card is found on the UPDATE Input Tape.\* FAP will then resume normal updating and assembly.

---

\* As of May, 1962, the M. I. T. version of FAP requires THRU in columns 15 to 18; this differs from the FAP Reference Manual description of DELETE THRU.

To delete a block of cards from the middle of a program: First, insert a DELETE card with serialization of the first card in the block. This DELETE card should be followed by a DELETE THRU with serialization equal to the serial number of the last card to be deleted. DELETE THRU will delete a card of equal but not higher serialization. The input tapes should never be moved backward while updating a program.

#### The Necessary END Card

To insure proper operation of UPDATE, the last card of the input deck for each subprogram updated must be a serialized END card. The serialization of the END card in the input deck must be identical to that of the END card on the UPDATE Input Tape for the subprogram being updated.

#### Bypassing Assembly of Subprograms

The UPDATE Input Tape will be rewound before the job starts and we may assume that it is properly positioned to begin assembly of the first subprogram on the tape. The order of subprograms on the UPDATE Input Tape is specified in Figure 5.2. The order is the same as on the CAP listings.

The first

```
* FAP  
UPDATE 11
```

would therefore, start assembly of subprogram CAP. At the end of this assembly the UPDATE Input Tape would be positioned ready to start assembly of the second subprogram. The next


```
* FAP  
UPDATE 11
```

would start assembly of PASS1, and so forth.

Most of the suggested alterations to CAP require changes to only a few of the subprograms. Therefore, it would be wasteful of machine time to assemble all of the CAP subprograms during each run. Assembly of subprograms not being modified on the UPDATE Input Tape may be omitted by proper use of the SKIPTØ pseudo-operations.

When FAP reads a card image from the System Input Tape with SKIPTØ in its operation field, assembly is suspended and the UPDATE Input Tape is read until a card image of serialization identical to the serialization of the SKIPTØ card is found. Normal updating and assembly commence with the card of identical serialization on the UPDATE Input Tape. A card of serialization higher than that of the SKIPTØ card will not terminate the SKIPTØ operation; the serializations must be identical. Thus, assembly of a subprogram can be avoided by using a SKIPTØ card serialized with the serial number of the first card in the next subprogram to be updated. Subprograms must be updated and assembled in the order that they appear on the UPDATE Input Tape; SKIPTØ cannot be used to move the UPDATE Input Tape backward.

It is good practice to include a SKIPTØ card in the input deck for every subprogram to be updated. If the UPDATE Input Tape is positioned ready to read the card specified by the SKIPTØ card, FAP will begin assembly with that card. Inclusion of the SKIPTØ cards in all input decks makes each subprogram independent of all others. The input cards for a particular subprogram may be removed from the complete input deck without



SYSINT - System Input Tape

UDINT - UPDATE Input Tape

SYSINT=UDINT - Serialization on card from SYSINT equals serialization on card from UDINT.

SYSINT<UDINT - Serialization on card from SYSINT is less than serialization on card from UDINT.

SYSINT>UDINT - Serialization on card from SYSINT is greater than serialization on card from UDINT.

Figure 5.1a. UPDATE flow diagram.




Figure 5.1b. UPDATE flow diagram.

<u>Subprogram</u>	<u>Serialization of first card</u>	<u>Serialization of END card</u>
CAP	CAP00010	CAP00320
PASS1	PAS10010	PAS10790
PASS2	PAS20010	PAS22210
VAREVL	VEVL0010	VEVL2220
ØPTBL	ØPTB0010	ØPTB0790
INTØP	INTP0010	INTP0990
UTILITIES	UTIL0010	UTIL1140
SYMSTØ	SYMS0010	SYMS0540
ENDØP	ENDP0010	ENDP1020
CØMPØP	CØMP0010	CØMP1860
EXPR	EXPR0010	EXPR1710
TERM	TERM0010	TERM1350

Figure 5.2. Order of subprograms on CAP UPDATE Input Tape.

the need to add a SKIPTØ card in the deck for the following subprogram. The first three cards for each subprogram to be updated should be

```
* FAP
UPDATE 11
SKIPTØ
```

Column 73  
↓  
SUBR0010

( Serial number of  
 the first card in  
 the subprogram  
 to be updated. )

Remember that the UPDATE Input Tape contains the unaltered, symbolic version of the CAP subprograms as contained in the listing in Appendix A. When we submit a deck to update a CAP subprogram, it is the combination of that symbolic input deck and the unaltered symbolic program on the UPDATE Input Tape that is assembled. When new changes are made to a subprogram all previous desired changes to that subprogram must be included in the input deck.

### 5.3 How CAP Is Tested

If the modified version of CAP assembles successfully, it may be tested on the same computer run. To simplify this testing a special library tape is used with the FØRTRAN Monitor System. This library tape contains the execution monitor program and all of the subroutines of the CAP assembler in an unmodified, binary form. The student need only

assemble those subprograms of CAP for which changes are desired, and the library will provide the rest of the subroutines needed to complete CAP. The student must also provide a main program which calls the execution monitor program.

Once a subprogram has been modified, assembled, and checked out, it may be submitted on later runs in binary form; it need not be reassembled if no changes are to be made to it.

Let us suppose that a student has made a change to one subprogram, VAREVL, in his attempt to add division to the variable field operations. If he submits an assembly and a main program as an FMS job, the following steps will be carried out:

1. The FAP assembly will take place.
2. If the assembly is successful, the main program and the program just assembled, VAREVL, will be loaded into core memory.
3. The library will be searched for the rest of the CAP assembler and the execution monitor, and they will be loaded into core memory.
4. The CAP assembler, as modified, is then run under the execution monitor program. The input-output simulator will provide a symbolic test program for CAP to assemble. A typical symbolic program used to test CAP is shown in Appendix B.
5. When CAP finishes its assembly of the test program (or gets into a loop or stops because of the modifications), control of the computer returns to the execution monitor which prints out for debugging and comparison purposes, the following:
  - a. The symbolic test program CAP worked on.
  - b. The collation tape, if anything was written on it by subroutine WCTL. The collation tape is printed out in BCD.
  - c. An octal postmortem of all programs which were submitted (in this case, only VAREVL and the main program).
  - d. An octal postmortem of the region in core storage in which CAP was to have placed the assembled program.

In the case of the VAREVL test, it will be noted that the symbolic test program in Appendix B has in it several variable field division signs. Examination of the addresses assembled for these instructions will tell whether or not the modification worked correctly.

In case of difficulty, such as a program stop or loop, the collation tape dump is often most helpful if the stop occurred in pass one, since the tape will contain the last instruction processed correctly. Similarly, pass two loops or stops may be diagnosed by observing which instruction was the last processed and printed on the CAP assembly listing. For example, if the first instruction which does not appear on the CAP output listing is the first instruction in which division appears in the variable field, one might suspect the new VAREVL modification.

In connection with item five, listed earlier in this section, the execution monitor assumes CAP to be in an endless loop if it takes longer than five seconds to complete its assembly. The postmortem indicates the instruction location where the program was stopped. Adding one to this location will give the instruction which was next to be executed. A normal CAP assembly takes about one second on the IBM 7090 and the most complicated interaction of modifications should not extend this time by more than three seconds.

A typical CAP execution run is shown in Appendix B following assembly listings of the execution monitor subprograms. The format of the CAP assembly output and of the postmortem outputs can be seen there.

#### 5.4 Tactics for Modifying CAP

Experience has shown that the following tactics can be helpful in making maximum use of the limited number of computer runs available for debugging modifications to CAP.

1. Some modifications are closely related to others; making the first modification allows the second to follow with but a few instructions.
2. All anticipated modifications should be submitted before the fourth or fifth run (if eight runs are available) to allow sufficient time for debugging.
3. Leave the addition of pseudo-operations which change the ILC (such as BSS) until later runs; debugging the simpler modifications in early runs. (If one of these pseudo-operations fails, the result is usually catastrophic.)
4. Observe that the point values attached to modifications are an indication of their relative difficulty. In particular, modifications to the compiler require an understanding of advanced material in Chapter 4 and should be avoided by the beginner.

#### 5.5 The Instructor's Point of View

The material discussed in this section is of an advanced nature and may be skipped by the reader not interested in teaching CAP to a class.

##### The Execution Monitor

The execution monitor is a package of library subroutines called by a main program. The calling sequence to this monitor is

```
TSX      $TESTS,4
```

The main program listed in Appendix B, which contains the above instruction, may be assembled and given to the student in binary form for submission along with his modifications. The main program also contains three words of octal 7's which prevent the student from duplicating the binary cards on an IBM 026 keypunch. Without the octal 7's the 026 may duplicate the cards incorrectly but the 7's prevent all duplication, and thus they insure against the possibility of an incorrect binary main program. Note also that the execution monitor does not return to the main program which called it, it exits to the FORTRAN Monitor System when finished testing CAP.

The execution monitor first prints a subprogram storage map of all binary and symbolic programs submitted by the student. This is done by reference to subroutine MØVIE inserted at the time of loading by the BSS loader.\* The storage map lists all subprograms found in MØVIE from the beginning of core storage up to the subroutine TESTS, which is the first subprogram loaded from the library.

Depending on the status of sense switch one, either a core storage clock or a magnetic tape on channel B of the 7090 in combination with a data channel trap is used as a five-second timer. In the latter case, a scratch tape (tape B3 as the program is shown in Appendix B) is write selected and a sequence of data channel commands with a word count of 50000 and terminating with an IØCT command is given to channel B.

---

\* Subroutine MØVIE is a copy of the BSS loader table which has been moved to a position following the last subprogram loaded and given an entry point name by the BSS loader before beginning execution. This loader table consists of entry name and entry point pairs and permits a selective storage map and postmortem to be given.

Since the word transmission rate of a 729 mod IV magnetic tape is about 10,000 words per second, the data channel trap will occur in about 5 seconds if CAP has not completed its assembly and returned to the monitor by that time. This trap will restart the computer if it is at a program stop.

Other trap returns are also set by the execution monitor. A standard floating point trap interpreter is provided which changes underflow to zero and terminates the run on overflow. The select trap return is set up and the select trap enabled before calling CAP.

After these traps have been enabled, the execution monitor places in the AC the origin of the symbolic program that CAP is to assemble (50000<sub>8</sub>) and calls CAP.

An I/O simulator package handles all calls for input and output from CAP. The input tape is simulated by a core storage buffer containing strings of card images. Subprogram PRØG is used as a buffer to hold these strings. The collation tape is also simulated using a core buffer.

Control eventually returns to the execution monitor; it returns either via the expected return from CAP, or via timer or select traps. The execution monitor prints an appropriate comment and gives a postmortem of relevant information. It then returns to the FØRTRAN Monitor System with a standard system load sequence.

#### Miscellaneous Details About the Laboratory

If a student has made a modification which is not tested in the symbolic test program contained in subprogram PRØG, a special input/output package is used which reads card images from the System Input Tape after the student's \* DATA card. All other I/O operations are handled in exactly the same way as in the usual I/O simulator package.

Each student must have the UPDATE Input Tape rewound at the beginning of his job. This rewind may be accomplished in one of several ways; perhaps the simplest is the temporary modification of the FØRTRAN Monitor System to rewind the tape between jobs.\* An alternative might be to require that each student use the REWIND pseudo-operation in his first FAP assembly.

#### Making an UPDATE Input Tape

The UPDATE Input Tape used for CAP may be made with the aid of the FAP UPDATE facility. In the following discussion, since the tape is being written, it will be referred to as an UPDATE Output Tape. When making an UPDATE tape from a card deck, only an output tape is specified on the UPDATE card. For example, if the tape being written is on logical drive 11, the FAP control card would be

UPDATE ,11,,D

The D in the fourth subfield specifies that assembly is deleted, permitting the entire tape, including all subroutines, to be written with only one loading of FAP.

Since the third subfield is void, the output tape will be in blocked format. This blocked format is preferable to unblocked, as less time will be required to move the UPDATE tape when it is used later by a class. (FAP writes blocked records 16 cards to a block.)

Since assembly is deleted by the fourth subfield, regular END cards (in the subroutines being placed on the UPDATE Output Tape) will not stop FAP: the pseudo-operation ENDUP will. Following the last subroutine being placed on the UPDATE Output Tape, the UPDATE pseudo-operations ENDFIL and REWIND may be used to complete the tape.

If a student should attempt to SKIPTØ a serial number not on the UPDATE tape, FAP will stop with a comment and print the last card on the UPDATE tape. For this reason, a card with a distinctive comment such as "SKIPTØ ERRØR" may be inserted after the last subroutine written on the UPDATE tape.

---

\* J. H. Saltzer, M.I.T. Computation Center Memo CC-204 (February, 1963).



## Appendix A

### LISTING OF THE CLASSROOM ASSEMBLY PROGRAM

This appendix consists of FAP listings of the complete Classroom Assembly Program. At the end of these listings is an assembly output produced by CAP, of a sample CAP language program. Certain conventions have been observed in these listings. The double asterisk (\*\*) has been used as a zero element in the variable field of those instructions subject to program modification. Each subroutine begins with the pseudo-operation PCC to insure that all cards in the original subprogram appear on the listing. Since the listings are to be used as references for UPDATE modifications, the position of all control cards must be known.

<u>Index to Appendix A</u>	<u>Page</u>
Main program	48
CAP	50
PASS1	52
PASS2	55
VAREVL	61
ØPTBL	67
INTØP	69
CØMMA,	72
SYMSTØ,	76
ENDØP, PIVAR, GENØP, GNSTØ, ERASE	78
CØMPØP	81
EXPR	86
TERM	91
READ1, PRINT, WCT1, REWIND, READ2	95

## MAIN PROGRAM FOR CAP.

84

	PCC COUNT LBL	26 MAIN	BINARY CARD LABEL.	MAIN0010 MAIN0020 MAIN0030
<b>TRANSFER VECTOR</b>				
00000	336225636447	.SETUP		
00001	475131456360	PRINT		
00002	232147606060	CAP		
00003	256731636060	EXIT		
00004	0074 00 4 00000	CALL	.SETUP	SETUP LIBRARY TIMER AND DUMP RETURNS. MAIN0050
00005	1 00000 0 00007			
00006	0 00004 0 00000			
00007	0074 00 4 00001	TSX	\$PRINT,4	PRINT 'BEGIN ASSEMBLY' COMMENT. MAIN0060
00010	0 00007 0 00031	PZE	BEG,0,7	.. MAIN0070
00011	-0500 00 0 00030	CAL	ORG	SET ORIGIN. MAIN0080
00012	0074 00 4 00002	TSX	\$CAP,4	GO TO CAP. MAIN0090
00013	-0130 00 0 00000	XCL		GET ENTRY POINT. MAIN0100
00014	-0763 00 0 00025	LGL	21	CONVERT ENTRY TO OCTAL-BCI. MAIN0110
00015	-0754 00 0 00000	ZAC		.. MAIN0120
00016	0774 00 4 00005	AXT	5,4	.. MAIN0130
00017	0767 00 0 00003	ALS	3	.. MAIN0140
00020	-0763 00 0 00003	LGL	3	.. MAIN0150
00021	2 00001 4 00017	TIX	*-2,4,1	.. MAIN0160
00022	-0602 00 0 00047	DRS	RET+7	OR TO COMMENT. MAIN0170
00023	0074 00 4 00001	TSX	\$PRINT,4	PRINT 'RETURN FROM CAP' COMMENT. MAIN0180
00024	0 00011 0 00040	PZE	RET,0,9	.. MAIN0190
00025	0 07400 4 00003	CALL	EXIT	RETURN TO FORTRAN MONITOR SYSTEM. MAIN0200
00026	1 00000 0 00030			
00027	0 00201 0 00000			
00030	+000000050000	ORG	OCT	50000 CAP PROGRAM ORIGIN. MAIN0210
00031	016060606060	BEG	BCI	7,1 TEST OF CAP, BEGIN ASSEMBLY. MAIN0220
00032	606060606060			
00033	632562636046			
00034	266023214773			
00035	602225273145			
00036	602162622544			
00037	224370336060			
00040	006060606060	RET	BCI	9,0 RETURN FROM CAP, ENTRY POINT IS 00000. MAIN0250
00041	606060606051			
00042	256364514560			
00043	265146446023			
00044	214773602545			
00045	635170604746			
00046	314563603162			
00047	600000000000			
00050	336060606060			
		END		MAIN0260

MAIN PROGRAM FOR CAP.  
POST PROCESSOR ASSEMBLY DATA

51 IS THE FIRST LOCATION NOT USED BY THIS PROGRAM

REFERENCES TO DEFINED SYMBOLS

31	BEG	10
2	CAP	12
30	ORG	11
40	RET	22, 24
3	EXIT	25
1	PRINT	7, 23
0	.SETUP	4

NO ERROR IN ABOVE ASSEMBLY.  
\*TIME SPENT IN FAP.. 000003 IN HUNDREDTHS OF MINUTES.

## SUBROUTINE CAP, CLASS ASSEMBLY PROGRAM.

5

	PCC			CAP00010	
	COUNT	32		CAP00020	
	LBL	CAP	BINARY CARD LABEL.	CAP00040	
00005	ENTRY	CAP	START CLASS ASSEMBLY PROGRAM.	CAP00050	
 TRANSFER VECTOR					
00000	472162620160	PASS1			
00001	472162620260	PASS2			
00002	475131456360	PRINT			
 LINKAGE DIRECTOR					
00003	000000000000				
00004	232147606060				
00005	0634 00 4 00020	CAP	SXA RX4,4	SAVE IR4.	CAP00060
00006	0601 00 0 00025		STO ORG	SAVE ORIGIN.	CAP00070
00007	0441 00 0 00034		LDI =0	CLEAR ERROR FLAGS.	CAP00080
00010	0074 00 4 00000		TSX \$PASS1,4	GO TO PASS1.	CAP00100
00011	-0054 00 000001		LFT 1	TEST FOR SYMBOL TABLE OVERFLOW.	CAP00120
00012	0020 00 0 00022		TRA STFL	YES, GIVE DIAGNOSTIC.	CAP00130
00013	0604 00 0 00026	STOK	STI SIND	SAVE PASS1 FLAGS.	CAP00140
00014	0441 00 0 00034		LDI =0	CLEAR INDICATORS FOR PASS2.	CAP00150
00015	0500 00 0 00025		CLA ORG	GET ORIGIN.	CAP00160
00016	0074 00 4 00001		TSX \$PASS2,4	GO TO PASS2.	CAP00180
00017	0442 00 0 00026		OSI SIND	FORM COMPLETE ERROR FLAGS.	CAP00200
00020	0774 00 4 00000	RX4	AXT **,4	RESTORE IR4.	CAP00210
00021	0020 00 4 00001		TRA 1,4	RETURN.	CAP00220
00022	0074 00 4 00002	STFL	TSX \$PRINT,4	COMMENT.	CAP00240
00023	0 00005 0 00027		PZE WSTFL,0,5	..	CAP00250
00024	0020 00 0 00013		TRA STOK	RETURN FOR PASS2 ANYWAY.	CAP00260
00025	0 00000 0 00000	ORG	PZE	STORAGE FOR PROGRAM ORIGIN.	CAP00280
00026	0 00000 0 00000	SIND	PZE	STORAGE FOR SENSE INDICATORS.	CAP00290
00027	006270442246		WSTFL BCI	5,0SYMBOL TABLE SIZE EXCEEDED.	CAP00300
00030	436063212243				
00031	256062317125				
00032	602567232525				
00033	242524336060				
		END		CAP00310	
				CAP00320	
 LITERALS					
00034	000000000000				

SUBROUTINE CAP, CLASS ASSEMBLY PROGRAM.  
POST PROCESSOR ASSEMBLY DATA

35 IS THE FIRST LOCATION NOT USED BY THIS PROGRAM

REFERENCES TO DEFINED SYMBOLS

5	CAP	
25	ORG	6, 15
20	RX4	5
26	SIND	13, 17
22	STFL	12
13	STCK	24
0	PASS1	10
1	PASS2	16
2	PRINT	22
27	WSTFL	23

NO ERROR IN ABOVE ASSEMBLY.

\*TIME SPENT IN FAP.. 000003 IN HUNDREDTHS OF MINUTES.

## PASS 1 OF CLASS ASSEMBLY PROGRAM.

	PCC				PAS10010
	COUNT	79			PAS10020
	LBL	PASS1	BINARY CARD LABEL.		PAS10040
00012	ENTRY	PASS1	FIRST ASSEMBLY PASS OF CAP.		PAS10050
 TRANSFER VECTOR					
00000	662363016060	WCT1			
00001	512521240160	READ1			
00002	622321456060	SCAN			
00003	627044626346	SYMS TO			
00004	234644442160	COMMA			
00005	234644474647	COMP OP			
00006	254524464760	END OP			
00007	512566314524	REWIND			
 LINKAGE DIRECTOR					
00010	000000000000				
00011	472162620160				
00012	0634 00 4 00076	PASS1	SXA RX4,4	SAVE IR4.	PAS10060
00013	0737 00 1 00000		PAC 0,1	IR1 IS -(ILC).	PAS10070
00014	0020 00 0 00017		TRA RCC	SKIP TAPE WRITING FOR FIRST CARD.	PAS10080
00015	0074 00 4 00000	NEXT	TSX \$WCT1,4	WRITE CARD ON COLLATION TAPE.	PAS10090
00016	0 00000 0 00100		PZE BUFF	..	PAS10100
00017	0074 00 4 00001	RCD	TSX \$READ1,4	READ IN NEXT CARD.	PAS10110
00020	0 00000 0 00100		PZE BUFF	..	PAS10120
00021	-0500 00 0 00101	CFLD	CAL BUFF+1	GET OP-FIELD.	PAS10130
00022	0074 00 4 00002		TSX \$SCAN,4	COMPRESS TO RIGHT.	PAS10140
00023	0774 00 4 00012		AXT NPTBL,4	CHECK FOR PSEUDO-OP.	PAS10150
00024	-0340 00 4 00045		LAS PTBL+NPTBL,4	COMPARE WITH TABLE.	PAS10160
00025	0020 00 0 00027		TRA *+2	NO, SKIP.	PAS10170
00026	0020 60 4 00046		TRA* PTBL+NPTBL+1,4	YES, EXIT.	PAS10180
00027	2 00002 4 00024		TIX -3,4,2	NO, INDEX AND TRY AGAIN.	PAS10190
00030	-0500 00 0 00100	OP	CAL BUFF	NOT A PSEUDO-OP, ASSUME OP,	PAS10200
00031	0074 00 4 00003		TSX \$SYMS TO,4	GET SYMBOL, AND SAVE.	PAS10210
00032	1 77777 1 00015		TXI NEXT,1,-1	ADVANCE ILC AND RETURN.	PAS10220
		SPACE	2	PSEUDO-OP TABLE AND TRANSFERS.	PAS10230
00033	000000512544	PTBL	BCI 1,000REM	REMARK CARD.	PAS10240
00034	0020 00 0 00045		TRA REM	..	PAS10250
00035	000000314563		BCI 1,000INT	FORTRAN INTEGER.	PAS10260
00036	0020 00 0 00046		TRA INT	..	PAS10270
00037	000046236343		BCI 1,000CTL	SIMPLE OCTAL.	PAS10280
00040	0020 00 0 00062		TRA OCTL	..	PAS10290
00041	000023464447		BCI 1,000COMP	ARITHMETIC.	PAS10300
00042	0020 00 0 00053		TRA COMP	..	PAS10310
00043	000000254524		BCI 1,000END	END CARD.	PAS10320
00044	0020 00 0 00065		TRA END	..	PAS10330

PASS 1 OF CLASS ASSEMBLY PROGRAM.

	00012	NPTBL	EQU	*-PTBL	2*(NUMBER OF PSEUDO-OPS).	PAS10410
				SPACE	2 PSEUDO-OPS.	PAS10420
00045	0020 00 0 00015	REM	TRA	NEXT	IGNORE REMARK, RETURN.	PAS10430
00046	-0500 00 0 00100	INT	CAL	BUFF	GET SYMBOL.	PAS10440
00047	0074 00 4 00003		TSX	\$SYMST0,4	SAVE.	PAS10450
00050	0074 00 4 00004		TSX	\$COMMA,4	GO COUNT COMMAS.	PAS10460
00051	0 00000 0 00100		PZE	BUFF	..	PAS10470
00052	0020 00 0 00015		TRA	NEXT	RETURN.	PAS10480
00053	-0500 00 0 00100	COMP	CAL	BUFF	GET SYMBOL.	PAS10490
00054	0074 00 4 00003		TSX	\$SYMST0,4	SAVE.	PAS10500
00055	0074 00 4 00000		TSX	\$WCTL1,4	WRITE COMP CARD ON COLLATION TAPE.	PAS10510
00056	0 00000 0 00100		PZE	BUFF	..	PAS10520
00057	0074 00 4 00005		TSX	\$COMPPOP,4	GO COMPILE.	PAS10530
00060	0 00000 0 00100		PZE	BUFF	..	PAS10540
00061	0020 00 0 00017		TRA	RCD	RETURN FOR NEXT CARD.	PAS10550
00062	-0500 00 0 00100	OCTL	CAL	BUFF	GET SYMBOL.	PAS10560
00063	0074 00 4 00003		TSX	\$SYMST0,4	SAVE.	PAS10570
00064	1 77777 1 00015		TXI	NEXT,1,-1	ADVANCE ILC AND RETURN.	PAS10580
00065	0074 00 4 00006	END	TSX	\$ENDOP,4	GO TO RESERVE STORAGE AND LITERALS.	PAS10590
00066	0074 00 4 00000		TSX	\$WCTL1,4	WRITE END CARD ON COLLATION TAPE.	PAS10600
00067	0 00000 0 00100		PZE	BUFF	..	PAS10610
00070	-0500 00 0 00100		CAL	BUFF	GET SYMBOL.	PAS10620
00071	0074 00 4 00003		TSX	\$SYMST0,4	SAVE.	PAS10630
00072	0074 00 4 00007		TSX	\$REWIND,4	REWIND COLLATION TAPE.	PAS10640
00073	0754 00 1 00000		PXA	0,1	GET FIRST LOCATION NOT USED BY PROGRAM.	PAS10650
00074	0737 00 4 00000		PAC	0,4	RECOMPLEMENT.	PAS10660
00075	0754 00 4 00000		PXA	0,4	PUT IN AC.	PAS10670
00076	0774 00 4 00000	RX4	AXT	*,4	RESTORE IR4.	PAS10680
00077	0020 00 4 00001		TRA	1,4	RETURN TO CALLER.	PAS10690
00100		BUFF	BSS	14	STORAGE FOR HOLLERITH CARD IMAGE.	PAS10700
			END			PAS10710
						PAS10720
						PAS10730
						PAS10740
						PAS10750
						PAS10760
						PAS10770
						PAS10780
						PAS10790

PASS 1 OF CLASS ASSEMBLY PROGRAM.  
POST PROCESSOR ASSEMBLY DATA

54

116 IS THE FIRST LOCATION NOT USED BY THIS PROGRAM

REFERENCES TO DEFINED SYMBOLS

30	OP	
65	END	44
46	INT	36
17	RCD	14, 61
45	REM	34
76	RX4	12
100	BUFF	16, 20, 21, 30, 46, 51, 53, 56, 60, 62, 67, 70
53	COMP	42
15	NEXT	32, 45, 52, 64
62	OCTL	40
21	OFLD	
33	PTBL	24, 26, 45
2	SCAN	22
0	WCT1	15, 55, 66
4	COMMA	50
6	ENDOP	65
12	NPTBL	23, 24, 26, 45
12	PASS1	
1	READ1	17
5	COMPCTP	57
7	REWIND	72
3	SYMSTO	31, 47, 54, 63, 71

NO ERROR IN ABCVE ASSEMBLY.

\*TIME SPENT IN FAP.. 000005 IN HUNDREDTHS OF MINUTES.

PASS 2 OF CLASS ASSEMBLY PROGRAM.

	PCC				PAS20010
	COUNT	221			PAS20020
00010	LBL	PASS2	BINARY CARD LABEL.		PAS20030
	ENTRY	PASS2	SECOND ASSEMBLY PASS OF CAP.		PAS20050
<b>TRANSFER VECTOR</b>					
00000	464763224360	OPTBL			
00001	512521240260	READ2			
00002	622321456060	SCAN			
00003	652151256543	VAREVL			
00004	314563464760	INTOP			
00005	475131456360	PRINT			
<b>LINKAGE DIRECTOR</b>					
00006	000000000000				
00007	472162620260				
00010	0634 00 4 00136	PASS2	SXA Rx4,4	SAVE IR4.	PAS20060
00011	0737 00 1 00000	PAC	0,1	IR1 IS -(ILC).	PAS20070
00012	-0500 60 0 00000	CAL*	\$OPTBL	SETUP SEARCH FOR OP.	PAS20080
00013	0771 00 0 00022	ARS	18	LENGTH TO ADDRESS.	PAS20090
00014	0621 00 0 00037	STA	OPAXT	SAVE LENGTH.	PAS20100
00015	0361 60 0 00000	ACL*	\$OPTBL	FIRST+LTH.	PAS20110
00016	0621 00 0 00040	STA	OPLAS	SAVE FOR LAS.	PAS20120
00017	0621 00 0 00047	STA	OPFND	SAVE FOR PICKUP.	PAS20130
00020	0441 00 0 00312	LDI	=0	CLEAR INDICATORS.	PAS20140
00021	0600 00 0 00263	STZ	FLGSM	CLEAR TOTAL FLAGS.	PAS20150
00022	0442 00 0 00263	NEXT	OSI	FORM COMPOSITE FLAGS.	PAS20160
00023	0604 00 0 00263	STI	FLGSM	SAVE.	PAS20170
00024	0441 00 0 00312	LDI	=0	CLEAR INDICATORS.	PAS20180
00025	0634 00 1 00257	SXA	LOC,1	INITIAL ILC FOR EACH CARD.	PAS20190
00026	0074 00 4 00001		TSX	\$READ2,4	PAS20200
00027	0 00000 0 00274		PZE	BUFF	PAS20210
00030	-0500 00 0 00275	OFLD	CAL	GET COMPRESSED OP-FIELD.	PAS20220
00031	0074 00 4 00002		TSX	\$SCAN,4	PAS20230
00032	0774 00 4 00012		AXT	NPTBL,4	PAS20240
00033	-0340 00 4 00070		LAS	PTBL+NPTBL,4	PAS20250
00034	0020 00 0 00036		TRA	**2	PAS20260
00035	0020 60 4 00071		TRA*	PTBL+NPTBL+1,4 YES, EXIT.	PAS20270
00036	2 00002 4 00033		TIX	**-3,4,2 NO, INDEX AND TRY AGAIN.	PAS20280
00037	0774 00 4 00000	OPAXT	AXT	OP, GET LENGTH OF OP-TABLE FOR SEARCH.	PAS20290
00040	-0340 00 4 00000	OPLAS	LAS	COMPARE WITH CURRENT TABLE ENTRY.	PAS20300
00041	0020 00 0 00043	TRA	**2	NO, SKIP.	PAS20310
00042	1 77777 4 00047	TXI	OPFND,4,-1	FOUND, INDEX AND EXIT.	PAS20320
00043	2 00002 4 00040	TIX	**-3,4,2	NO, INDEX AND TRY AGAIN.	PAS20330
00044	0055 00 000002	SIR	2	ILLEGAL OPCODE, SET FLAG.	PAS20340
00045	-0754 00 0 00000	PXD	0,0	TAKE ZERO FOR OP.	PAS20350
00046	0020 00 0 00050	TRA	OPFND+1	SKIP PICKUP.	PAS20360
00047	-0500 00 4 00000	OPFND	CAL	**,,4 PICKUP OPCODE FROM OP-TABLE.	PAS20370

## PASS 2 OF CLASS ASSEMBLY PROGRAM.

00050	0602 00 1 00000	SLW	0,1	INSERT IN ASSEMBLED PROGRAM.	PAS20450	
00051	0074 00 4 00003	TSX	\$VAREVL,4	GO EVALUATE VARIABLE FIELD.	PAS20460	
00052	0 00000 0 00274	PZE	BUFF	..	PAS20470	
00053	-0602 00 1 00000	ORS	0,1	OR TO WORD IN ASSEMBLED PROGRAM.	PAS20480	
00054	0074 00 4 00142	TSX	PRNT1,4	GO PRINT ASSEMBLY LISTING.	PAS20490	
00055	1 77777 1 00022	TXI	NEXT,1,-1	RETURN.	PAS20500	
		SPACE	2	PSEUDO-OP TABLE AND TRANSFERS.	PAS20510	
00056	000000512544	PTBL	BCI	1,COOREM	REMARK CARD.	PAS20520
00057	0020 00 0 00070		TRA	REM	..	PAS20530
00060	000000314563		BCI	1,000INT	FORTRAN INTEGER.	PAS20540
00061	0020 00 0 00072		TRA	INT	..	PAS20550
00062	000046236343		BCI	1,000CTL	SIMPLE OCTAL.	PAS20560
00063	0020 00 0 00076		TRA	OCTL	..	PAS20570
00064	000023464447		BCI	1,00COMP	ARITHMETIC.	PAS20580
00065	0020 00 0 00111		TRA	COMP	..	PAS20590
00066	000000254524		BCI	1,000END	END CARD.	PAS20600
00067	0020 00 0 00113		TRA	END	..	PAS20610
	00012	NPTBL	EQU	--PTBL	2*(NUMBER OF PSEUDO-OPS).	PAS20620
		SPACE	2	PSEUDO-OPS.	PAS20630	
00070	0074 00 4 00173	REM	TSX	PRNT2,4	PRINT REMARK.	PAS20640
00071	0020 00 0 00022		TRA	NEXT	RETURN.	PAS20650
00072	0074 00 4 00004	INT	TSX	\$INTOP,4	DO INTEGER CONVERSION.	PAS20660
00073	0 00000 0 00274	PZE	BUFF	..	PAS20670	
00074	0074 00 4 00142	TSX	PRNT1,4	GO PRINT ASSEMBLY LISTING.	PAS20680	
00075	0020 00 0 00022	TRA	NEXT	RETURN.	PAS20690	
00076	-0754 00 0 00000	OCTL	PXD	0,0	SIMPLE OCTAL, CLEAR AC.	PAS20700
00077	0774 00 2 00002		AXT	2,2	2 WORDS.	PAS20710
00100	0774 00 4 00006	OLP	AXT	6,4	6 CHARACTERS PER WORD.	PAS20720
00101	0560 00 2 00300		LDQ	BUFF+2+2,2	GET WORD.	PAS20730
00102	-0773 00 0 00003		RQL	3	BCI-OCTAL CONVERSION.	PAS20740
00103	-0763 00 0 00003		LGL	3	..	PAS20750
00104	2 00001 4 00102		TIK	--2,4,1	COUNT CHARACTERS.	PAS20760
00105	2 00001 2 00100		TIK	OLP,2,1	COUNT WORDS.	PAS20770
00106	0602 00 1 00000	SLW	0,1	INSERT IN ASSEMBLED PROGRAM.	PAS20780	
00107	0074 00 4 00142	TSX	PRNT1,4	GO PRINT ASSEMBLY LISTING.	PAS20790	
00110	1 77777 1 00022	TXI	NEXT,1,-1	INDEX AND RETURN.	PAS20800	
00111	0074 00 4 00173	COMP	TSX	PRNT2,4	PRINT COMP AS A REMARK.	PAS20810
00112	0020 00 0 00022		TRA	NEXT	RETURN.	PAS20820
00113	0074 00 4 00003	END	TSX	\$VAREVL,4	EVALUATE VARIABLE FIELD.	PAS20830
00114	0 00000 0 00274	PZE	BUFF	..	PAS20840	
00115	0601 00 0 00260	STO	EPNT	SAVE AS ENTRY POINT.	PAS20850	

PASS 2 OF CLASS ASSEMBLY PROGRAM.

00116	0074 00 4 00204		TSX	FLAGS,4	GET FLAGS.	PAS20970
00117	0602 00 0 00267		SLW	PBUFF	PLACE IN PBUFF.	PAS20980
00120	0500 00 0 00260		CLA	EPNT	CONVERT ENTRY POINT.	PAS20990
00121	0074 00 4 00225		TSX	OCTA,4	..	PAS21000
00122	0560 00 0 00312		LDQ	=0	CLEAR MQ.	PAS21010
00123	-0765 00 0 00022		LGR	18	SHIFT TO POSITION.	PAS21020
00124	-0501 00 0 00316		ORA	=H 000	INSERT BLANKS LEFT.	PAS21030
00125	0602 00 0 00272		SLW	PBUFF+3	INSERT IN PBUFF.	PAS21040
00126	-0130 00 0 00000		XCL		GET RIGHT HALF.	PAS21050
00127	-0501 00 0 00315		ORA	=H000	INSERT BLANKS RIGHT.	PAS21060
00130	0602 00 0 00273		SLW	PBUFF+4	INSERT IN PBUFF.	PAS21070
00131	-0500 00 0 00317		CAL	=H	BLANK OUT REST OF PBUFF.	PAS21080
00132	0602 00 0 00270		SLW	PBUFF+1	..	PAS21090
00133	0602 00 0 00271		SLW	PBUFF+2	..	PAS21100
00134	0074 00 4 00005		TSX	\$PRINT,4	GO PRINT.	PAS21110
00135	0 00023 0 00267		PZE	PBUFF,0,19	..	PAS21120
00136	0774 00 4 00000	RX4	AXT	**,*4	RESTORE IR4.	PAS21130
00137	0500 00 0 00260		CLA	EPNT	GET ENTRY.	PAS21140
00140	0442 00 0 00263		OSI	FLGSM	GET TOTAL ERROR FLAGS.	PAS21150
00141	0020 00 4 00001		TRA	1,4	RETURN.	PAS21160

		SPACE	2	PRINT ROUTINES.		
00142	0634 00 4 00171	PRNT1	SXA	P1X4,4	SAVE IR4.	PAS21170
00143	0074 00 4 00204		TSX	FLAGS,4	GET ERROR FLAGS.	PAS21180
00144	0602 00 0 00267		SLW	PBUFF	PLACE IN PBUFF.	PAS21190
00145	0535 00 4 00257		LAC	LOC,4	GET +(ILC).	PAS21200
00146	0754 00 4 00000		PXA	0,4	..	PAS21210
00147	0074 00 4 00225		TSX	OCTA,4	CONVERT OCTAL ADDRESS.	PAS21220
00150	0602 00 0 00270		SLW	PBUFF+1	PLACE IN PBUFF.	PAS21230
00151	0534 00 4 00257		LXA	LOC,4	GET -(ILC).	PAS21240
00152	-0500 00 4 00000		CAL	0,4	GET ASSEMBLED WORD.	PAS21250
00153	0074 00 4 00236		TSX	OCTW,4	CONVERT OCTAL WORD.	PAS21260
00154	-0600 00 0 00262		STQ	RHOCT	SAVE RIGHT HALF.	PAS21270
00155	-0765 00 0 00022		LGR	18	SHIFT TO POSITION.	PAS21280
00156	-0501 00 0 00316		ORA	=H 000	INSERT BLANKS LEFT.	PAS21290
00157	0602 00 0 00271		SLW	PBUFF+2	PLACE IN PBUFF.	PAS21300
00160	-0600 00 0 00272		STQ	PBUFF+3	..	PAS21310
00161	-0500 00 0 00262		CAL	RHOCT	GET RIGHT HALF.	PAS21320
00162	0560 00 0 00312		LDQ	=0	ZERO MQ.	PAS21330
00163	-0765 00 0 00022		LGR	18	SHIFT TO POSITION.	PAS21340
00164	-0130 00 0 00000		XCL		PLACE IN AC.	PAS21350
00165	-0501 00 0 00315		ORA	=H000	INSERT BLANKS RIGHT.	PAS21360
00166	0602 00 0 00273		SLW	PBUFF+4	PLACE IN PBUFF.	PAS21370
00167	0074 00 4 00005		TSX	\$PRINT,4	GO PRINT.	PAS21380
00170	0 00023 0 00267		PZE	PBUFF,0,19	..	PAS21390
00171	0774 00 4 00000	P1X4	AXT	**,*4	RESTORE IR4.	PAS21400
00172	0020 00 4 00001		TRA	1,4	RETURN.	PAS21410
00173	0634 00 4 00202	PRNT2	SXA	P2X4,4	SAVE IR4.	PAS21420
00174	0774 00 4 00005		AXT	5,4	BLANK OUT PBUFF TO PBUFF+4.	PAS21430
00175	-0500 00 0 00317		CAL	=H	..	PAS21440
00176	0602 00 4 00274		SLW	PBUFF+5,4	..	PAS21450
00177	2 00001 4 00176		TIX	*-1,4,1	..	PAS21460

PASS 2 OF CLASS ASSEMBLY PROGRAM.

00200	0074 00 4 00005		TSX	\$PRINT,4	GO PRINT.	PAS21510
00201	0 00023 0 00267	P2X4	PZE	PBUFF,0,19	..	PAS21520
00202	0774 00 4 00000		AXT	**,4	RESTORE IR4.	PAS21530
00203	0020 00 4 00001		TRA	1,4	RETURN.	PAS21540
		SPACE	2		BCI CONVERSION ROUTINES.	PAS21550
00204	0634 00 4 00223	FLAGS	SXA	FLX4,4	SAVE IR4.	PAS21560
00205	0140 00 0 00206		TOV	**+1	TURN OFF OVERFLOW LIGHT.	PAS21570
00206	-0046 00 0 00000		PIA		GET ERROR FLAGS.	PAS21580
00207	-0765 00 0 00003		LGR	NFLGS	SHIFT TO MQ.	PAS21590
00210	-0500 00 0 00314		CAL	=H00001	BLANK FOR CARRIAGE CONTROL.	PAS21600
00211	0774 00 4 00003		AXT	NFLGS,4	CONVERT FLAGS.	PAS21610
00212	0162 00 0 00215		TQP	**+3	IF PLUS, NO FLAG.	PAS21620
00213	0767 00 0 00006		ALS	6	INSERT FLAG.	PAS21630
00214	0361 00 4 00267		ACL	TFLGS+NFLGS,4	..	PAS21640
00215	-0773 00 0 00001		RQL	1	CHECK NEXT BIT.	PAS21650
00216	2 00001 4 00212		TIK	**-4,4,1	INDEX.	PAS21660
00217	0560 00 0 00317		LDQ	=H	FILL IN BLANKS ON RIGHT.	PAS21670
00220	0140 00 0 00223		TOV	**+3	..	PAS21680
00221	-0763 00 0 00006		LGL	6	..	PAS21690
00222	-0140 00 0 00221		TNO	**-1	..	PAS21700
00223	0774 00 4 00000	FLX4	AXT	**,4	RESTORE IR4.	PAS21710
00224	0020 00 4 00001		TRA	1,4	RETURN.	PAS21720
00225	0634 00 4 00234	OCTA	SXA	OAX4,4	SAVE IR4.	PAS21730
00226	-0765 00 0 00017		LGR	15	SHIFT TO MQ.	PAS21740
00227	-0500 00 0 00313		CAL	=H00000	FIRST, A BLANK.	PAS21750
00230	0774 00 4 00005		AXT	5,4	5 DIGITS.	PAS21760
00231	0767 00 0 00003		ALS	3	CONVERT TO BCI.	PAS21770
00232	-0763 00 0 00003		LGL	3	..	PAS21780
00233	2 00001 4 00231		TIK	**-2,4,1	..	PAS21790
00234	0774 00 4 00000	OAX4	AXT	**,4	RESTORE IR4.	PAS21800
00235	0020 00 4 00001		TRA	1,4	RETURN.	PAS21810
00236	0634 00 4 00255	OCTW	SXA	OWX4,4	SAVE IR4.	PAS21820
00237	-0130 00 0 00000		XCL		PLACE IN MQ.	PAS21830
00240	-0754 00 0 00000		PXD	0,0	FIRST HALF, CLEAR AC.	PAS21840
00241	0774 00 4 00006		AXT	6,4	6 DIGITS.	PAS21850
00242	0767 00 0 00003		ALS	3	CONVERT.	PAS21860
00243	-0763 00 0 00003		LGL	3	..	PAS21870
00244	2 00001 4 00242		TIK	**-2,4,1	..	PAS21880
00245	0602 00 0 00261		SLW	LHOCT	SAVE LEFT HALF.	PAS21890
00246	-0754 00 0 00000		PXD	0,0	LAST HALF, CLEAR AC.	PAS21900
00247	0774 00 4 00006		AXT	6,4	6 DIGITS.	PAS21910
00250	0767 00 0 00003		ALS	3	CONVERT.	PAS21920
00251	-0763 00 0 00003		LGL	3	..	PAS21930
00252	2 00001 4 00250		TIK	**-2,4,1	..	PAS21940
00253	-0130 00 0 00000		XCL		FORM COMPLETE RESULT.	PAS21950
00254	-0500 00 0 00261		CAL	LHOCT	..	PAS21960
00255	0774 00 4 00000	OWX4	AXT	**,4	RESTORE IR4.	PAS21970
00256	0020 00 4 00001		TRA	1,4	RETURN.	PAS21980

PASS 2 OF CLASS ASSEMBLY PROGRAM.

	SPACE	2		
		STORAGE AND CONSTANTS.		
00257	0 00000 0 00000	LOC PZE	-(ILC) BEFORE CONVERSIONS.	PAS22030
00260	0 00000 0 00000	EPNT PZE	ENTRY POINT FROM END CARD.	PAS22040
00261	0 00000 0 00000	LHOCT PZE	LEFT HALF OF OCTAL-BCI.	PAS22050
00262	0 00000 0 00000	RHOCT PZE	RIGHT HALF OF OCTAL-BCI.	PAS22060
00263	0 00000 0 00000	FLGSM PZE	TOTAL ERROR FLAGS.	PAS22070
	00264	TFLGS SYN *	TABLE OF ERROR FLAGS.	PAS22080
00265	000000000025	BCI 1,000000	SI BIT 33.	PAS22090
00266	000000000046	BCI 1,000000	SI BIT 34.	PAS22100
	00003	NFLGS EQU *-TFLGS	SI BIT 35.	PAS22110
	00267	PBUFF BSS 19	NUMBER OF ERROR FLAGS.	PAS22120
	00274	BUFF SYN PBUFF+5	PRINT BUFFER.	PAS22130
			START OF CARD IMAGE BUFFER.	PAS22140
		END		PAS22150
				PAS22160
				PAS22170
				PAS22180
				PAS22190
				PAS22200
				PAS22210

LITERALS

00312	000000000000
00313	000000000060
00314	000000000160
00315	000000606060
00316	606060000000
00317	606060606060

PASS 2 OF CLASS ASSEMBLY PROGRAM.  
POST PROCESSOR ASSEMBLY DATA

320 IS THE FIRST LOCATION NOT USED BY THIS PROGRAM

REFERENCES TO DEFINED SYMBOLS

113	END	67
72	INT	61
257	LCC	25, 145, 151
100	OLP	105
70	REM	57
136	RX4	10
274	BUFF	27, 30, 52, 73, 101, 114, 312
111	COMP	65
260	EPNT	115, 120, 137
223	FLX4	204
22	NEXT	55, 71, 75, 110, 112
234	OAX4	225
225	OCTA	121, 147
76	OCTL	63
236	OCTW	153
30	OFLD	
255	OWX4	236
171	P1X4	142
202	P2X4	173
56	PTBL	33, 35, 70
2	SCAN	31
204	FLAGS	116, 143
263	FLGSM	21, 22, 23, 140
4	INTOP	72
261	LHOCT	245, 254
3	NFLGS	207, 211, 214, 267
12	NPTBL	32, 33, 35, 70
37	OPAXT	14
47	OPFND	17, 42, 46
40	OPLAS	16
0	OPTBL	12, 15
10	PASS2	
267	PBUFF	117, 125, 130, 132, 133, 135, 144, 150, 157, 160, 166, 170, 176, 201, 312
5	PRINT	134, 167, 200
142	PRNT1	54, 74, 107
173	PRNT2	70, 111
1	READ2	26
262	RHOCT	154, 161
264	TFLGS	214, 264, 267
3	VAREVL	51, 113

NO ERROR IN ABOVE ASSEMBLY.  
\*TIME SPENT IN FAP.. 000009 IN HUNDREDS OF MINUTES.

\$VAREVL, SCAN AND EVALUATE VARIABLE FIELD OF CAP CARD.

	PCC				
	COUNT	222			VEVL0010
00034	LBL	VAREVL	BINARY CARD LABEL.		VEVL0020
00005	ENTRY	RVREVL	EVALUATE FIELDS BETWEEN COMMAS.		VEVL0030
	ENTRY	VAREVL	EVALUATE FIRST FIELD.		VEVL0050
					VEVL0060
TRANSFER VECTOR					
00000	627044272563	SYMGET			
00001	622165256060	SAVE			
00002	644562216525	UNSAVE			
LINKAGE DIRECTOR					
00003	000000000000				
00004	516551256543				
00005	0634 00 4 00030	VAREVL	SXA RX4,4	SAVE IRS.	VEVL0070
00006	0634 00 2 00031		SXA RX2,2	..	VEVL0080
00007	0634 00 1 00032		SXA RX1,1	..	VEVL0090
00010	-0500 00 4 00001	CAL	1,4	GET BUFFER ADDRESS.	VEVL0100
00011	0361 00 0 00254	ACL	=12	BUFF+12.	VEVL0110
00012	0621 00 0 00063	STA	LDQ	SAVE FOR PICKUP.	VEVL0120
00013	0600 00 0 00245	STZ	TEOF	RESET EOF MARK.	VEVL0130
00014	0600 00 0 00246	STZ	TCOM	RESET COMMA MARK.	VEVL0140
00015	-0760 00 0 00141	SLT	1	TURN OFF LIGHT 1.	VEVL0150
00016	0761 00 0 00000	NOP		..	VEVL0160
00017	0774 00 2 00012	AXT	10,2	COUNT 10 WORDS.	VEVL0170
00020	0774 00 1 00007	AXT	7,1	COUNT 6 CHARACTERS.	VEVL0180
00021	0560 60 0 00063	LDQ*	LDQ	GET FIRST WORD OF VARIABLE FIELD.	VEVL0190
00022	-0600 00 0 00252	STQ	MQ	SAVE FOR EVAL.	VEVL0200
00023	0074 00 4 00052	GEVAL	TSX EVAL,4	GO EVALUATE FIELD.	VEVL0210
00024	0734 00 4 00000		PAX 0,4	PLACE RESULT IN IR4.	VEVL0220
00025	0120 00 0 00027	TPL	*+2	PLUS OR MINUS.	VEVL0230
00026	0737 00 4 00000	PAC	0,4	MINUS, FORM 2S COMPLEMENT.	VEVL0240
00027	0754 00 4 00000	PXA	0,4	FINAL RESULT IN A(AC).	VEVL0250
00030	0774 00 4 00000	RX4	AXT **,4	RESTORE IRS.	VEVL0260
00031	0774 00 2 00000	RX2	AXT **,2	..	VEVL0270
00032	0774 00 1 00000	RX1	AXT **,1	..	VEVL0280
00033	0020 00 4 00002		TRA 2,4	RETURN WITH RESULT IN AC.	VEVL0290
	SPACE	2			
			RE-ENTRY TO EVALUATE MULTIPLE FIELDS.		
00034	-0754 00 0 00000	RVREVL	PXD 0,0	CLEAR AC.	VEVL0300
00035	-0520 00 0 00246		NZT TCOM	CHECK FOR COMMA ENCOUNTERED.	VEVL0310
00036	0020 00 4 00001		TRA 1,4	NO, EXIT WITH ZERO.	VEVL0320
00037	0600 00 0 00245	STZ TECF		RESET EOF MARK.	VEVL0330
00040	0600 00 0 00246	STZ TCOM		RESET COMMA MARK.	VEVL0340
00041	-0760 00 0 00141	SLT 1		TURN OFF LIGHT 1.	VEVL0350
00042	0761 00 0 00000	NOP		..	VEVL0360
00043	1 00001 4 00044	TX1 *+1,4,1		DECREASE CALL LOCATION BY ONE.	VEVL0370
00044	0634 00 4 00030	SXA RX4,4		SAVE IRS.	VEVL0380
00045	0634 00 2 00031	SXA RX2,2		..	VEVL0390
00046	0634 00 1 00032	SXA RX1,1		..	VEVL0400
00047	0774 00 1 00000	REX1 AXT **,1		RESTORE IRS FOR POSITION IN FIELD.	VEVL0410
00050	0774 00 2 00000	REX2 AXT **,2		..	VEVL0420

**\$VAREVL, SCAN AND EVALUATE VARIABLE FIELD OF CAP CARD.**

00051	0020 00 0 00023	TRA	GEVAL	GO EVALUATE THIS FIELD.	VEVL0460
		SPACE	2	EVALUATION SUBROUTINE, RECURSIVELY DEFINED.	VEVL0470
00052	0634 00 4 00243	EVAL	SXA	EVX4,4 SAVE IR4.	VEVL0480
00053	0600 00 0 00241		STZ	SUM INITIALIZE REGISTERS.	VEVL0490
00054	0600 00 0 00242		STZ	TERM ..	VEVL0500
00055	0600 00 0 00251		STZ	VAL ..	VEVL0510
00056	0600 00 0 00250		STZ	SYM RESET SYM.	VEVL0520
00057	0774 00 4 00025		AXT	NPL,4 SET LBKCH TO PLUS.	VEVL0530
00060	0634 00 4 00244		SXA	LBKCH,4 ..	VEVL0540
00061	0020 00 0 00100		TRA	RSCAN GO TO SCANNER.	VEVL0550
00062	0774 00 1 00006	SCAN	AXT	6,1 COUNT 6 CHARACTERS.	VEVL0560
00063	0560 00 2 00000	LDQ	LDQ	**,2 PICKUP NEXT WORD. ADDRESS IS BUFF+12.	VEVL0570
00064	-0754 00 0 00000	CHAR	PXD	0,0 CLEAR AC.	VEVL0580
00065	-0763 00 0 00006		LGL	6 GET CHARACTER.	VEVL0590
00066	-0600 00 0 00252		STQ	MQ SAVE MQ.	VEVL0600
00067	0774 00 4 00025		AXT	NBK,4 COMPARE WITH LIST OF BREAKS.	VEVL0610
00068	-0340 00 4 00136		LAS	TABBK+NBK,4 ..	VEVL0620
00069	0020 00 0 00073		TRA	*+2 NOT THIS ONE, SKIP.	VEVL0630
00070	0020 00 0 00136		TRA	BKCH BREAK FOUND, EXIT.	VEVL0640
00071	0020 00 0 00073		TIX	*-3,4,3 NOT THIS ONE, INDEX AND TRY AGAIN.	VEVL0650
00072	0020 00 0 00136		TRA	BKCH NOT A BREAK, BUILD SYMBOL.	VEVL0660
00073	2 00003 4 00070		TIX	6 ..	VEVL0670
00074	-0765 00 0 00006		LGR	6 ..	VEVL0680
00075	-0500 00 0 00250		CAL	SYM SAVE PARTIAL SYMBOL.	VEVL0690
00076	-0763 00 0 00006		LGL	6 TEST FOR END-OF-FIELD.	VEVL0700
00077	0602 00 0 00250		SLW	SYM YES, EXIT TO RPAR SECTION.	VEVL0710
00100	0520 00 0 00245	RSCAN	ZET	EOF NO, RESTORE MQ.	VEVL0720
00101	0020 00 0 00106		TRA	EOFB COUNT CHARACTERS.	VEVL0730
00102	0560 00 0 00252		LDQ	MQ COUNT WORDS.	VEVL0740
00103	2 00001 1 00064		TIX	CHAR,1,1 SCAN,2,1	VEVL0750
00104	2 00001 2 00062		TIX	TECF END-OF-FIELD REACHED, APPEND AS	VEVL0760
00105	-0625 00 0 00245		STL	NRPAR,4 MANY RPAR AS NECESSARY.	VEVL0770
00106	0774 00 4 00003	EOFB	AXT	=H000C0)	VEVL0780
00107	-0500 00 0 00255		CAL	..	VEVL0790
00110	0020 00 0 00136		TRA	BKCH GO TO BREAK.	VEVL0800
		SPACE	2	TABLE OF BREAKS.	VEVL0810
	00111	TABBK SYN	*		VEVL0820
00111	000000000020	CPL	BC I	1,00000+ PLUS.	VEVL0830
00112	0020 00 0 00172		TRA	LPL ..	VEVL0840
00113	0020 00 0 00210		TRA	RPL ..	VEVL0850
00114	0000000000C40		BC I	1,00000- MINUS.	VEVL0860
00115	0020 00 0 00175		TRA	LMI ..	VEVL0870
00116	0020 00 0 00210		TRA	RMI ..	VEVL0880
00117	0000000000054		BC I	1,00000* STAR.	VEVL0890
00120	0020 00 0 00200		TRA	LST ..	VEVL0900
00121	0020 00 0 00215		TRA	RST ..	VEVL0910
00122	0000000000060		BC I	1,00000 BLANK.	VEVL0920
00123	0000 60 0 00123		HTR*	*	VEVL0930
				SHOULD NEVER GET HERE.	VEVL0940
					VEVL0950
					VEVL0960
					VEVL0970

\$VAREVL, SCAN AND EVALUATE VARIABLE FIELD OF CAP CARD.

00124	0020 00 0 00237		TRA	BLANK	..	VEVL0980
00125	000000000073		BCI	1,00000,	COMMA.	VEVL0990
00126	0000 60 0 00126		HTR*	*	SHOULD NEVER GET HERE.	VEVL1000
00127	0020 00 0 00231		TRA	RCOM	..	VEVL1010
00130	000000000074		BCI	1,00000(	LPAR.	VEVL1020
00131	0000 60 0 00131		HTR*	*	SHOULD NEVER GET HERE.	VEVL1030
00132	0020 00 0 00216		TRA	LPAR	..	VEVL1040
00133	000000000034	CRPAR	BCI	1,00000)	RPAR.	VEVL1050
00134	0000 60 0 00134		HTR*	*	SHOULD NEVER GET HERE.	VEVL1060
00135	0020 00 0 00225		TRA	RPAR	..	VEVL1070
	00025	NBK	EQU	--TABBK	NUMBER OF BREAK CHARACTERS.	VEVL1080
	00003	NRPAR	EQU	--CRPAR	BREAK NUMBER OR RPAR.	VEVL1090
	00025	NPL	EQU	--CPL	BREAK NUMBER OF PLUS.	VEVL1100
			SPACE	2		VEVL1110
					BREAK CHARACTER SECTION.	
00136	0634 00 4 00247	BKCH	SXA	RBKCH,4	SAVE NUMBER OF RIGHT BREAK.	VEVL1120
00137	-0340 00 0 00256		LAS	=H00000(	CHECK FOR LPAR.	VEVL1130
00140	0020 00 0 00142		TRA	*+2	NO, SKIP.	VEVL1140
00141	0020 00 0 00216		TRA	LPAR	YES, GO TO IT.	VEVL1150
00142	0520 00 0 00251		ZET	VAL	EXPRESSION, SYMBOL, OR NUMBER.	VEVL1160
00143	0020 00 0 00167		TRA	LBK	EXPRESSION, NO SYMBOL TO CONVERT.	VEVL1170
00144	-0500 00 0 00250		CAL	SYM	SYMBOL OR NUMBER.	VEVL1180
00145	-0320 00 0 00257		ANA	=H	NUMBERS HAVE NO ZONE.	VEVL1190
00146	0100 00 0 00153		TZE	NUM	NUMBER, GO CONVERT.	VEVL1200
00147	-0500 00 0 00250		CAL	SYM	SYMBOL, GET VALUE.	VEVL1210
00150	0074 00 4 00000		TSX	\$SYMGET,4	..	VEVL1220
00151	0601 00 0 00251		STO	VAL	SAVE VALUE.	VEVL1230
00152	0020 00 0 00167		TRA	LBK	EXIT TO LBK.	VEVL1240
00153	0560 00 0 00250	NUM	LDQ	SYM	NUMBER, UNSIGNED.	VEVL1250
00154	0774 00 4 00006		AXT	6,4	COUNT 6 DIGITS.	VEVL1260
00155	-0754 00 0 00000	NLOOP	PXD	0,0	CLEAR AC.	VEVL1270
00156	-0763 00 0 00006		LGL	6	GET DIGIT.	VEVL1280
00157	0601 00 0 00253		STO	DIG	SAVE.	VEVL1290
00160	0500 00 0 00251		CLA	VAL	PROGRAMED 10*VAL.	VEVL1300
00161	0767 00 0 00002		ALS	2	4*VAL.	VEVL1310
00162	0400 00 0 00251		ADD	VAL	4*VAL+VAL.	VEVL1320
00163	0767 00 0 00001		ALS	1	2*(4*VAL+VAL)=10*VAL.	VEVL1330
00164	0400 00 0 00253		ADD	DIG	ADD THIS DIGIT.	VEVL1340
00165	0601 00 0 00251		STO	VAL	SAVE PARTIAL RESULT.	VEVL1350
00166	2 00001 4 00155		TIX	NLCOP,4,1	COUNT DIGITS CONVERTED.	VEVL1360
			SPACE	2		VEVL1370
					LEFT BREAK SECTION	
00167	0600 00 0 00250	LBK	STZ	SYM	LEFT BREAK, RESET SYM.	VEVL1380
00170	0534 00 4 00244		LXA	LBKCH,4	GET NUMBER OF LEFT BREAK.	VEVL1390
00171	0020 00 4 00137		TRA	TABBK+NBK+1,4	GO TO LEFT BREAK.	VEVL1400
00172	0500 00 0 00251	LPL	CLA	VAL	+, TERM=VAL.	VEVL1410
00173	0601 00 0 00242		STO	TERM	..	VEVL1420

**\$VAREVL, SCAN AND EVALUATE VARIABLE FIELD OF CAP CARD.**

00174	0020 00 0 00204		TRA	RBK	GO TO RIGHT BREAK.	VEVL1500 VEVL1510 VEVL1520 VEVL1530 VEVL1540 VEVL1550 VEVL1560 VEVL1570 VEVL1580 VEVL1590
00175	0502 00 0 00251	LMI	CLS	VAL	-, TERM=-VAL.	
00176	0601 00 0 00242		STO	TERM	..	
00177	0020 00 0 00204		TRA	RBK	GO TO RIGHT BREAK.	
00200	0560 00 0 00251	LST	LDQ	VAL	*, TERM=TERM*VAL.	
00201	0200 00 0 00242		MPY	TERM	..	
00202	-0600 00 0 00242		STQ	TERM	..	
00203	0020 00 0 00204		TRA	RBK	GO TO RIGHT BREAK.	
			SPACE	2	RIGHT BREAK SECTION.	VEVL1600 VEVL1610 VEVL1620 VEVL1630 VEVL1640 VEVL1650 VEVL1660 VEVL1670 VEVL1680 VEVL1690 VEVL1700 VEVL1710 VEVL1720 VEVL1730 VEVL1740 VEVL1750 VEVL1760
00204	0534 00 4 00247	RBK	LXA	RBKCH,4	GET NUMBER OF RIGHT BREAK.	
00205	0634 00 4 00244		SXA	LBKCH,4	THIS IS NEXT LEFT BREAK.	
00206	0600 00 0 00251		STZ	VAL	RESET VAL.	
00207	0020 00 4 00140		TRA	TABBK+NBK+2,4	GO TO RIGHT BREAK.	
00210	0500 00 0 00241	RPL	CLA	SUM	+, SUM=SUM+TERM.	
00211	0400 00 0 00242		ADD	TERM	..	
00212	0601 00 0 00241		STO	SUM	..	
00213	0600 00 0 00242		STZ	TERM	RESET TERM.	
00214	0020 00 0 00100		TRA	RSCAN	RESUME SCAN.	
	00210	RMI	SYN	RPL	-, SAME AS +.	
00215	0020 00 0 00100	RST	TRA	RSCAN	*, RESUME SCAN.	
			SPACE	2	LPAR, RPAR, AND EOF SECTION.	VEVL1770 VEVL1780 VEVL1790 VEVL1800 VEVL1810 VEVL1820 VEVL1830 VEVL1840 VEVL1850 VEVL1860 VEVL1870 VEVL1880 VEVL1890 VEVL1900 VEVL1910 VEVL1920 VEVL1930 VEVL1940 VEVL1950 VEVL1960 VEVL1970 VEVL1980 VEVL1990 VEVL2000 VEVL2010
00216	0074 00 4 00001	LPAR	TSX	\$SAVE,4	{, SAVE REGISTERS.	
00217	0 00004 0 00241		PZE	SUM,0,4	..	
00220	0074 00 4 00052		TSX	EVAL,4	CALL SELF.	
00221	0601 00 0 00251		STO	VAL	RESULT IS VAL.	
00222	0074 00 4 00002		TSX	\$UNSAVE,4	RESTORE REGISTERS.	
00223	0 00004 0 00241		PZE	SUM,0,4	..	
00224	0020 00 0 00100		TRA	RSCAN	RESUME SCAN.	
00225	0500 00 0 00241	RPAR	CLA	SUM	}, END OF EXPRESSION, GET SUM.	
00226	0400 00 0 00242		ADD	TERM	ADD IN CURRENT TERM.	
00227	0534 00 4 00243		LXA	EVX4,4	RESTORE IR4.	
00230	0020 00 4 00001		TRA	1,4	RETURN TO CALLER.	
00231	-0625 00 0 00246	RCOM	STL	TCOM	SET MARK FOR COMMA ENCOUNTERED.	
00232	-0625 00 0 00245		STL	TEOF	SET MARK FOR EOF.	
00233	0760 00 0 00141		SLN	1	EXTERNAL MARK FOR COMMA ENCOUNTERED.	
00234	0634 00 1 00047		SXA	REX1,1	SAVE IRS FOR RE-SCAN.	
00235	0634 00 2 00050		SXA	REX2,2	..	
00236	0020 00 0 00225		TRA	EOF	GO TO ECF SECTION.	
00237	-0625 00 0 00245	BLANK	STL	TEOF	END-OF-FIELD.	
00240	0020 00 0 00225		TRA	EOF	..	

\$VAREVL, SCAN AND EVALUATE VARIABLE FIELD OF CAP CARD.

00225	EOF	SYN	RPAR	SAME AS RPAR.	VEVL2020 VEVL2030
SPACE 2 STORAGE AREA FOR SAVE.					VEVL2040 VEVL2050
00241	0 00000 0 00000	SUM	PZE	..	VEVL2060
00242	0 00000 0 00000	TERM	PZE	..	VEVL2070
00243	0 00000 0 00000	EVX4	PZE	..	VEVL2080
00244	0 00000 0 00000	LBKCH	PZE	..	VEVL2090 VEVL2100
SPACE 2 TEMPORARY STORAGE.					VEVL2110 VEVL2120
00245	0 00000 0 00000	TEOF	PZE	..	VEVL2130
00246	0 00000 0 00000	TCOM	PZE	..	VEVL2140
00247	0 00000 0 00000	RBKCH	PZE	..	VEVL2150
00250	0 00000 0 00000	SYM	PZE	..	VEVL2160
00251	0 00000 0 00000	VAL	PZE	..	VEVL2170
00252	0 00000 0 00000	MQ	PZE	..	VEVL2180
00253	0 OCCOC 0 00000	DIG	PZE	..	VEVL2190 VEVL2200 VEVL2210 VEVL2220
END					
LITERALS					
00254	000000000014				
00255	000000000034				
00256	000000000074				
00257	606060606060				

\$VAREVL, SCAN AND EVALUATE VARIABLE FIELD OF CAP CARD.  
POST PROCESSOR ASSEMBLY DATA

260 IS THE FIRST LOCATION NOT USED BY THIS PROGRAM

REFERENCES TO DEFINED SYMBOLS

252	MQ	22,	66,	102								
111	CPL	136										
253	DIG	157,	164									
225	EOF	236,	240,	241								
167	LBK	143,	152									
63	LCQ	12,	21									
175	LMI	115										
172	LPL	112										
200	LST	120										
25	NBK	67,	70,	136,	171,	207						
25	NPL	57,	136									
153	NUM	146										
204	RBK	174,	177,	203								
210	RMI	116,	215									
210	RPL	113,	215									
215	RST	121										
32	RX1	7,	46									
31	RX2	6,	45									
30	RX4	5,	44									
241	SUM	53,	210,	212,	217,	223,	225					
250	SYM	56,	75,	77,	144,	147,	153,	167				
251	VAL	55,	142,	151,	160,	162,	165,	172,	175,	200,	206,	221
136	BKCH	72,	110									
64	CHAR	103										
106	EOF8	101										
52	EVAL	23,	220									
243	EVX4	52,	227									
216	LPAR	132,	141									
231	RCOM	127										
47	REX1	234										
50	REX2	235										
225	RPAR	135,	241									
1	SAVE	216										
62	SCAN	104										
246	TCOM	14,	35,	40,	231							
245	TEOF	13,	37,	100,	105,	232,	237					
242	TERM	54,	173,	176,	201,	202,	211,	213,	226			
237	BLANK	124										
133	CRPAR	136										
23	GEVAL	51										
244	LBKCH	60,	170,	205								
155	NLCCP	166										
3	NRPAR	106,	136									
247	RBKCH	136,	204									
100	RSCAN	61,	214,	215,	224							
111	TABBK	70,	111,	136,	171,	207						
34	RVREVL											
0	SYMGET	150										
2	UNSAVE	222										
5	VAREVL											

NO ERROR IN ABOVE ASSEMBLY.  
\*TIME SPENT IN FAP.. 000010 IN HUNDREDTHS OF MINUTES.

OPERATION TABLE FOR CAP.

		PCC COUNT LBL ENTRY	79 OPTBL OPTBL	BINARY CARD LABEL. ENTRY TO POINTER WORD.	OPTB0010 OPTB0020 OPTB0040 OPTB0050
00002					
<p>LINKAGE DIRECTOR</p> <p>00000 000000000000</p> <p>00001 464763224360</p>					
00002	0 00104 0 00003	OPTBL PZE	*+1,0,LTH	CONTROL WORD.	OPTB0060
00003	000000212343	BCI	1,000ACL	CAP MNEMONIC.	OPTB0070
00004	+036100000000	OCT	03610C000C00	7090 INSTRUCTION.	OPTB0080
00005	000000214521	BCI	1,CC0ANA		OPTB0090
00006	-032000000000	OCT	43200C000000		OPTB0100
00007	000000232143	BCI	1,000CAL		OPTB0110
00010	-050000000000	OCT	450000000000		OPTB0120
00011	000000233062	BCI	1,C00CHS		OPTB0130
00012	+076000000002	OCT	076000000002		OPTB0140
00013	000000234321	BCI	1,000CLA		OPTB0150
00014	+050000000000	OCT	050000000000		OPTB0160
00015	000000234362	BCI	1,000CLS		OPTB0170
00016	+050200000000	OCT	05C20C000000		OPTB0180
00017	000000234644	BCI	1,000COM		OPTB0190
00020	+076000000006	OCT	07600C000006		OPTB0200
00021	000000262124	BCI	1,C00FAD		OPTB0210
00022	+030000000000	OCT	03000C000000		OPTB0220
00023	000000262447	BCI	1,000FDP		OPTB0230
00024	+02410000C000	OCT	02410C000000		OPTB0240
00025	000000264447	BCI	1,C00FMP		OPTB0250
00026	+026000000000	OCT	026000000000		OPTB0260
00027	000000266222	BCI	1,000FSB		OPTB0270
00030	+030200000000	OCT	03C20C000000		OPTB0280
00031	000000432123	BCI	1,000LAC		OPTB0290
00032	+053500400000	OCT	053500400000		OPTB0300
00033	000000432162	BCI	1,000LAS		OPTB0310
00034	-034000000000	OCT	43400C000000		OPTB0320
00035	000000432263	BCI	1,CC0LBT		OPTB0330
00036	+076000000001	OCT	07600C000001		OPTB0340
00037	000000432450	BCI	1,000LDQ		OPTB0350
00040	+056000000000	OCT	05600C000000		OPTB0360
00041	000000432743	BCI	1,COOLGL		OPTB0370
00042	-076300000000	OCT	476300000000		OPTB0380
00043	000000432751	BCI	1,000LGR		OPTB0390
00044	-076500000000	OCT	47650C000000		OPTB0400
00045	000000436721	BCI	1,COOLXA		OPTB0410
00046	+053400400000	OCT	053400400000		OPTB0420
00047	000000465121	BCI	1,0000RA		OPTB0430
00050	-050100000000	OCT	450100000000		OPTB0440
00051	000000472263	BCI	1,000PBT		OPTB0450
00052	-076000000001	OCT	476000000C01		OPTB0460
00053	000000515043	BCI	1,000RQL		OPTB0470
00054	-077300000000	OCT	477300000C00		OPTB0480
00055	000000624366	BCI	1,C00SLW		OPTB0490
00056	+060200000000	OCT	060200000000		OPTB0500
00057	000000626346	BCI	1,000STO		OPTB0510
					OPTB0520

## OPERATION TABLE FOR CAP.

68

00060	+060100000000	OCT	060100000000	OPTB0530
00061	000000626350	BCI	1,000STQ	OPTB0540
00062	-060000000000	OCT	46000C000C00	OPTB0550
00063	000000626721	BCI	1,000SX <sub>A</sub>	OPTB0560
00064	+063400400000	OCT	063400400000	OPTB0570
00065	000000633167	BCI	1,000TIX	OPTB0580
00066	+200001400000	OCT	200001400C00	OPTB0590
00067	000000634431	BCI	1,C00TM <sub>I</sub>	OPTB0600
00070	-012000000000	OCT	412000000000	OPTB0610
00071	000000634743	BCI	1,000TPL	OPTB0620
00072	+012000000000	OCT	012000000000	OPTB0630
00073	000000635047	BCI	1,C00TQP	OPTB0640
00074	+016200000000	OCT	016200000000	OPTB0650
00075	000000635121	BCI	1,000TRA	OPTB0660
00076	+002000000000	OCT	002000000C00	OPTB0670
00077	000000636267	BCI	1,C00TSX	OPTB0680
00100	+007400400000	OCT	007400400000	OPTB0690
00101	000000637125	BCI	1,000TZE	OPTB0700
00102	+010000000000	OCT	01000C000000	OPTB0710
00103	000000672321	BCI	1,C00XCA	OPTB0720
00104	+013100000000	OCT	013100000000	OPTB0730
00105	000000672343	BCI	1,000XCL	OPTB0740
00106	-013000000C00	OCT	413000000000	OPTB0750
00104	LTH	EQU	*-OPTBL-1	2*(NUMBER OF ALLOWED OPERATIONS).
END				

## POST PROCESSOR ASSEMBLY DATA

107 IS THE FIRST LOCATION NOT USED BY THIS PROGRAM

REFERENCES TO DEFINED SYMBOLS  
 104 LTH 2, 107  
 2 OPTBL 107

NO ERROR IN ABOVE ASSEMBLY.  
 \*TIME SPENT IN FAP.. 000004 IN HUNDREDTHS OF MINUTES.

INTOP, EVALUATE INT PSEUDO-OP.

	PCC COUNT LBL ENTRY	99 INTOP INTOP	BINARY CARD LABEL. PSEUDO-OP 'INT' EVALUATOR.	INTP0010 INTP0020 INTP0040 INTP0050	
00002					
LINKAGE DIRECTOR					
00000	000000000000				
00001	314563464760				
00002	0634 00 4 00112	INTCP SXA	RX4,4	SAVE IRS.	
00003	0634 00 2 00113	SXA	RX2,2	..	
00004	0634 00 1 00066	SXA	HX1,1	..	
00005	-0500 00 4 00001	CAL	1,4	GET BUFFER ORIGIN.	
00006	0361 00 0 00122	ACL	=12	FORM BUFF+12.	
00007	0621 00 0 00014	STA	SCAN	..	
00010	0600 00 0 00115	STZ	INT	CLEAR CONVERSION.	
00011	0600 00 0 00117	STZ	TER	RESET ERROR MARK.	
00012	0600 00 0 00120	STZ	TDG	RESET DIGIT MARK.	
00013	0774 00 2 00012	AXT	10,2	SCAN TEN WORDS.	
00014	0560 00 2 00000	SCAN	LDQ	**,* GET BUFFER WORD. ADDRESS IS BUFF+12.	
00015	0774 00 4 00006	AXT	6,4	SIX CHARACTERS.	
00016	-0754 00 0 00000	PXD	0,0	CLEAR AC.	
00017	-0763 00 0 00006	LGL	6	GET CHARACTER.	
00020	-0340 00 0 00121	LAS	=10	CHECK FCR DIGIT.	
00021	0020 00 0 00036	TRA	CHAR	MUST BE CHARACTER.	
00022	0020 00 0 00054	TRA	ERROR	NO CHARACTER FOR CODE TEN.	
00023	-0625 00 0 00120	STL	TDG	DIGIT ENCOUNTERED, SET MARK.	
00024	0601 00 0 00116	STO	DIG	SAVE DIGIT.	
00025	0500 00 0 00115	CLA	INT	PROGRAMMED MULTIPLICATION OF INT BY TEN.	
00026	0767 00 0 00002	ALS	2	4*INT.	
00027	0400 00 0 00115	ADD	INT	4*INT+INT=5*INT.	
00030	0767 00 0 00001	ALS	1	2*(4*INT+INT)=10*INT.	
00031	0361 00 0 00116	ACL	DIG	ADD DIGIT, IGNORING SIGN.	
00032	0601 00 0 00115	STO	INT	SAVE.	
00033	2 00001 4 00016	RSCAN	TIX	COUNT CHARACTERS.	
00034	2 00001 2 00014	TIX	SCAN,2,1	COUNT WORDS.	
00035	0020 00 0 00102	TRA	BLANK	END OF FIELD EQUIVALENT TO BLANK.	
00036	0774 00 1 00010	CHAR	AXT	NBK,1	COMPARISON LOOP, GET NUMBER OF BREAKS.
00037	-0340 00 1 00054	LAS	TABBK+NBK,1	COMPARE WITH TABLE.	
00040	0020 00 0 00042	TRA	*+2	NOT THIS ONE, TRY AGAIN.	
00041	0020 60 1 00055	TRA*	TABBK+NBK+1,1	BREAK FOUND, GO TO IT.	
00042	2 00002 1 00037	TIX	*-3,1,2	NOT THIS ONE, INDEX AND TRY AGAIN.	
00043	0020 00 0 00054	TRA	ERROR	CANT FIND BREAK, ERROR.	
00044	000000000020	TABBK	BCI	1,00000+	BREAK TABLE, PLUS.
00045	0020 00 0 00057	TRA	PLUS	..	
00046	000000000040	BCI	1,COCCO-	MINUS.	
00047	0020 00 0 00062	TRA	MINUS	..	
00050	000000000073	BCI	1,C0000,	COMMA.	
00051	0020 00 0 00066	TRA	COMMA	..	
00052	000000000060	BCI	1,C0000	BLANK.	
00053	0020 00 0 00102	TRA	BLANK	..	
00010	NBK	EQU	*-TABBK	LENGTH OF BREAK TABLE.	
				INTP0510 INTP0520	

## INTOP, EVALUATE INT PSEUDO-OP.

00054	0055 00 000004	ERRCR	SIR	4	MARK INTOP ERROR.	INTP0530
00055	-0625 00 0 00117		STL	TER	MARK ERROR IN THIS WORD.	INTP0540
00056	0020 00 0 00033		TRA	RSCAN	RESUME SCAN.	INTP0550
00057	0520 00 0 00120	PLUS	ZET	TDG	PLUS SIGN, ILLEGAL AFTER DIGIT.	INTP0560
00060	0020 00 0 00054		TRA	ERROR	NG, GO MARK ERROR.	INTP0570
00061	0020 00 0 00033		TRA	RSCAN	OK, IGNORE PLUS.	INTP0580
00062	0520 00 0 00120	MINUS	ZET	TDG	MINUS SIGN, ILLEGAL AFTER DIGIT.	INTP0590
00063	0020 00 0 00054		TRA	ERROR	..	INTP0600
00064	0502 00 0 00115		CLS	INT	IF LEGAL, CHANGE SIGN OF INT.	INTP0610
00065	0020 00 0 00032		TRA	RSCAN-1	..	INTP0620
00066	0774 00 1 00000	COMMA	AXT	**,1	FIELD MARK, STORE THIS WORD, AND, PREPARE FOR NEXT WORD.	INTP0630
00067	0500 00 0 00115		CLA	INT	..	INTP0640
C0070	0767 00 0 00022		ALS	18	TEST FOR ERROR IN THIS WORD.	INTP0650
00071	0520 00 0 00117		ZET	TER	YES, CONVERSION IS ZERO.	INTP0660
00072	-0754 00 0 00000		PXD	0,0	RESET ERROR MARK.	INTP0670
C0073	060C 00 0 00117		STZ	TER	..	INTP0680
00074	0601 00 1 00000		STO	0,1	..	INTP0690
00075	0600 00 0 00115		STZ	INT	..	INTP0700
00076	0600 00 0 00120		STZ	TDG	RESET DIGIT MARK.	INTP0710
00077	1 77777 1 00100		TXI	**+,1,-1	..	INTP0720
00100	0634 00 1 00066		SXA	HX1,1	..	INTP0730
00101	0020 00 0 00033		TRA	RSCAN	..	INTP0740
	00066	HX1	SYN	COMMA	STORAGE FOR IRI IS IN COMMA.	INTP0750
00102	0534 00 1 00066	BLANK	LXA	HX1,1	END OF FIELD MARK, STORE THIS WORD, AND PREPARE TO EXIT.	INTP0760
00103	0500 00 0 00115		CLA	INT	..	INTP0770
00104	0767 00 0 00022		ALS	18	TEST FOR ERROR IN THIS WORD.	INTP0780
00105	0520 00 0 00117		ZET	TER	YES, CLEAR CCNVERSIO.	INTP0790
00106	-0754 00 0 00000		PXD	0,0	RESET ERROR MARK.	INTP0800
00107	0600 00 0 00117		STZ	TER	..	INTP0810
C00110	0601 00 1 00000		STO	0,1	..	INTP0820
00111	1 77777 1 00112		TXI	**+,1,-1	COUNT LAST WORD CONVERTED.	INTP0830
00112	0774 00 4 00000	RX4	AXT	**,4	RESTORE IRS.	INTP0840
00113	0774 00 2 00000	RX2	AXT	**,2	..	INTP0850
00114	0020 00 4 00002		TRA	2,4	EXIT TO CALLER.	INTP0860
00115	0 00000 0 00000	INT	PZE		STORAGE FOR CONVERSIO.	INTP0870
00116	0 00000 0 00000	DIG	PZE		STCRAGE FOR DIGIT.	INTP0880
00117	0 00000 0 00000	TER	PZE		MARK FOR ERROR THIS WORD.	INTP0890
00120	0 00000 0 00000	TDG	PZE		MARK FOR DIGIT ENCOUNTERED THIS FIELD.	INTP0900
					END	INTP0910
						INTP0920
						INTP0930
						INTP0940
						INTP0950
						INTP0960
						INTP0970
						INTP0980
						INTP0990

## LITERALS

00121 000000000012  
00122 000000000014

INTOP, EVALUATE INT PSEUDO-OP.  
POST PROCESSOR ASSEMBLY DATA

123 IS THE FIRST LOCATION NOT USED BY THIS PROGRAM

REFERENCES TO DEFINED SYMBOLS

116	DIG	24,	31						
66	HX1	4,	100,	1C2					
115	INT	10,	25,	27,	32,	64,	67,	75,	103
10	NBK	36,	37,	41,	54				
113	RX2	3							
112	RX4	2							
120	TG	12,	23,	57,	62,	76			
117	TER	11,	55,	71,	73,	105,	107		
36	CHAR	21							
57	PLUS	45							
14	SCAN	7,	33,	34					
102	BLANK	35,	53						
66	COMMA	51,	102						
54	ERRCR	22,	43,	60,	63				
2	INTOP								
62	MINUS	47							
33	RSCAN	56,	61,	65,	101				
44	TABBK	37,	41,	54					

NO ERROR IN ABOVE ASSEMBLY.

\*TIME SPENT IN FAP.. 000005 IN HUNDREDS OF MINUTES.

## UTILITY PROGRAMS FOR CAP.

72

UTILITY PROGRAMS FOR CAP.

EJECT

			\$COMMA, COUNT COMMAS IN VARIABLE FIELD PLUS ONE TO FIRST BLANK OR COLUMN 72. COUNT IS SUBTRACTED FROM IRI.	UTIL0340 UTIL0350 UTIL0360 UTIL0370	
00024	0634 00 4 00047	COMMA SXA	COX4,4	SAVE IRS.	UTIL0380
00025	0634 00 2 00050	SXA	COX2,2	..	UTIL0390
00026	-0500 00 4 00001	CAL	1,4	GET BUFFER ADDRESS.	UTIL0400
00027	0361 00 0 01106	ACL	=12	PLUS 12.	UTIL0410
00030	0621 00 0 00033	STA	LDG	STA IN PICKUP.	UTIL0420
00031	0774 00 4 00012	AXT	10,4	SCAN BUFF+2 TO BUFF+12.	UTIL0430
00032	0774 00 2 00006	CLP4	AXT	6,2	UTIL0440
00033	0560 00 4 00000	LDQ	LDQ	SIX CHARACTERS.	UTIL0450
00034	-0754 00 0 00000	CLP2	PXD	**,4	UTIL0460
00035	-0763 00 0 00006	LGL	0,0	GET WORD.	UTIL0470
00036	-0340 00 0 01110	LAS	6	CLEAR AC.	UTIL0480
00037	0020 00 0 00044	LAS	=HC0000,	GET CHARACTER.	UTIL0490
00040	1 77777 1 00044	TRA	RCLP	CHECK FOR COMMA.	UTIL0500
00041	-0340 00 0 01107	TXI	RCLP,1,-1	NO, CANT BE BLANK.	UTIL0510
00042	0020 00 0 00044	LAS	=HC0000	YES, COUNT AND RESUME SCAN.	UTIL0520
00043	0020 00 0 00046	TRA	**+2	CHECK FOR BLANK.	UTIL0530
00044	2 00001 2 00034	RCLP	ECSCN	NO, SKIP.	UTIL0540
00045	2 00001 4 00032	TXI	CLP2,2,1	END OF COMMA SCAN.	UTIL0550
			CLP4,4,1	COUNT CHARACTERS.	UTIL0560
				COUNT WORDS.	UTIL0570
00046	1 77777 1 00047	ECSCN	TXI	COUNT LAST BLANK OR E.O.F.	UTIL0580
00047	0774 00 4 00000	COX4	AXT	**+,4	UTIL0590
00050	0774 00 2 00000	COX2	AXT	**+,2	UTIL0600
00051	0020 00 4 00002	TRA	2,4	RESTORE IRS.	UTIL0610
				..	UTIL0620
				RETURN.	UTIL0630
				END OF COMMA.	

## UTILITY PROGRAMS FOR CAP.

EJECT							
						\$SAVE AND \$UNSAVE, PUSHDOWN LIST.	
00052	0634 00 4 00071	SAVE	SXA	SVX4,4	SAVE IRS.	UTIL0640	
C0053	0634 00 2 00072		SXA	SVX2,2	..	UTIL0650	
00054	-0500 00 4 00001		CAL	1,4	GET CONTROL WORD.	UTIL0660	
00055	-0734 00 2 00000		PDX	0,2	COUNT TC IR2.	UTIL0670	
00056	0754 00 2 00000		PXA	0,2	COUNT TC A(AC).	UTIL0680	
00057	0361 00 4 00001		ACL	1,4	(ADDRESS OF FIRST)+COUNT.	UTIL0690	
00060	0621 00 0 00062		STA	*+2	STA IN PICKUP.	UTIL0700	
00061	0774 00 4 00764	SCNT	AXT	SVN,4	CURRENT STORAGE COUNT TO IR4.	UTIL0710	
00062	-0500 00 2 00000		CAL	**,,2	GET WORD. **= BES OF CURRENT BLOCK	UTIL0720	
00063	0602 00 4 01106		SLW	SBUFF+SVN,4	PLACE IN LIST.	UTIL0730	
00064	2 00001 4 00067		TIX	*+3,4,1	COUNT LIST.	UTIL0740	
00065	-0055 00 00002		SIL	2	LIST EXCEEDED, SET INDICATOR,	UTIL0750	
00066	0020 00 0 00071		TRA	SVX4	AND EXIT.	UTIL0760	
00067	2 00001 2 00062		TIX	*-5,2,1	COUNT WORDS TRANSMITTED.	UTIL0770	
00070	0634 00 4 00061		SXA	SCNT,4	SAVE LIST COUNT.	UTIL0780	
00071	0774 00 4 00000	SVX4	AXT	*,,4	RESTORE IRS.	UTIL0790	
00072	0774 00 2 00000	SVX2	AXT	**,,2	..	UTIL0800	
00073	0020 00 4 00002		TRA	2,4	RETURN.	UTIL0810	
00074	0634 00 4 00117	UNSAVE	SXA	UNSX4,4	SAVE IRS.	UTIL0820	
00075	0634 00 2 00120		SXA	UNSX2,2	..	UTIL0830	
00076	-0500 00 4 00001		CAL	1,4	GET CONTROL WORD.	UTIL0840	
00077	0622 00 0 00115		STD	UNTXL	INSERT COUNT.	UTIL0850	
00100	0771 00 0 0022		ARS	18	COUNT TC A(AC).	UTIL0860	
00101	0361 00 4 00001		ACL	1,4	(ADDRESS OF FIRST)+COUNT.	UTIL0870	
00102	0621 00 0 00113		STA	UNSLW	STA IN STORE.	UTIL0880	
00103	0774 00 2 00001		AXT	1,2	SETUP FOR WORD COUNT.	UTIL0890	
00104	0534 00 4 00061		LXA	SCNT,4	LIST COUNT TO IR4.	UTIL0900	
00105	1 00001 4 00106	UNSLP	TXI	*+1,4,1	COUNT IN LIST.	UTIL0910	
00106	-3 00764 4 00111		TXL	*+3,4,SVN	IS LIST EXCEEDED.	UTIL0920	
00107	-0055 00 00004		SIL	4	YES, SET INDICATOR,	UTIL0930	
00110	0020 00 0 00117		TRA	UNSX4	AND EXIT.	UTIL0940	
00111	-0500 00 4 01106		CAL	SBUFF+SVN,4	OK, GET WORD,	UTIL0950	
00112	0600 00 4 01106		STZ	SBUFF+SVN,4	AND CLEAR LIST.	UTIL0960	
00113	0602 00 2 00000	UNSLW	SLW	**,,2	INSERT IN CALLING PROGRAM.	UTIL0970	
00114	1 00001 2 00115		TXI	*+1,2,1	COUNT WORDS TRANSMITTED.	UTIL0980	
00115	-3 00000 2 00113	UNTXL	TXL	UNSLW,2,**	COMPARE WITH BLOCK LENGTH.	UTIL0990	
00116	0634 00 4 00061		SXA	SCNT,4	SAVE LIST COUNT.	UTIL1000	
00117	0774 00 4 00000	UNSX4	AXT	*,,4	RESTORE IRS.	UTIL1010	
00120	0774 00 2 00000	UNSX2	AXT	**,,2	..	UTIL1020	
00121	0020 00 4 00002		TRA	2,4	RETURN.	UTIL1030	
00122		00764	SVN EQU	500	LENGTH OF SAVE LIST.	UTIL1040	
			SBUFF BSS	SVN	LIST BUFFER.	UTIL1050	
					END OF SAVE AND UNSAVE.	UTIL1060	
					END	UTIL1070	
						UTIL1080	
						UTIL1090	
						UTIL1100	
						UTIL1110	
						UTIL1120	
						UTIL1130	
						UTIL1140	

## LITERALS

01106 000000000014  
 01107 000000000060  
 01110 000000000073

UTILITY PROGRAMS FOR CAP.  
POST PROCESSOR ASSEMBLY DATA

1111 IS THE FIRST LOCATION NOT USED BY THIS PROGRAM

REFERENCES TO DEFINED SYMBOLS

33	LCQ	30
764	SVN	61, 63, 106, 111, 112, 122, 1106
34	CLP2	44
32	CLP4	45
50	COX2	25
47	COX4	24
44	RCLP	37, 40
52	SAVE	
2	SCAN	
61	SCNT	70, 104, 116
21	SCX4	2
72	SVX2	53
71	SVX4	52, 66
23	WORD	5, 14, 16, 20
24	COMMA	
46	ECSNC	43
17	RSCAN	12
122	SBUFF	63, 111, 112
6	SLOCP	17
105	UNSLP	
113	UNSLW	102, 115
120	UNSX2	75
117	UNSX4	74, 110
115	UNTXL	77
74	UNSAVE	

NO ERROR IN ABOVE ASSEMBLY.

\*TIME SPENT IN FAP.. 000006 IN HUNDREDTHS OF MINUTES.

**\$SYMSTO, AND \$SYMGET, OPERATIONS WITH SYMBOL TABLE.**

		PCC					SYMS0010
		COUNT	54				SYMS0020
		LBL	SYMSTO	BINARY CARD LABEL.			SYMS0040
00026		ENTRY	SYMGET	ENTRY TO LOOK-UP VALUE OF SYMBOL.			SYMS0050
00042		ENTRY	PSMTBL	POINTER TO SYMBOL TABLE AND SIZE.			SYMS0060
00003		ENTRY	SYMSTO	ENTRY TO PLACE SYMBOL AND VALUE IN TABLE.			SYMS0070
				\$SYMSTO, FORM SYMBOL TABLE.			SYMS0080
							SYMS0090
							SYMS0100
<b>TRANSFER VECTOR</b>							
00000	622321456060	SCAN					
<b>LINKAGE DIRECTOR</b>							
00001	000000000000						
00002	627044272563						
00003	-0340 00 0 00353	SYMSTO	LAS	=H	CHECK FOR BLANK LOCATION FIELD.		SYMS0110
00004	0020 00 0 00006		TRA	*+2	NOT BLANK, SKIP.		SYMS0120
00005	0020 00 4 00001		TRA	1,4	BLANK, DONT STORE, RETURN TO CALLER.		SYMS0130
00006	0634 00 4 00024		SXA	SSX4,4	SAVE IR4.		SYMS0140
00007	0074 00 4 00000		TSX	\$SCAN,4	COMPRESS SYMBOL TO RIGHT.		SYMS0150
00010	-0130 00 0 00000		XCL		PLACE SYMBOL IN MQ.		SYMS0160
00011	0754 00 1 00000		PXA	0,1	GET +(ILC).		SYMS0170
00012	0737 00 4 00000		PAC	0,4	..		SYMS0180
00013	0754 00 4 00000		PXA	0,4	..		SYMS0190
00014	-0534 00 4 00042		LXD	PSMTBL,4	GET CURRENT COUNT OF TABLE.		SYMS0200
00015	1 00002 4 00016		TXI	*+1,4,2	MAKE ROOM FOR ONE MORE.		SYMS0210
00016	-3 00310 4 00021		TXL	*+3,4,LSMTBL	CHECK FOR TABLE OVERFLOW.		SYMS0220
00017	-0055 00 000001		SIL	1	SYMTBL EXCEEDED, SET INDICATOR.		SYMS0230
00020	0020 00 0 00024		TRA	SSX4	GO TO RETURN.		SYMS0240
00021	-0600 00 4 00353		STQ	SYMTBL,4	SAVE SYMBOL.		SYMS0250
00022	0060 00 4 00354		SLW	SYMTBL+1,4	SAVE VALUE.		SYMS0260
00023	-0634 00 4 00042		SXD	PSMTBL,4	SAVE TABLE COUNT.		SYMS0270
00024	0774 00 4 00000	SSX4	AXT	***,4	RESTORE IR4.		SYMS0280
00025	0020 00 4 00001		TRA	1,4	RETURN.		SYMS0290
		SPACE		2			
					\$SYMGET, LOOK UP SYMBOL AND GET VALUE.		SYMS0300
00026	0634 00 4 00040	SYMGET	SXA	SGX4,4	SAVE IR4.		SYMS0330
00027	-0534 00 4 00042		LXD	PSMTBL,4	GET TABLE COUNT.		SYMS0340
00030	-0340 00 4 00353		LAS	SYMTBL,4	COMPARE WITH TABLE.		SYMS0350
00031	0020 00 0 00033		TRA	*+2	NOT THIS ONE, SKIP.		SYMS0360
00032	0020 00 0 00037		TRA	SYMFND	FOUND, EXIT.		SYMS0370
00033	2 00002 4 00030		TIX	*-3,4,2	INDEX AND TRY AGAIN.		SYMS0380
00034	-0754 00 0 00000		PXD	0,0	NOT FOUND, VALUE IS ZERO.		SYMS0400
00035	0055 00 000001		SIR	1	SET UNDEFINED SYMBOL INDICATOR.		SYMS0410
00036	0020 00 0 00040		TRA	SGX4	GO TO EXIT.		SYMS0420
00037	-0500 00 4 00354	SYMFD	CAL	SYMTBL+1,4	FOUND, GET VALUE.		SYMS0440
00040	0774 00 4 00000	SGX4	AXT	***,4	RESTORE IR4.		SYMS0450
00041	0020 00 4 00001		TRA	1,4	RETURN.		SYMS0460

**\$SYMSTO, AND \$SYMGET, OPERATIONS WITH SYMBOL TABLE.**

		SPACE	2			SYMS0470
			STORAGE AND CONSTANTS.			SYMS0480
00042	0 00000 0	00310 LSMTBL EQU 00353 PSMTBL PZE 00353 SYMTBL BES	2*100 SYMTBL,0,** LSMTBL	ROOM FOR 100 SYMBOLS. POINTER WORD TO SYMTBL. SYMBOL TABLE.		SYMS0490
		END				SYMS0500
		LITERALS				SYMS0510
	00353	606060606060				SYMS0520
						SYMS0530
						SYMS0540

**POST PROCESSOR ASSEMBLY DATA**

**354 IS THE FIRST LOCATION NOT USED BY THIS PROGRAM**

**REFERENCES TO DEFINED SYMBOLS**

0	SCAN	7
40	SGX4	26, 36
24	SSX4	6, 20
310	LSMTBL	16, 42, 353
42	PSMTBL	14, 23, 27
37	SYMFND	32
26	SYMGET	
3	SYMSTO	
353	SYMTBL	21, 22, 30, 37, 42

**NO ERROR IN ABOVE ASSEMBLY.**

**\*TIME SPENT IN FAPP.. 000004 IN HUNDREDS OF MINUTES.**

## ENDOP AND OTHER SUBROUTINES USED BY COMP.

	PCC				ENDP0010
	COUNT	102			ENDP0020
	LBL	ENDOP	BINARY CARD LABEL.		ENDP0040
00036	ENTRY	PIVAR	ENTRY TO PLACE WORD IN VARIABLE FIELD.		ENDP0050
00045	ENTRY	GENOP	ENTRY TO PLACE OP IN OP-FIELD AND WCT1.		ENDP0060
00053	ENTRY	ILC	ENTRY LOCATION FOR SAVING CURRENT ILC.		ENDP0070
00071	ENTRY	GNSTO	ENTRY TO GENERATE TEMPORARY STORAGE.		ENDP0080
00060	ENTRY	ERASE	ENTRY TO ERASE VARIABLE FIELD.		ENDP0090
00122	ENTRY	NSTO	ENTRY TO COUNT LOCATIONS FOR ERASABLES.		ENDP0100
00004	ENTRY	ENDOP	END CARC PSEUDO-OP.		ENDP0110
			ENTRY TO RESERVE STORAGE.		ENDP0120
					ENDP0130
					ENDP0140
 TRANSFER VECTOR					
00000	627044626346	SYMSTO			
00001	662363016060	WCT1			
 LINKAGE DIRECTOR					
00002	000000000000				
00003	473165215160				
00004	-0520 00 0 00123	ENDOP NZT	MSTO	IF NO STORAGE ALLOCATED,	ENDP0150
00005	0020 00 4 00001	TRA	1,4	RETURN TO CALLER.	ENDP0160
00006	0634 00 4 00016	SXA	ENDX4,4	STORAGE ALLOCATED, SAVE IR4.	ENDP0170
00007	-0500 00 0 00150	CAL	=HTEM	INSERT THIS SYMBOL IN SYMBOL TABLE.	ENDP0180
00010	0074 00 4 00000	TSX	\$SYMSTO,4	..	ENDP0190
00011	0074 00 4 00001	TSX	\$WCT1,4	PUT REM CARD ON CT1.	ENDP0200
00012	0 00000 0 00020	PZE	EBUFF	..	ENDP0210
00013	0535 00 4 00123	LAC	MSTO,4	INCREASE ILC FOR STORAGE.	ENDP0220
00014	-0634 00 4 00015	SXD	*+1,4	..	ENDP0230
00015	1 00000 1 00016	TXI	*+1,1,**	..	ENDP0240
00016	0774 00 4 00000	ENDX4 AXT	**,,4	RESTORE IR4.	ENDP0250
00017	0020 00 4 00001	TRA	1,4	RETURN.	ENDP0260
00020	606325446060	EBUFF BCI	9, TEM	TEMPORARY STORAGE AREA BEGINS HERE.	ENDP0270
00021	605125446060				ENDP0280
00022	632544474651				
00023	215170606263				
00024	465121272560				
00025	215125216022				
00026	252731456260				
00027	302551253360				
00030	606060606060				
00031	606060606060	BCI	5,		ENDP0290
00032	606060606060				
00033	606060606060				
00034	606060606060				
00035	606060606060				
			ENTRY TO FORM VARIABLE FIELD.		
00036	0634 00 4 00043	PIVAR SXA	PX4,4	SAVE IR4.	ENDP0300
00037	0774 00 4 00013	PCNT AXT	11,4	COUNT 10 WORDS WITH TNX.	ENDP0310
00040	-2 00001 4 00043	TNX	PX4,4,1	INDEX WORD COUNT.	ENDP0320
00041	0602 00 4 00141	SLW	PBUFF+12,4	PLACE WORD IN BUFFER.	ENDP0330
					ENDP0340
					ENDP0350
					ENDP0360

ENDOP AND OTHER SUBROUTINES USED BY COMP.

00042	0634 00 4 00037		SXA	PCNT,4	SAVE WORD COUNT.	ENDP0370
00043	0774 00 4 00000	PX4	AXT	**,4	RESTORE IR4.	ENDP0380
00044	0020 00 4 00001		TRA	1,4	RETURN.	ENDP0390

			SPACE	2	ENTRY TO INSERT OP-FIELD AND WCT1.	ENDP0400
						ENDP0410
00045	0634 00 4 00056	GENOP	SXA	GOPX4,4	SAVE IR4.	ENDP0420
00046	-0500 00 4 00001		CAL	1,4	GET OP.	ENDP0430
C0047	0602 00 0 00126		SLW	PBUFF+1	INSERT CP-FIELD.	ENDP0440
00050	0074 00 4 00001		TSX	\$WCT1,4	WRITE COLLATION TAPE.	ENDP0450
00051	0 00000 0 00125		PZE	PBUFF	..	ENDP0460
00052	0074 00 4 00060		TSX	ERASE,4	CLEAR PBUFF.	ENDP0470
00053	0774 00 4 00000	ILC	AXT	**,4	INCREMENT ILC.	ENDP0480
00054	1 77777 4 00055		TXI	**+1,4,-1	..	ENDP0490
00055	0634 00 4 00053		SXA	ILC,4	SAVE CURRENT ILC.	ENDP0500
00056	0774 00 4 00000	GOPX4	AXT	**,4	RESTORE IR4.	ENDP0510
C0057	0020 00 4 00002		TRA	2,4	RETURN.	ENDP0520
						ENDP0530

			SPACE	2	ENTRY TO ERASE PBUFF.	ENDP0540
						ENDP0550
00060	0634 00 4 00067	ERASE	SXA	ERX4,4	SAVE IR4.	ENDP0560
C0061	0774 00 4 00013		AXT	11,4	RESET PCNT.	ENDP0570
00062	0634 00 4 00037		SXA	PCNT,4	..	ENDP0580
00063	0774 00 4 00016		AXT	14,4	LOAD BUFFER WITH BLANKS.	ENDP0590
00064	-0500 00 0 00145		CAL	=H	..	ENDP0600
00065	0602 00 4 00143		SLW	PBLFF+14,4	..	ENDP0610
C0066	2 00001 4 00065		TIX	**-1,4,1	..	ENDP0620
00067	0774 00 4 00000	ERX4	AXT	**,4	RESTORE IR4.	ENDP0630
00070	0020 00 4 00001		TRA	1,4	RETURN.	ENDP0640
						ENDP0650

			SPACE	2	ENTRY TO GET NEXT TEMPORARY STORAGE SYMBOL.	ENDP0660
						ENDP0670
00071	0500 00 0 00122	GNSTO	CLA	NSTO	PLACE NUMBER OF LAST STORAGE.	ENDP0680
00072	0560 00 0 00122		LDQ	NSTO	IN AC AND MQ.	ENDP0690
00073	0400 00 0 00143		ADD	=1	INCREMENT AND SAVE FOR NEXT.	ENDP0700
00074	0601 00 0 00122		STO	NSTO	..	ENDP0710
00075	0340 00 0 00123		CAS	MSTO	CHECK FOR MSTO EXCEEDED.	ENDP0720
00076	0601 00 0 00123		STO	MSTO	YES, UPDATE MSTO.	ENDP0730
00077	0761 00 0 00000		NOP		EQUAL, IGNORE.	ENDP0740
00100	0131 00 0 00000		XCA		PLACE NSTO IN AC.	ENDP0750
00101	-0100 00 0 00104		TNL	**+3	CHECK FOR ZERO NSTO.	ENDP0760
00102	-0500 00 0 00150		CAL	=HTEM	ZERO, PICKUP CHARACTERS.	ENDP0770
00103	0020 00 4 00001		TRA	1,4	RETURN TO CALLER.	ENDP0780
00104	0340 00 0 00144		CAS	=10	CHECK FOR ONLY ONE DIGIT.	ENDP0790
00105	0020 00 0 00112		TRA	TWODG	TWO DIGITS.	ENDP0800
00106	0020 00 0 00112		TRA	TWODG	..	ENDP0810
00107	0767 00 0 00006		ALS	6	ONE DIGIT, SHIFT TO POSITION.	ENDP0820
00110	-0501 00 0 00147		ORA	=HTEM+0	INSERT CHARACTERS.	ENDP0830
00111	0020 00 4 00001		TRA	1,4	RETURN TO CALLER.	ENDP0840
00112	0131 00 0 00000	TWODG	XCA		TWO DIGITS, PLACE NSTO IN MQ AGAIN.	ENDP0850
						ENDP0860

## ENDOP AND OTHER SUBROUTINES USED BY COMP.

00113 -0754 00 0 00000	PXD	0,C	CLEAR AC.	ENDP0870
00114 0221 00 0 00144	DVP	=10	MOD 10.	ENDP0880
00115 -0773 00 0 00006	RQL	6	FIRST DIGIT TO K5.	ENDP0890
00116 -060C 00 0 00124	STQ	DNSTO	SAVE.	ENDP0900
00117 -0501 00 0 00124	ORA	DNSTO	FORM DECIMAL STORAGE NUMBER.	ENDP0910
00120 -0501 00 0 00146	ORA	=HTEM+00	INSERT CHARACTERS.	ENDP0920
00121 0020 00 4 00001	TRA	1,4	RETURN WITH RESULT IN AC.	ENDP0930

SPACE 2  
STCRAGE AND CONSTANTS.

00122 0 00000 0 00000	NSTC	PZE	CURRENT STORAGE COUNTER.	ENDP0940
00123 0 00000 0 00000	MSTO	PZE	MAXIMUM STORAGE COUNTER.	ENDP0950
00124 0 00000 0 00000	CNSTC	PZE	DECIMAL STORAGE COUNTER.	ENDP0960
00125	PBUFF	BSS	STATEMENT BUFFER.	ENDP0970
		14		ENDP0980
				ENDP0990
				ENDP1000
				ENDP1010
				ENDP1020

END

## LITERALS

00143	0000CC0000001
00144	000000000012
00145	606060606060
00146	632544200C00
00147	632544200060
00150	632544606060

## POST PROCESSOR ASSEMBLY DATA

151 IS THE FIRST LOCATION NOT USED BY THIS PROGRAM

## REFERENCES TO DEFINED SYMBOLS

53	ILC	55
43	PX4	36, 40
67	ERX4	60
123	MSTO	4, 13, 75, 76
122	NSTC	71, 72, 74
37	PCNT	42, 62
1	WCT1	11, 50
124	DNSTO	116, 117
20	EBUFF	12
4	ENDOP	
16	ENDX4	6
60	ERASE	52
45	GENOP	
71	GNSTO	
56	GOPX4	45
125	PBUFF	41, 47, 51, 65
36	PIVAR	
112	TWOODG	105, 106
0	SYMSTO	10

NO ERROR IN ABOVE ASSEMBLY.  
\*TIME SPENT IN FAP.. 000005 IN HUNDREDTHS OF MINUTES.

SUBROUTINE COMPOP, COMPILE ARITHMETICS FOR CAP.

PCC		COMP0010	
COUNT	186	COMP0020	
00010	LBL COMPOP      ENTRY COMPOP	BINARY CARD LABEL. EVALUATE 'COMP' PSEUDO-OP.	COMP0040
*	\$COMPOP IS CALLED BY,	COMP0050	
*	TSX \$COMPOP,4	COMP0060	
*	PZE BLFF	COMP0070	
*	WHERE BUFF IS A 14 WORD BUFFER CONTAINING THE HOLLERITH CARD IMAGE OF THE COMP STATEMENT.	COMP0080	
*	COMPOP TAKES THE VARIABLE FIELD AS A FORTRAN	COMP0090	
*	ARITHMETIC STATEMENT AND COMPILES IN FLOATING	COMP0100	
*	POINT. COMMAS ARE TREATED AS PART OF THE SYMBOL, HENCE TAGGING IS ALLOWED. BLANKS ARE IGNORED.	COMP0110	
*	COMPOP OPERATES IN 2 PASSES. PASS1 TAKES THE CARD IMAGE APART SEPARATING SYMBOLS FROM OPERATION	COMP0120	
*	CHARACTERS. PASS2 EVALUATES EXPRESSIONS FROM THE	COMP0130	
*	INNERMOST (...) PAIR OUTWARD. SOME OPTIMIZATION	COMP0140	
*	IS DONE BUT THERE ARE NO DIAGNOSTICS.	COMP0150	
		COMP0160	
		COMP0170	
		COMP0180	
		COMP0190	
		COMP0200	
		COMP0210	
		COMP0220	
		COMP0230	

TRANSFER VECTOR

00000	314323606060	ILC
00001	456263466060	NSTO
00002	255121622560	ERASE
00003	256747516060	EXPR
00004	473165215160	PIVAR
00005	272545464760	GENOP

LINKAGE DIRECTOR

00006	000000000000
00007	234644474647

00010	0634 00 4 00210	COMPOP SXA	RX4,4	SAVE IRS.	COMP0240
00011	0634 00 2 00211	SXA	RX2,2	..	COMP0250
00012	0754 00 1 00000	PXA	0,1	GET -(ILC).	COMP0260
00013	0621 60 0 00000	STA*	\$ILC	SAVE.	COMP0270
00014	-0500 00 4 00001	CAL	1,4	GET CONTROL WORD.	COMP0280
00015	0361 00 0 00536	ACL	=12	BUFF+12.	COMP0290
00016	0621 00 0 00032	STA	CAL1	STA IN PICKUP.	COMP0300
00017	0600 60 0 00001	STZ*	\$NSTO	ZERO NUMBER OF TEMPORARY STORAGE.	COMP0310
00020	0600 00 0 00216	STZ	TEOF1	RESET EOF MARK.	COMP0320
00021	-0500 00 0 00534	CAL	=1	SETUP SYM.	COMP0330
00022	0602 00 0 00215	SLW	SYM	..	COMP0340
00023	0074 00 4 00002	TSX	\$ERASE,4	ERASE BUFFER.	COMP0350
00024	0774 00 4 00310	AXT	LFLD,4	SETUP FLD COUNT.	COMP0360
00025	0634 00 4 00124	SXA	FCNT,4	..	COMP0370
00026	0140 00 0 00027	TOV	*+1	TURN OFF OVERFLOW LIGHT.	COMP0380
00027	0020 00 0 00030	TRA	CPASI	GO TO PASS1.	COMP0390

## SUBROUTINE COMPOP, COMPILE ARITHMETICS FOR CAP.

		SPACE	2	PASS 1 OF COMP, SEPARATE FIELD INTO SYMBOL AND BREAKS.		
00030	0774 00 2 00012	CPAS1	AXT	10,2	COUNT 10 WORDS IN VARIABLE FIELD.	COMP0400
C0031	0774 00 1 00006	BSCNI	AXT	6,1	COUNT 6 CHARACTERS.	COMP0410
00032	-0500 00 2 00000	CAL1	CAL	**,2	GET WORD.	COMP0420
00033	-0340 00 0 00542	LAS	=H		CHECK FOR ALL BLANKS.	COMP0430
00034	0020 00 0 00036	TRA	*+2		NO, SKIP.	COMP0440
00035	0020 00 0 00063	TRA	RSCN1+2		ALL BLANK, IGNORE.	COMP0450
00036	-0130 00 0 00000	XCL			PLACE IN MQ.	COMP0460
00037	-0754 00 0 00000	SCN1	PXD	0,0	CLEAR AC.	COMP0470
00040	-0763 00 0 00006	LGL		6	GET NEXT CHARACTER.	COMP0480
00041	-0600 00 0 00217	STQ	MQ		SAVE MQ.	COMP0490
00042	-0340 00 0 00540	LAS	=H000C0		CHECK FOR BLANK.	COMP0500
00043	0020 00 0 00045	TRA	*+2		NO, SKIP.	COMP0510
00044	0020 00 0 00061	TRA	RSCN1		YES, IGNORE.	COMP0520
00045	0774 00 4 000C7	AXT	NBK,4		CHECK FOR BREAK.	COMP0530
00046	-0340 00 4 00075	LAS	TABBK+NBK,4		COMPARE WITH TABLE.	COMP0540
00047	0020 00 0 00051	TRA	*+2		NO, SKIP.	COMP0550
00050	0020 00 0 00075	TRA	BRK		BREAK FOUND, EXIT.	COMP0560
00051	2 00001 4 00046	TIX	*-3,4,1		INDEX, AND TRY AGAIN.	COMP0570
00052	-0765 00 0 00006	LGR	6		BUILD SYM.	COMP0580
00053	-0500 00 0 00215	CAL	SYM	..		COMP0590
00054	-0763 00 0 00006	LGL	6			COMP0600
00055	-0140 00 0 00060	TNO	*+3		IF SYMBOL FULL,	COMP0610
00056	0074 00 4 00123	TSX	STFLD,4		INSERT IN LIST,	COMP0620
00057	-0500 00 0 00534	CAL	=1		AND BEGIN NEW SYMBOL.	COMP0630
00060	0602 00 0 00215	SLW	SYM		SAVE PARTIAL SYMBOL.	COMP0640
00061	0560 00 0 00217	RSCN1	LDQ	MQ	RESTORE MQ.	COMP0650
00062	2 00001 1 00037	TIX	SCN1,1,1		COUNT CHARACTERS.	COMP0660
00063	2 00001 2 00031	TIX	BSCN1,2,1		COUNT WORDS.	COMP0670
00064	-0625 00 0 00216	STL	TEOF1		SET EOF MARK.	COMP0680
00065	0020 00 0 00075	TRA	BRK		GO PROCESS BREAK.	COMP0690
00066	000000000020	TABBK	BCI	1,00000+	TABLE OF BREAK CHARACTERS.	COMP0700
00067	000000000040		BCI	1,0000C-	..	COMP0710
00070	000000000C54		BCI	1,CCCC*	..	COMP0720
00071	000000000061		BCI	1,COOC0/	..	COMP0730
00072	000000000074		BCI	1,00000(	..	COMP0740
00073	000000000034		BCI	1,00000)	..	COMP0750
00074	000000000013		BCI	1,00000=	..	COMP0760
	000007	NBK	EQU	--TABBK	SIZE OF TABLE.	COMP0770
00075	0602 00 0 00220	BRK	SLW	LBRK	SAVE BREAK CHARACTER.	COMP0780
00076	-0500 00 0 00215		CAL	SYM	GET SYMBOL.	COMP0790
00077	-0340 00 0 00534		LAS	=1	CHECK FOR NO CHARACTERS.	COMP0800
00100	0020 00 0 00102	TRA	*+2		YES, SKIP.	COMP0810
00101	0020 00 0 00110	TRA	NOSYM		NO, DONT STORE.	COMP0820
00102	0560 00 0 00542	LDQ	=H		SYMBOL, LEFT JUSTIFY.	COMP0830
00103	-0763 00 0 00006	LGL	6		..	COMP0840
00104	-0140 00 0 00103	TNO	*-1		..	COMP0850
00105	0074 00 4 00123	TSX	STFLD,4		PLACE IN FLD.	COMP0860
00106	-0500 00 0 00534	CAL	=1		BEGIN NEW SYMBOL.	COMP0870
00107	0602 00 0 00215	SLW	SYM	..		COMP0880
00110	0520 00 0 00216	NOSYM	ZET	TEOF1	CHECK FOR EOF.	COMP0890
00111	0020 00 0 00134		TRA	EOF1	EOF, GO TO IT.	COMP0900

SUBROUTINE COMPOP, COMPILE ARITHMETICS FOR CAP.

00112 -0500 00 0 00220	CAL	LBRK	NOT EOF, GET BREAK CHARACTER.	COMP0960
00113 0074 00 4 00123	TSX	STFLD,4	PLACE IN FIELD.	COMP0970
00114 -0500 00 0 00220	CAL	LBRK	GET BREAK CHARACTER.	COMP0980
00115 0322 00 0 00535	ERA	=H00000=	CHECK FOR =.	COMP0990
00116 -0100 00 0 00061	TNZ	RSCN1	NO, RESUME SCAN.	COMP1000
00117 -0500 00 0 00124	CAL	FCNT	YES, MARK TOP OF FIELD.	COMP1010
00120 0361 00 0 00534	ACL	=1	..	COMP1020
00121 0621 00 0 00221	STA	TFLD	..	COMP1030
00122 0020 00 0 00061	TRA	RSCN1	RESUME SCAN.	COMP1040
00123 0634 00 4 00130	STFLD	SXA	SAVE IR4.	COMP1060
00124 0774 00 4 00310	FCNT	AXT	GET CURRENT FLD INDEX.	COMP1070
00125 0602 00 4 00534	SLW	FLC,4	INSERT WORD.	COMP1080
00126 -2 00001 4 00132	TNX	XFLD,4,1	COUNT THIS WORD.	COMP1090
00127 0634 00 4 00124	SXA	*-3,4	SAVE COUNT.	COMP1100
00130 0774 00 4 00000	STX4	AXT	RESTORE IR4.	COMP1110
00131 0020 00 4 00001	TRA	1,4	RETURN.	COMP1120
00132 -0055 00 000010	XFLD	SIL	COMP STATEMENT TOO LONG, MARK ERROR,	COMP1140
00133 0020 00 0 00210	TRA	RX4	AND RETURN.	COMP1150
00134 -0500 00 0 00124	EOF1	CAL	MARK BOTTOM OF FIELD.	COMP1170
00135 0621 00 0 00222	STA	BFLD	..	COMP1180
00136 0020 00 0 00137	TRA	CPAS2	GO TO PASS2.	COMP1190

	SPACE	2	PASS 2 OF COMP, FIND AND EVALUATE EXPRESSIONS.	COMP1200	
				COMP1210	
				COMP1220	
00137 0534 00 1 00222	CPAS2	LXA	BFLD,1	SET CONTROL TXH.	COMP1230
00140 -C634 00 1 00155		SXD	RSCN2+1,1	..	COMP1240
00141 0534 00 1 00221	BSCN2	LXA	TFLD,1	GET TOP OF FIELD.	COMP1250
00142 0634 00 1 00223		SXA	LLPAR,1	TREAT AS LAST (.	COMP1260
00143 1 77777 1 00144		TXI	*+1,1,-1	INDEX TO FIRST WORD.	COMP1270
00144 -0500 00 1 00534	SCN2	CAL	FLC,1	GET NEXT FLD WORD.	COMP1280
00145 0100 00 0 00154	TZE		RSCN2	IF ZERO, IGNORE.	COMP1290
00146 -0340 00 0 00541	LAS		=HC00C01	CHECK FOR (.	COMP1300
00147 0020 00 0 00151	TRA		*+2	NO, SKIP.	COMP1310
00150 0020 00 0 00157	TRA		LPAR2	YES, GO TO IT.	COMP1320
00151 -0340 00 0 00537	LAS		=H00000)	CHECK FOR ).	COMP1330
00152 0020 00 0 00154	TRA		*+2	NO, SKIP.	COMP1340
00153 0020 00 0 00161	TRA		RPAR2	YES, GO TO IT.	COMP1350
00154 1 77777 1 00155	RSCN2	TXI	*+1,1,-1	COUNT WORDS.	COMP1360
00155 3 00000 1 00144		TXH	SCN2,1,**	CHECK FOR EOF.	COMP1370
00156 0020 00 0 00172	TRA		EOF2	EOF, GO TO IT.	COMP1380
00157 0634 00 1 00223	LPAR2	SXA	LLPAR,1	SET LAST (.	COMP1400
00160 0020 00 0 00154	TRA		RSCN2	RESUME SCAN.	COMP1410
00161 -0634 00 1 00167	RPAR2	SXD	EXPW1,1	EXPRESSION, MARK BOTTOM FOR \$EXPR.	COMP1430
00162 0600 00 1 00534	STZ		FLD,1	CLEAR FLD.	COMP1440
00163 0534 00 1 00223	LXA		LLPAR,1	GET INDEX OF LAST (.	COMP1450
00164 0600 00 1 00534	STZ		FLC,1	CLEAR FLD.	COMP1460
00165 0634 00 1 00167	SXA		EXPW1,1	MARK TOP FOR \$EXPR.	COMP1470
00166 0074 00 4 00003	TSX		\$EXPR,4	GO EVALUATE EXPRESSION.	COMP1480
00167 0 00000 0 00000	EXPW1	PZE	**,0,**	ZERO TAG MEANS STORE INTERMEDIATE.	COMP1490

## SUBROUTINE COMPOP, COMPILE ARITHMETICS FOR CAP.

C0170 0 00000 C 00534	PZE	FLC	..	COMP1500	
00171 0020 00 0 00141	TRA	BSCN2	RESTART SCAN.	COMP1510	
00172 -0634 00 1 00177	EOF2	SXD	EXPW2,1	COMP1520	
00173 0534 00 1 00223	LXA	LLPAR,1	FINAL EXPR, MARK BOTTOM.	COMP1530	
00174 0600 00 1 00534	STZ	FLC,1	GET INDEX OF TOP.	COMP1540	
00175 0634 00 1 00177	SXA	EXPW2,1	CLEAR FLD.	COMP1550	
00176 0074 00 4 00003	TSX	\$EXPR,4	MARK TOP.	COMP1560	
C0177 0 00000 7 00000	EXPW2	PZE	EVALUATE EXPRESSION.	COMP1570	
	**,7,**		NON-ZERO TAG MEANS LEAVE IN AC.	COMP1580	
00200 0 00000 0 00534	PZE	FLC	..	COMP1590	
00201 0774 00 1 00310	AXT	LFLD,1	FORM FINAL STORAGE.	COMP1600	
00202 -0500 00 1 00534	CAL	FLD,1	GET WORD.	COMP1610	
00203 0100 00 0 00206	TZE	*+3	IF ZERO, SYMBOL DONE.	COMP1620	
00204 0074 00 4 00004	TSX	\$PIVAR,4	PLACE IN VARIABLE FIELD.	COMP1630	
00205 1 77777 1 00202	TXI	*-3,1,-1	INDEX FOR NEXT WORD.	COMP1640	
00206 0074 00 4 00005	TSX	\$GENOP,4	FINAL OP IS STO.	COMP1650	
00207 606263466060	BCI	1, STO	..	COMP1660	
00210 0774 00 4 00000	RX4	AXT	RESTORE IRS.	COMP1670	
00211 0774 00 2 00000	RX2	AXT	**,2	COMP1680	
C0212 -050C 60 0 00000	CAL*	\$ILC	..	COMP1690	
00213 0734 00 1 00000	PAX	0,1	RESTORE ILC.	COMP1700	
00214 0020 00 4 00002	TRA	2,4	..	COMP1710	
			RETURN.	COMP1720	
SPACE 2				COMP1730	
STORAGE AND CONSTANTS.				COMP1740	
PARTIAL SYMBOL STORAGE.				COMP1750	
C0215 0 00000 0 00000	SYM	PZE	END OF FIELD MARK.	COMP1760	
00216 0 00000 0 00000	TEOF1	PZE	MQ STORAGE.	COMP1770	
00217 0 00000 0 00000	MQ	PZE	LAST BREAK.	COMP1780	
C0220 0 00000 0 00000	LBRK	PZE	TOP OF FLD.	COMP1790	
C0221 0 00000 0 00000	TFLC	PZE	BOTTOM OF FLD.	COMP1800	
00222 0 00000 0 00000	BFLC	PZE	LAST (.	COMP1810	
00223 0 00000 0 00000	LLPAR	PZE	LENGTH OF FLD.	COMP1820	
	00310	LFLD	EQU	ARITHMETIC FIELD BUFFER.	COMP1830
C0534		FLD	BES	200	COMP1840
					COMP1850
					COMP1860
END					

## LITERALS

00534 000000000001
00535 000000000013
00536 000000000014
00537 000000000034
00540 000000000060
00541 000000000074
00542 606060606060

SUBROUTINE COMPOP, COMPILE ARITHMETICS FOR CAP.  
POST PROCESSOR ASSEMBLY DATA

543 IS THE FIRST LOCATION NOT USED BY THIS PROGRAM

REFERENCES TO DEFINED SYMBOLS

217	MQ	41,	61						
75	BRK	50,	65						
534	FLD	125,	144,	162,	164,	170,	174,	200,	202
0	ILC	13,	212						
7	NBK	45,	46,	75					
211	RX2	11							
210	RX4	10,	133						
215	SYM	22,	53,	60,	76,	107			
222	BFLD	135,	137						
32	CALL	16							
134	EOF1	111							
172	EOF2	156							
3	EXPR	166,	176						
124	FCNT	25,	117,	134					
220	LBRK	75,	112,	114					
310	LFLD	24,	124,	201,	224,	534			
1	NSTO	17							
37	SCN1	62							
144	SCN2	155							
130	STX4	123							
221	TFLD	121,	141						
132	XFLD	126							
31	BSCN1	63							
141	BSCN2	171							
30	CPAS1	27							
137	CPAS2	136							
2	ERASE	23							
167	EXPW1	161,	165						
177	EXPW2	172,	175						
5	GENOP	206							
223	LLPAR	142,	157,	163,	173				
157	LPAR2	150							
110	NOSYM	101							
4	PIVAR	204							
161	RPAR2	153							
61	RSCN1	35,	44,	116,	122				
154	RSCN2	140,	145,	160					
123	STFLD	56,	105,	113					
66	TABBK	46,	75						
216	TEOF1	20,	64,	110					
10	COMPCP								

NO ERROR IN ABCVE ASSEMBLY.

\*TIME SPENT IN FAP.. 000008 IN HUNDREDTHS OF MINUTES.

## SUBROUTINE EXPR, EVALUATE EXPRESSION FOR COMPOP.

	PCC		EXPR0010		
00006	COUNT	171	EXPR0020		
	LBL	EXPR	EXPR0040		
	ENTRY	EXPR	EXPR0050		
		BINARY CARD LABEL.	EXPR0060		
		ARITHMETIC EXPRESSION EVALUATOR.	EXPR0070		
*		\$EXPR IS CALLED BY,	EXPR0080		
*			EXPR0090		
*		TSX \$EXPR,4	EXPR0100		
*		PZE LI,T,RI	EXPR0110		
*		PZE FLD	EXPR0120		
*		WHERE (FLD-LI) IS THE ADDRESS OF THE LEFT BREAK,	EXPR0130		
*		AND (FLD-RI) IS THE ADDRESS OF THE RIGHT BREAK.	EXPR0140		
*		EXPR TAKES A STRING OF SYMBOLS CONNECTED BY	EXPR0150		
*		+ - * OR / (S) AND COMPILES THE RESULT IN	EXPR0160		
*		FLOATING POINT. IF T=0, THE RESULT IS PLACED IN	EXPR0170		
*		TEMPORARY STORAGE, OTHERWISE, RESULT IS IN AC. THE	EXPR0180		
*		SYMBOLIC FIELD IS MODIFIED ACCORDINGLY.	EXPR0190		
*			EXPR0200		
*		\$EXPR OPERATES IN TWO PASSES. PASS1 USES \$TERM	EXPR0210		
*		TO REDUCE THE EXPRESSION TO A SUMMATION. PASS2	EXPR0220		
*		PERFORMS THE SUMMATION. SOME OPTIMIZATION	EXPR0230		
*		IS DONE.	EXPR0240		
 TRANSFER VECTOR					
00000	632551446060	TERM			
00001	473165215160	PIVAR			
00002	272545464760	GENOP			
00003	274562634660	GNSTC			
 LINKAGE DIRECTOR					
C0004	000000000000				
C0005	256747516060				
00006	0634 00 4 00164	EXPR	SAVE IRS.	EXPR0250	
00007	0634 00 2 00165	SXA	RX2,2	EXPR0260	
C0010	0634 00 1 00166	SXA	RX1,1	EXPR0270	
00011	-0500 00 4 00001	CAL	1,4	GET CONTROL WORD.	EXPR0280
00012	0622 00 0 00054	STD	RSCN1+1	RIGHT BREAK INDEX, PASS 1.	EXPR0290
00013	0622 00 0 00116	STD	RSCN2+1	RIGHT BREAK INDEX, PASS 2.	EXPR0300
00014	0625 00 0 00171	STT	TAG	SAVE TAG FOR DECISION TO STORE.	EXPR0310
00015	0621 00 0 00065	STA	TRMWD	SAVE LEFT BREAK INDEX FOR FIRST TERM.	EXPR0320
00016	0734 00 1 00000	PAK	0,1	INDEX FOR LEFT BREAK.	EXPR0330
00017	1 77777 1 00020	TXI	*+1,1,-1	INDEX OF FIRST WORD IN FLD.	EXPR0340
00020	0634 00 1 00100	SXA	IWD1,1	SAVE FOR PASS2.	EXPR0350
00021	-0500 00 4 00002	CAL	2,4	INSERT FLD ADDRESSES.	EXPR0360
00022	0621 00 0 00035	STA	EPASI	..	EXPR0370
00023	0621 00 0 00102	STA	SCN2	..	EXPR0380
C0024	0621 00 0 00066	STA	BA1	..	EXPR0390
00025	0621 00 0 00104	STA	BA2	..	EXPR0400
00026	0402 00 0 00176	SUB	=1	..	EXPR0410
C0027	0621 00 0 00160	STA	BA3	..	EXPR0420
00030	0600 00 0 00172	STZ	TEOF	RESET EOF MARK.	EXPR0430
00031	0600 00 0 00170	STZ	LBKR	RESET LEFT BREAK.	EXPR0440
00032	0600 00 0 00173	STZ	TSYM	RESET SYMBOL MARK.	EXPR0450
C0033	0600 00 0 00174	STZ	TSTSL	RESET */ MARK.	EXPR0460

SUBROUTINE EXPR, EVALUATE EXPRESSION FOR COMPOP.

00034 0020 00 0 00035	TRA	EPAS1	GO TO PASS 1 OF EXPR.	EXPRO470
	SPACE	2		
		PASS1, REDUCE TO SUMMATION.		
00035 -0500 00 1 00000	EPAS1	CAL	FLD,1 GET NEXT WORD IN FLD.	EXPRO480
00036 0100 00 0 00053		TZE	RSCN1 IF ZERO, IGNORE.	EXPRO490
00037 -0340 00 0 00202		LAS	=H00000/ CHECK FOR /.	EXPRO500
00040 0020 00 0 00042		TRA	*+2 NO, SKIP.	EXPRO510
00041 0020 00 0 00057		TRA	STSL1 YES, EXIT.	EXPRO520
00042 -0340 00 0 00201		LAS	=H00000* CHECK FOR *.	EXPRO530
00043 0020 00 0 00045		TRA	*+2 NO, SKIP.	EXPRO540
00044 0020 00 0 00057		TRA	STSL1 YES, EXIT.	EXPRO550
00045 -0340 00 0 00200		LAS	=H00000- CHECK FOR -.	EXPRO560
00046 0020 00 0 00050		TRA	*+2 NO, SKIP.	EXPRO570
00047 0020 00 0 00061		TRA	PLMII YES, EXIT.	EXPRO580
00050 -0340 00 0 00177		LAS	=H00000+ CHECK FCR +.	EXPRO590
00051 0020 00 0 00053		TRA	*+2 NO, SKIP.	EXPRO600
00052 0020 00 0 00061		TRA	PLMII YES, EXIT.	EXPRO610
00053 1 77777 1 00054	RSCN1	TXI	*+1,-1 COUNT WORDS.	EXPRO620
00054 3 00000 1 00035		TXH	EPAS1,1,** CHECK FCR EOF.	EXPRO630
00055 -0625 00 0 00172		STL	TEOF SET EOF MARK,	EXPRO640
00056 0020 00 0 00061		TRA	PLMII AND TREAT AS +-.	EXPRO650
00057 -0625 00 0 00174	STSL1	STL	TSTSL * OR / MET, SET MARK.	EXPRO660
00060 0020 00 0 00053		TRA	RSCN1 RESUME SCAN.	EXPRO670
00061 -0520 00 0 00174	PLMII	NZT	TSTSL END OF TERM, CHECK FOR */.	EXPRO680
00062 0020 00 0 00070		TRA	NSTSL NO, SKIP TERM.	EXPRO690
00063 -0634 00 1 00065		SXD	TRMWD,1 SET RIGHT INDEX FOR TERM.	EXPRO700
00064 0074 00 4 00000		TSX	\$TERM,4 GO TO TERM.	EXPRO710
00065 0 00000 0 00000	TRMWD	PZE	**,0,** ..	EXPRO720
00066 0 00000 0 00000	BA1	PZE	fld ..	EXPRO730
00067 0600 00 0 00174		STZ	TSTSL RETURN FROM TERM, RESET STSL.	EXPRO740
00070 0634 00 1 00065	NSTSL	SXA	TRMWD,1 SET NEXT LEFT INDEX.	EXPRO750
00071 -0520 00 0 00172		NZT	TEOF TEST FOR EOF.	EXPRO760
00072 0020 00 0 00053		TRA	RSCN1 NO, RESUME SCAN.	EXPRO770
00073 0020 00 0 00074		TRA	EPAS2 YES, GO TO PASS2.	EXPRO780
	SPACE	2		
		PASS2, COMPUTE SUM.		
00074 0600 00 0 00173	EPAS2	STZ	TSYM RESET SYMBOL MARK.	EXPRO790
00075 -0500 00 0 00177		CAL	=H00000+ SET LBRK=+.	EXPRO800
00076 0602 00 0 00170		SLW	LBRK ..	EXPRO810
00077 -0625 00 0 00175		STL	FIRST SET FIRST ADDEND MARK.	EXPRO820
00100 0774 00 1 00000	IWD1	AXT	**,1 GET INDEX OF FIRST WORD IN FLD.	EXPRO830
00101 0600 00 0 00172		STZ	TECF RESET ECF MARK.	EXPRO840
00102 -0500 00 1 00000	SCN2	CAL	FLD,1 GET NEXT WORD IN FLD.	EXPRO850
00103 0100 00 0 00115		TZE	RSCN2 IF ZERO, IGNORE.	EXPRO860
00104 0600 00 1 00000	BA2	STZ	FLD,1 ZERO FLD LOCATION.	EXPRO870
00105 -0340 00 0 00200		LAS	=H00000- CHECK FOR -.	EXPRO880
00106 0020 00 0 00110		TRA	*+2 NO, SKIP.	EXPRO890
00107 0020 00 0 00121		TRA	BRK YES, EXIT.	EXPRO900

## SUBROUTINE EXPR, EVALUATE EXPRESSION FOR COMPOP.

00110 -0340 00 0 00177	LAS	=H00000+	CHECK FOR +.	EXPR0990	
00111 0020 00 0 00113	TRA	*+2	NO, SKIP.	EXPR1000	
00112 0020 00 0 00121	TRA	BRK	YES, EXIT.	EXPR1010	
00113 0074 00 4 00001	TSX	\$PIVAR,4	SYMBOL, PLACE IN VARIABLE FIELD.	EXPR1020	
00114 -0625 00 0 00173	STL	TSYM	SET SYMBOL MARK.	EXPR1030	
00115 1 77777 1 00116	RSCN2	TXI	*+1,1,-1 COUNT WORDS.	EXPR1040	
00116 3 00000 1 00102	TXH	SCN2,1,*	CHECK FOR EOF.	EXPR1050	
00117 -0625 00 0 00172	STL	TECF	SET EOF MARK,	EXPR1060	
00120 0020 00 0 00121	TRA	BRK	AND TREAT AS +-.	EXPR1070	
SPACE 2 ANALYZE BREAK.				EXPR1080 EXPR1090 EXPR1100	
00121 -0130 00 0 00000	BRK	XCL	GET LAST BREAK,	EXPR1110	
00122 0500 00 0 00170		CLA	AND STORE THIS ONE IN LBRK.	EXPR1120	
00123 -0600 00 0 00170		STQ	LBRK	EXPR1130	
00124 0520 00 0 00175		ZET	FIRST	EXPR1140	
00125 0020 00 0 00137		TRA	FBRK	EXPR1150	
00126 0322 00 0 00177		ERA	=H0000+	EXPR1160	
00127 0100 00 0 00131		TZE	FAC	EXPR1170	
00130 0020 00 0 00134		TRA	FSB	EXPR1180	
00131 0074 00 4 00002	FAD	TSX	\$GENOP,4	EXPR1200	
00132 602621246060		BCI	1, FAD	EXPR1210	
00133 0020 00 0 00153		TRA	EOF2	EXPR1220	
00134 0074 00 4 00002	FSB	TSX	\$GENOP,4	EXPR1240	
00135 602662226060		BCI	1, FSB	EXPR1250	
00136 0020 00 0 00153		TRA	EOF2	EXPR1260	
SPACE 2 FIRST BREAK SECTION.				EXPR1270 EXPR1280 EXPR1290	
00137 -0520 00 0 00173	FBRK	NZT	TSYM	CHECK FOR SYMBOL.	EXPR1300
00140 0020 00 0 00153		TRA	EOF2	NO SYMBCL, IGNORE UNARY OP.	EXPR1310
00141 0600 00 0 00175		STZ	FIRST	FIRST ACCDEND ENCOUNTERED.	EXPR1320
00142 0322 00 0 00177		ERA	=H0000+	CHECK FOR PLUS.	EXPR1330
00143 0100 00 0 00145		TZE	CLA	YES, GO TO IT.	EXPR1340
00144 0020 00 0 00150		TRA	CLS	NO, MUST BE -, GO TO IT.	EXPR1350
00145 0074 00 4 00002	CLA	TSX	\$GENOP,4	LBRK=+, OP=CLA.	EXPR1370
00146 602343216060		BCI	1, CLA	..	EXPR1380
00147 0020 00 0 00153		TRA	EOF2	CHECK FOR EOF.	EXPR1390
00150 0074 00 4 00002	CLS	TSX	\$GENOP,4	LBRK=-, OP=CLS.	EXPR1410
00151 602343626060		BCI	1, CLS	..	EXPR1420
00152 0020 00 0 00153		TRA	EOF2	CHECK FOR EOF.	EXPR1430
SPACE 2 END-OF-FIELD AND RETURN SECTION.				EXPR1440 EXPR1450 EXPR1460	
00153 -0520 00 0 00172	EOF2	NZT	TEOF	TEST FOR EOF REACHED.	EXPR1470
00154 0020 00 0 00115		TRA	RSCN2	NO, RESUME SCAN.	EXPR1480

SUBROUTINE EXPR, EVALUATE EXPRESSION FOR COMPOP.

00155	0520 00 0 00171	ZET	TAG	CHECK TAG OF CONTROL WORD.	EXPR1490	
00156	0020 00 0 00164	TRA	RX4	NON-ZERO, LEAVE IN AC, RETURN.	EXPR1500	
00157	0074 00 4 00003	TSX	\$GNSTO,4	ZERO, GENERATE TEMPORARY STORAGE.	EXPR1510	
00160	0602 00 1 77777	BA3	SLW	FLD-1,1	EXPR1520	
00161	0074 00 4 00001	TSX	\$PIVAR,4	PLACE SYMBOL IN VARIABLE FIELD.	EXPR1530	
00162	0074 00 4 00002	TSX	\$GENOP,4	FINAL OP IS STO.	EXPR1540	
00163	606263466060	BCI	1, STO	..	EXPR1550	
00164	0774 00 4 00000	RX4	AXT	**,4	RESTORE IRS.	EXPR1560
00165	0774 00 2 00000	RX2	AXT	**,2	..	EXPR1570
00166	0774 00 1 00000	RXI	AXT	**,1	..	EXPR1580
00167	0020 00 4 00003	TRA		3,4	RETURN TO CALLER.	EXPR1590

SPACE	2				
		STORAGE AND CONSTANTS.			
00170	0 00000 0 00000	LBRK	PZE	LAST BREAK.	EXPR1600
00171	0 00000 0 00000	TAG	PZE	TAG OF CONTROL WORD.	EXPR1610
00172	0 00000 0 00000	TEOF	PZE	EOF MARK.	EXPR1620
00173	0 00000 0 00000	TSYM	PZE	SYMBOL MARK.	EXPR1630
00174	0 00000 0 00000	TSTSL	PZE	*/ MARK.	EXPR1640
00175	0 00000 0 00000	FIRST	PZE	FIRST ADDEND MARK.	EXPR1650
	00000	FLD	EQU	DUMMY SYMBOL FOR FLD.	EXPR1660
			**		EXPR1670
					EXPR1680
					EXPR1690
					EXPR1700
					EXPR1710

LITERALS

00176	000000000C01
00177	000000000020
00200	000000000040
00201	000000000054
00202	000000000061

SUBROUTINE EXPR, EVALUATE EXPRESSION FOR COMPOP.  
POST PROCESSOR ASSEMBLY DATA

06

203 IS THE FIRST LOCATION NOT USED BY THIS PROGRAM

REFERENCES TO DEFINED SYMBOLS

66	BA1	24
104	BA2	25
160	BA3	27
121	BRK	107, 112, 120
145	CLA	143
150	CLS	144
131	FAD	127
0	FLD	35, 66, 102, 104, 160, 176
134	FSB	130
166	RX1	10
165	RX2	7
164	RX4	6, 156
171	TAG	14, 155
153	EOF2	133, 136, 140, 147, 152
6	EXPR	
137	FBRK	125
100	IWC1	20
170	LBRK	31, 76, 122, 123
102	SCN2	23, 116
172	TEOF	30, 55, 71, 101, 117, 153
0	TERM	64
173	TSYM	32, 74, 114, 137
35	EPAS1	22, 34, 54
74	EPAS2	73
175	FIRST	77, 124, 141
2	GENCP	131, 134, 145, 150, 162
3	GNSTC	157
70	NSTSL	62
1	PIVAR	113, 161
61	PLMI1	47, 52, 56
53	RSCN1	12, 36, 60, 72
115	RSCN2	13, 103, 154
57	STSL1	41, 44
65	TRMWD	15, 63, 70
174	TSTSL	33, 57, 61, 67

NO ERROR IN ABCVE ASSEMBLY.

\*TIME SPENT IN FAP.. 000008 IN HUNDREDTHS OF MINUTES.

SUBROUTINE TERM, EVALUATE SIMPLE TERMS FOR EXPR.

	PCC		TERM0010	
00006	COUNT 135		TERM0020	
	LBL TERM	BINARY CARD LABEL.	TERM0040	
	ENTRY TERM	EVALUATE TERM OF EXPRESSION.	TERM0050	
	*	\$TERM IS CALLED BY,	TERM0060	
	*		TERM0070	
	*	TSX \$TERM,4	TERM0080	
	*	PZE LI,0,RI	TERM0090	
	*	PZE FLD	TERM0100	
	*		TERM0110	
	*	WHERE (FLD-LI) IS THE ADDRESS OF THE LEFT BREAK,	TERM0120	
	*	AND (FLD-RI) IS THE ADDRESS OF THE RIGHT BREAK.	TERM0130	
	*	TERM TAKES A STRING OF SYMBOLS CONNECTED BY	TERM0140	
	*	* OR / (S) AND COMPILES THE RESULT IN FLOATING	TERM0150	
	*	POINT. THE RESULT IS STORED IN TEMPORARY	TERM0160	
	*	STORAGE, AND THE SPREAD FIELD IS MODIFIED ACCORDINGLY.	TERM0170	
	*	SOME OPTIMIZATION IS DONE.	TERM0180	
			TERM0190	
	TRANSFER VECTOR			
00000	473165215160	PIVAR		
00001	272545464760	GENOP		
00002	255121622560	ERASE		
00003	274562634660	GNSTC		
	LINKAGE DIRECTOR			
00004	000000000000			
00005	632551446060			
00006	0634 00 4 00133	TERM	SXA RX4,4 SAVE IRS.	TERM0200
00007	0634 00 2 00134		SXA RX2,2 ..	TERM0210
00010	0634 00 1 00135		SXA RX1,1 ..	TERM0220
00011	-0500 00 4 00001	CAL	1,4 GET CONTROL WORD.	TERM0230
00012	0622 00 0 00037	STD	RSCAN+1 INDEX OF RIGHT BREAK.	TERM0240
00013	0734 00 1 00000	PAX	0,1 INDEX OF LEFT BREAK.	TERM0250
00014	1 77777 1 00015	TXI	*+1,1,-1 INDEX OF FIRST WCRD IN FLD.	TERM0260
00015	-0500 00 4 00002	CAL	2,4 INSERT BUFFER ADDRESSES.	TERM0270
00016	0621 00 0 00024	STA	SCAN ..	TERM0280
00017	0621 00 0 00026	STA	BA1 ..	TERM0290
00020	0402 00 0 00140	SUB	=1 ..	TERM0300
00021	0621 00 0 00117	STA	BA2 ..	TERM0310
00022	0621 00 0 00127	STA	BA3 ..	TERM0320
00023	0600 00 0 00137	STZ	LBRK RESET LAST BREAK.	TERM0330
00024	-0500 00 1 00000	SCAN	CAL FLD,1 GET NEXT WORD IN FLD.	TERM0340
00025	0100 00 0 00036		TZE RSCAN IF ZERO, IGNORE.	TERM0350
00026	0600 00 1 00000	BA1	STZ FLD,1 ZERO FLD LOCATION.	TERM0360
00027	-0340 00 0 00142	LAS	=HC0000/ CHECK FOR /.	TERM0370
00030	0020 00 0 00032	TRA	*+2 NO, SKIP.	TERM0380
00031	0020 00 0 00063	TRA	SLASH YES, GO TO IT.	TERM0390
00032	-0340 00 0 00141	LAS	=HC0000* CHECK FOR *.	TERM0400
00033	0020 00 0 00035	TRA	*+2 NO, SKIP.	TERM0410
00034	0020 00 0 00041	TRA	STAR YES, GO TO IT.	TERM0420
00035	0074 00 4 00000	TSX	\$PIVAR,4 SYMBOL, PLACE IN VARIABLE FIELD.	TERM0430
00036	1 77777 1 00037	RSCAN TXI	*+1,1,-1 COUNT WORDS.	TERM0440
00037	3 00000 1 00024	TXH	SCAN,1,** CHECK FOR EOF.	TERM0450
				TERM0460

## SUBROUTINE TERM, EVALUATE SIMPLE TERMS FOR EXPR.

00040	0020 00 0 00105	TRA	EOF	EOF, GO TO IT.	TERM0470
		SPACE	2	BREAK=*.	TERM0480
00041	-0130 00 0 00000	STAR	XCL	STAR, GET LAST BREAK.	TERM0490
00042	-0500 00 0 00137	CAL	LBRK	THEN PLACE * IN LBRK.	TERM0500
00043	-0600 00 0 00137	STQ	LBRK	..	TERM0510
00044	0100 00 0 00050	TZE	ST1	IF LBRK=0, GO TO IT.	TERM0520
00045	0322 00 0 00141	ERA	=H00000*	CHECK, LBRK=*.	TERM0530
00046	0100 00 0 00053	TZE	ST2	YES, GO TO IT.	TERM0540
00047	0020 00 0 00060	TRA	ST3	NO, MUST BE /, GO TO IT.	TERM0550
00050	0074 00 4 00001	ST1	TSX	\$GENOP,4	TERM0560
00051	604324506060	BCI	1, LDQ	LBRK=0, OP=LDQ.	TERM0570
00052	0020 00 0 00036	TRA	RSCAN	.. RESUME SCAN.	TERM0580
00053	0074 00 4 00001	ST2	TSX	\$GENOP,4	TERM0590
00054	602644476060	BCI	1, FMP	LBRK=*, OP=FMP.	TERM0600
00055	0074 00 4 00001	TSX	\$GENOP,4	.. THEN, OP=XCA.	TERM0610
00056	606723216060	BCI	1, XCA	.. RESUME SCAN.	TERM0620
00057	0020 00 0 00036	TRA	RSCAN	TERM0630	
00060	0074 00 4 00001	ST3	TSX	\$GENOP,4	TERM0640
00061	602624476060	BCI	1, FDP	LBRK=1, OP=FDP.	TERM0650
00062	0020 00 0 00036	TRA	RSCAN	.. RESUME SCAN.	TERM0660
		SPACE	2	BREAK=/.	TERM0670
00063	-0130 00 0 00000	SLASH	XCL	SLASH, GET LAST BREAK.	TERM0680
00064	-0500 00 0 00137	CAL	LBRK	THEN PLACE / IN LBRK.	TERM0690
00065	-0600 00 0 00137	STQ	LBRK	..	TERM0700
00066	0100 00 0 00072	TZE	SL1	IF LBRK=0, GO TO IT.	TERM0710
00067	0322 00 0 00141	ERA	=H00000*	CHECK, LBRK=*.	TERM0720
00068	0100 00 0 00075	TZE	SL2	YES, GO TO IT.	TERM0730
00069	0020 00 0 00100	TRA	SL3	NO, MUST BE /, GO TO IT.	TERM0740
00072	0074 00 4 00001	SL1	TSX	\$GENOP,4	TERM0750
00073	602343216060	BCI	1, CLA	LBRK=0, OP=CLA.	TERM0760
00074	0020 00 0 00036	TRA	RSCAN	.. RESUME SCAN.	TERM0770
00075	0074 00 4 00001	SL2	TSX	\$GENOP,4	TERM0780
00076	602644476060	BCI	1, FMP	LBRK=*, OP=FMP.	TERM0790
00077	0020 00 0 00036	TRA	RSCAN	.. RESUME SCAN.	TERM0800
00100	0074 00 4 00001	SL3	TSX	\$GENOP,4	TERM0810
00101	602624476060	BCI	1, FDP	LBRK=1, OP=FDP.	TERM0820
00102	0074 00 4 00001	TSX	\$GENOP,4	.. THEN, OP=XCA.	TERM0830
00103	606723216060	BCI	1, XCA	.. RESUME SCAN.	TERM0840
00104	0020 00 0 00036	TRA	RSCAN	TERM0850	

SUBROUTINE TERM, EVALUATE SIMPLE TERMS FOR EXPR.

		SPACE	2		
		ENC-OF-FIELD AND RETURN SECTION.			
C0105	-0500 00 0 00137	EOF	CAL	LBRK	EOF, GET LBRK.
00106	0100 00 0 00112	TZE	EOF1		IF LBRK=0, GO TO IT.
00107	0322 00 0 00141	ERA	=H000CO*		CHECK, LBRK=*.
00110	0100 00 0 00114	TZE	EOF2		YES, GO TO IT.
C0111	0020 00 0 00124	TRA	EOF3		NO, MUST BE /, GO TO IT.
00112	0074 00 4 00002	EOF1	TSX	\$ERASE,4	LBRK=0, NO COMPILEATION.
00113	0020 00 0 00133	TRA	RX4		GO TO RETURN.
00114	0074 00 4 00001	EOF2	TSX	\$GENOP,4	LBRK=*, OP=FMP.
00115	602644476060	BCI	1, FMP		..
00116	0074 00 4 00003	TSX	\$GNSTO,4		GENERATE TEMPORARY STORAGE.
00117	0602 00 1 77777	BA2	SLW	FLC-1,1	INSERT IN FLD.
00120	0074 00 4 00000	TSX	\$PIVAR,4		PLACE SYMBOL IN VARIABLE FIELD.
00121	0074 00 4 00001	TSX	\$GENOP,4		FINAL OP IS STO.
00122	606263466060	BCI	1, STO		..
00123	0020 00 0 00133	TRA	RX4		GO TO RETURN.
00124	0074 00 4 00001	EOF3	TSX	\$GENOP,4	LBRK=/, OP=FDP.
00125	602624476060	BCI	1, FDP		..
00126	0074 00 4 00003	TSX	\$GNSTO,4		GENERATE TEMPORARY STORAGE.
00127	0602 00 1 77777	BA3	SLW	FLC-1,1	INSERT IN FLD.
00130	0074 00 4 00000	TSX	\$PIVAR,4		PLACE SYMBOL IN VARIABLE FIELD.
00131	0074 00 4 00001	TSX	\$GENOP,4		FINAL OP IS STQ.
00132	606263506060	BCI	1, STQ		..
00133	0774 00 4 00000	RX4	AXT	**,4	RESTORE IRS.
00134	0774 00 2 00000	RX2	AXT	**,2	..
C0135	0774 00 1 C0000	RX1	AXT	**,1	..
00136	0020 00 4 00003	TRA		3,4	RETURN TO CALLER.
		SPACE	2		
		STORAGE AND CONSTANTS.			
00137	0 00000 0 00000 00000	LBRK FLD	PZE EQU	**	LAST BREAK CHARACTER. DUMMY SYMBOL FOR FLD.
		END			

LITERALS

C0140 000000000001  
00141 000000000054  
00142 000000000061

SUBROUTINE TERM, EVALUATE SIMPLE TERMS FOR EXPR.  
POST PROCESSOR ASSEMBLY DATA

143 IS THE FIRST LOCATION NOT USED BY THIS PROGRAM

REFERENCES TO DEFINED SYMBOLS

26	BA1	17
117	BA2	21
127	BA3	22
105	ECF	40
0	FLD	24, 26, 117, 127, 140
135	RX1	10
134	RX2	7
133	RX4	6, 113, 123
72	SL1	66
75	SL2	70
100	SL3	71
50	ST1	44
53	ST2	46
60	ST3	47
112	EOF1	106
114	EOF2	110
124	EOF3	111
137	LBRK	23, 42, 43, 64, 65, 105
24	SCAN	16, 37
41	STAR	34
6	TERM	
2	ERASE	112
1	GENOP	50, 53, 55, 60, 72, 75, 100, 102, 114, 121, 124, 131
3	GNSTO	116, 126
0	PIVAR	35, 120, 130
36	RSCAN	12, 25, 52, 57, 62, 74, 77, 104
63	SLASH	31

NO ERROR IN ABOVE ASSEMBLY.

\*TIME SPENT IN FAP.. 000006 IN HUNDREDTHS OF MINUTES.

CIOP . . . BUFFERED I/O PACKAGE FOR CAP. NO TAPE ERROR CHECKING.

	PCC				
	COUNT	147			
00003	LBL	CIOP	BINARY CARD LABEL.	CIOP0010	
00154	ENTRY	READ1	READ ONE RECORD ON INPUT TAPE.	CIOP0020	
00030	ENTRY	PRINT	WRITE ONE RECORD ON OUTPUT TAPE.	CIOP0040	
00104	ENTRY	WCT1	WRITE ONE RECORD ON COLLATION TAPE.	CIOP0050	
00110	ENTRY	REWIND	END-FILE AND REWIND COLLATION TAPE.	CIOP0060	
	ENTRY	READ2	READ ONE RECORD FROM COLLATION TAPE.	CIOP0070	
				CIOP0080	
				CIOP0090	
				CIOP0100	
<b>TRANSFER VECTOR</b>					
00000	256731636060	EXIT			
<b>LINKAGE DIRECTOR</b>					
00001	000000000000				
00002	512521240160				
00003	0634 00 2 00013	READ1	SXA RX2,2	SAVE IR2.	CIOP0110
00004	-0500 00 4 00001		CAL 1,4	GET BUFFER ADDRESS.	CIOP0120
00005	0621 00 0 00015		STA INCARD	INSERT IN I/O COMMAND.	CIOP0130
00006	0762 00 0 01202		RTDA 2	SELECT INPUT TAPE.	CIOP0140
00007	0540 00 0 00015		RCHA INCARD	START DATA CHANNEL.	CIOP0150
00010	0060 00 0 00010		TCOA *	WAIT FOR DATA TO ARRIVE.	CIOP0160
00011	0774 00 2 00016		AXT WEOF1,2	GET ERROR COMMENT LOCATION.	CIOP0170
00012	0030 00 0 00214		TEFA ERROR	CHECK FOR ERROR.	CIOP0180
00013	0774 00 2 00000	RX2	AXT **,2	RESTORE IR2.	CIOP0190
00014	0020 00 4 00002		TRA 2,4	RETURN TO CALLER.	CIOP0200
00015	0 00016 0 00000	INCARD	IOCD **,0,14	READ ONE 14 WORD RECORD AND STOP.	CIOP0210
00016	0 00011 0 00017	WEOF1	IOCD **+1,0,9	OUTPUT COMMENT IN CASE OF ERROR.	CIOP0220
00017	002545246046		BCI 9,0	END OF FILE REACHED WHILE READING CAP INPUT TAPE.	CIOP0230
00020	266026314325				CIOP0240
00021	605125212330				CIOP0250
00022	252460663031				
00023	432560512521				
00024	243145276023				
00025	214760314547				
00026	646360632147				
00027	253360606060				
00030	0634 00 4 00067	WCT1	SXA WX4,4	SAVE IRS.	CIOP0260
00031	0634 00 2 00066		SXA WX2,2	..	CIOP0270
00032	-0520 00 0 00223		NZT FSTART	IS THIS THE FIRST CALL.	CIOP0280
00033	0772 00 0 02203		REWB 3	YES, MAKE SURE TAPE REWOUND.	CIOP0290
00034	-0625 00 0 00223		STL FSTART	SET MARKER.	CIOP0300
00035	-0500 00 4 00001		CAL 1,4	GET CONTROL WORD.	CIOP0310
00036	0625 00 0 00225		STT TAG	GET TAG.	CIOP0320
00037	-0520 00 0 00225		NZT TAG	IF ZERO,	CIOP0330
					CIOP0340
					CIOP0350
					CIOP0360
					CIOP0370
					CIOP0380
					CIOP0390
					CIOP0400
					CIOP0410

## CIOP . . . BUFFERED I/O PACKAGE FOR CAP. NO TAPE ERRGR CHECKING.

00040	-0500 00 0 00263	CAL	=14B17	ASSUME 14 WORDS IN BUFFER.	CIOP0420	
00041	-0734 00 2 00000	PDX	0,2	SAVE COUNT FOR MOVE OPERATION.	CIOP0430	
00042	0771 00 0 00022	ARS	18	MOVE COUNT TO ADDRESS.	CIOP0440	
00043	0361 00 4 00001	ACL	1,4	FCRM END ADDRESS.	CIOP0450	
00044	0621 00 0 00054	STA	PCKUP	INSERT IN PICKUP INSTRUCTION.	CIOP0460	
00045	0754 00 2 00000	PXA	0,2	SAVE IR2 IN AC.	CIOP0470	
00046	0774 00 2 00072	AXT	WEOCT,2	GET ADDRESS OF ERROR COMMENT.	CIOP0480	
00047	0061 00 0 00047	TCOB	*	WAIT FOR PREVIOUS WRITE TO FINISH.	CIOP0490	
00050	-0760 00 0 02000	ETTB		CHECK FOR END OF TAPE ON LAST WRITE.	CIOP0500	
00051	0020 00 0 00214	TRA	ERROR	END OF TAPE ENCOUNTERED, GO COMPLAIN.	CIOP0510	
00052	0734 00 2 00000	PAX	0,2	RESTORE IR2.	CIOP0520	
00053	0774 00 4 00016	AXT	14,4	SET MCVE COUNTER.	CIOP0530	
00054	-0500 00 2 00000	PCKUP	CAL	MOVE DATA INTO OUTPUT BUFFER.	CIOP0540	
00055	0602 00 4 00262	SLW	SLW	INSERT.	CIOP0550	
00056	-2 00001 4 00060	TNX	*+2,4,1	COUNT.	CIOP0560	
00057	2 00001 2 00054	TIX	PCKUP,2,1	INDEX, AND GET NEXT WORD.	CIOP0570	
00058	-3 00001 4 00064	TXL	*+4,4,1	IS BUFFER FULL.	CIOP0580	
00059	0061 -0500 00 0 00264	CAL	=H	NO, FILL IT OUT WITH BLANKS.	CIOP0590	
00060	0602 60 0 00055	SLW*	SLW	..	CIOP0600	
00061	2 00001 4 00061	TIX	*-2,4,1	TEST FOR BUFFER FULL.	CIOP0610	
00062	0766 00 0 02223	WTBB	3	SELECT COLLATION TAPE.	CIOP0620	
00063	-0540 00 0 00071	RCHB	IOWCT	START CHANNEL.	CIOP0630	
00064	0774 00 2 00000	WX2	AXT	RESTORE IRS.	CIOP0640	
00065	0774 00 4 00000	WX4	AXT	..	CIOP0650	
00066	0020 00 4 00002	TRA	2,4	RETURN TO CALLER.	CIOP0660	
00067	0 00016 0 00244	IOWCT	I OCD	WBUFF,0,14	WRITE A 14 WORD RECORD AND STOP.	CIOP0670
00068	0 00011 0 00073	WE OCT	I OCD	*+1,,9		
00069	002545246046	BCI		9,0END OF TAPE REACHED WHILE WRITING COLLATION TAPE.	CIOP0680	
00070	266063214725				CIOP0690	
00071	605125212330				CIOP0700	
00072	252460663031				CIOP0710	
00073	432560665131					
00074	633145276023					
00075	464343216331					
00076	464560632147					
00077	253360606060					
00078	00104 0770 00 0 02203	REWIND	WE FB	3	WRITE AN END OF FILE.	CIOP0720
00079	-0625 00 0 00224	STL	TREW		SET MARK FOR TAPE REWOUND.	CIOP0730
00080	00106 0772 00 0 02203	REWB		3	NOW REWIND TAPE.	CIOP0740
00081	00107 0020 00 4 000C1	TRA		1,4	RETURN TO CALLER.	CIOP0750
00082	00110 0634 00 2 00122	READ2	SXA	R2X2,2	SAVE IR2.	CIOP0760
00083	-0520 00 0 00224	NZT	TREW		HAS COLLATION TAPE BEEN REWOUND.	CIOP0770
00084	00111 0020 00 0 00125	TRA	NREW		NO, GO COMMENT.	CIOP0780
00085	00112 -0500 00 4 00001	CAL	1,4		GET CCNTROL WORD.	CIOP0790
00086	00113 0621 00 0 00124	STA	IOTIN		INSERT BUFFER ADDRESS IN I/O COMMAND.	CIOP0800
00087	00114 0762 00 0 02223	RTBB	3		READ SELECT COLLATION TAPE.	CIOP0810
00088	00115 -0540 00 0 00124	RCHB	IOTIN		START CHANNEL.	CIOP0820
00089	00116 0774 00 2 00142	AXT	WECFC,2		GET ADDRESS OF ERROR COMMENT.	CIOP0830
00090	00117 0061 00 0 00120	TCOB	*		WAIT FOR BUFFER TO FILL.	CIOP0840
00091	00118 -0030 00 0 00214	TEFB	ERROR		HAS END OF FILE BEE N REACHED.	CIOP0850
00092	00119 0774 00 2 00000	R2X2	AXT	**,,2	ALL OK, RESTORE IR2.	CIOP0860
00093	00120 0020 00 4 00002	TRA		2,4	RETURN TO CALLER.	CIOP0870

CIOP . . . BUFFERED I/O PACKAGE FOR CAP. NO TAPE ERROR CHECKING.

00124	3 00016 0 00000	IOTIN IORT	**,,14	READ CNE RECORD AND STOP.	CIOP0900 CIOP0910 CIOP0920 CIOP0930 CIOP0940 CIOP0950 CIOP0960 CIOP0970 CIOP0980
00125	0074 00 4 00154	NREW TSX	PRINT,,4	FORGOT TO REWIND, COMMENT.	CIOP0930
00126	0 00011 0 00131	PZE	WNREW,,0,9	..	CIOP0940
00127	0074 00 4 00104	TSX	REWIND,,4	REWIND IT.	CIOP0950
00130	0020 00 0 00113	TRA	READ2+3	RETURN TO READ ROUTINE.	CIOP0960 CIOP0970
00131	005125212402	WNREW BCI	9,CREAD2 CALLED BEFORE REWIND, COLLATION TAPE REWOUND.	CIOP0980	
00132	602321434325				
00133	246022252646				
00134	512560 512566				
00135	314524736023				
00136	464343216331				
00137	464560632147				
00140	256051256646				
00141	644524336060				
00142	0 00011 0 00143	WEOF C IOCD	*+1,,9	OUTPUT COMMENT IF ERROR.	CIOP0990
00143	002545246046	BCI	9,0END OF FILE REACHED WHILE READING COLLATION TAPE.	CIOP1000 CIOP1010	
00144	266026314325				
00145	605125212330				
00146	252460663031				
00147	432560512521				
00150	243145276023				
00151	464343216331				
00152	464560632147				
00153	253360606060				
00154	0634 00 2 00201	PRINT SXA	PX2,,2	SAVE IR2.	CIOP1020
00155	0774 00 2 00204	AXT	WLNX,,2	GET ADDRESS OF ERROR COMMENT.	CIOP1030
00156	0500 00 0 00222	CLA	LNCNT	GET LINECOUNT.	CIOP1040
00157	0402 00 0 00262	SUB	=1	LOWER BY ONE.	CIOP1050
00160	0601 00 0 00222	STO	LNCNT	RETURN.	CIOP1060
00161	-0120 00 0 00214	TMI	ERROR	EXIT IF TOO MANY LINES.	CIOP1070
00162	-0500 00 4 00001	CAL	1,,4	GET CONTROL WORD.	CIOP1080
00163	0622 00 0 00203	STD	PIO	INSERT COUNT IN I/O COMMAND.	CIOP1090
00164	-0734 00 2 00000	PDX	0,,2	GET COUNT.	CIOP1100
00165	0771 00 0 00022	ARS	18	MOVE TO ADDRESS.	CIOP1110
00166	0361 00 4 00001	ACL	1,,4	FORM END ADDRESS.	CIOP1120
00167	0621 00 0 00174	STA	GET	INSERT IN PICKUP.	CIOP1130
00170	0754 00 2 00000	PXA	0,,2	GET COUNT.	CIOP1140
00171	0361 00 0 00203	ACL	PIO	FORM BUFFER END ADDRESS.	CIOP1150
00172	0621 00 0 00175	STA	GIVE	INSERT IN STORE.	CIOP1160
00173	0060 00 0 00173	TCOA	*	WAIT FOR LAST PRINT TO FINISH.	CIOP1170
00174	-0500 00 2 00000	GET	CAL	MOVE DATA TO OUTPUT BUFFER.	CIOP1180
00175	0602 00 2 00000	GIVE	SLW	**,,2	CIOP1190
00176	2 00001 2 00174	TIX	**-2,,2,1	..	CIOP1200
00177	0766 00 0 01203	WTDA	3	WRITE SELECT OUTPUT TAPE.	CIOP1210
00200	0540 00 0 00203	RCHA	PIO	START CHANNEL.	CIOP1220
00201	0774 00 2 00000	PX2	AXT	RESTORE IRS.	CIOP1230
00202	0020 00 4 00002	TRA	2,,4	RETURN TO CALLER.	CIOP1240
00203	0 00000 0 00226	PIO	IOCD	PBUFF,,**	CIOP1250
00204	0 00007 0 00205	WLNX	IOCD	*+1,,7	CIOP1260
				OUTPUT COMMENT IF ERROR.	CIOP1270
					CIOP1280
					CIOP1290

## CIOP . . . BUFFERED I/O PACKAGE FOR CAP. NO TAPE ERROR CHECKING.

00205	004751462751	BCI	7,CPROGRAMMER OUTPUT EXCEEDS 300 RECORDS.	CIOP1300
00206	214444255160			
00207	466463476463			
00210	602567232525			
00211	246260030000			
00212	605125234651			
00213	246233606060			
GENERAL ERROR ROUTINE. MAKE SPECIFIED COMMENT, THEN RETURN TO MONITOR VIA EXIT.				
00214	0634 00 2 00216	ERRCR SXA	*+2,2	CIOP1310
00215	0766 00 0 01203	WTDA	3	CIOP1320
00216	0540 00 0 00000	RCHA	**	CIOP1330
00217	0074 00 4 00000	CALL	EXIT	CIOP1340
00220	1 00000 0 00222			CIOP1350
00221	0 10403 0 00001			CIOP1360
STORAGE AND CONSTANTS.				
00222	0 0C000 0 00454	LNCNT PZE	300	CIOP1390
00223	0 00000 0 00000	FSTART PZE		CIOP1400
00224	0 00000 0 00000	TREW PZE		CIOP1410
00225	0 00000 0 00000	TAG PZE		CIOP1420
00226		PBUFF BSS	14	CIOP1430
00244		WBUFF BSS	14	CIOP1440
		END		CIOP1450
				CIOP1460
				CIOP1470
LITERALS				
C0262	000C00000001			
C0263	000C16000000			
C0264	606060606060			

CIOP . . . BUFFERED I/O PACKAGE FOR CAP. NO TAPE ERROR CHECKING.  
POST PROCESSOR ASSEMBLY DATA

265 IS THE FIRST LOCATION NOT USED BY THIS PROGRAM

REFERENCES TO DEFINED SYMBOLS

174	GET	167
203	PIC	163, 171, 200
201	PX2	154
13	RX2	3
55	SLW	62
225	TAG	36, 37
66	WX2	31
67	WX4	30
0	EXIT	217
175	GIVE	172
125	NREW	112
122	R2X2	110
224	TREW	105, 111
30	WCT1	
214	ERROR	12, 51, 121, 161
124	IOTIN	114, 116
71	IOWCT	65
222	LNCNT	156, 160
226	PBUFF	203
54	PCKUP	44, 57
154	PRINT	125
3	READ1	
110	READ2	130
244	WBUFF	55, 71
72	WEOCT	46
142	WEOfC	117
16	WEOfI	11
204	WLNX	155
131	WNREW	126
223	FSTART	32, 34
15	INCARD	5, 7
104	REWIND	127

NO ERROR IN ABCVE ASSEMBLY.

\*TIME SPENT IN FAP.. 000007 IN HUNDRETHS OF MINUTES.

TEST OF CAP, BEGIN ASSEMBLY.						
	CAP	REM	THE FOLLOWING ARE ALL LEGAL CAP INSTRUCTIONS.			
			LDQ	ZERO	ZERO TEST CELLS	
50000	056000050016	COUNT	STQ	BITS	COUNT 36 BITS.	
50001	460000050021		LXA	THSX	BIT OR NO.	
50002	053400450020		LBT	NO	NO BIT.	
50003	076000000001	LCOP	TRA	WORD	BIT, SAVE AC,	
50004	002000050013		SLW	BITS	AND INCREMENT COUNT.	
50005	060200050022	YES	CAL	BITS		
50006	450000050021		ACL	ONE		
50007	036100050017		SLW	BITS		
50010	060200050021		CAL	'WORD	RESTORE AC.	
50011	450000050022		LGR	1	NEXT BIT.	
50012	476500000001		TIX	LOOP	INDEX.	
50013	200001450003	NO	CAL	BITS	GET COUNT.	
50014	450000050021		OCTL	002100070000	STOP WITH TRANSFER TO 70000 OCTAL.	
50015	002100070000	DONE	REM	STORAGE.		
50016	000000000000	ZERO	OCTL	000000000000	TRUE ZERO.	
50017	000001000000	ONE	INT	1	INCREMENT OF ONE.	
50020	434000000044	THSX	LAS	36	ADDRESS IS 36.	
			REM	CATA.		
50021	000000000000	BITS	INT	0	STORAGE FOR BIT COUNT.	
50022	000000000000	WORD	INT	0	TEMPORARY STORAGE FOR AC.	
			REM	TEST OF CAP PSEUDO-OPS, AND FLAGS.		
O	50023	0000000C0010	ILCD	8	ILLEGAL OPCODE.	
U	50024	002000000000	TRA	UNDEF	UNDEFINED SYMBOL.	
E	50025	000001000000	INT	1,2,-7,13A3,9	ERROR IN INTOP.	
OU	50032	000000000000	WMW	AEN	ILLEGAL OPCODE AND UNDEFINED SYMBOL.	
			COMP	NO = YES + LOOP		
50033	050000050005		CLA	YES		
50034	030000050003		FAD	LOOP		
50035	060100050013		STO	NO		
		COMP	COMP	COUNT = LOOP * YES * NO / DONE / ZERO / ONE		
50036	056000050003		LDQ	LOOP		
50037	026000050005		FMP	YES		
50040	013100000000		XCA			
50041	026000050013		FMP	NO		
50042	024100050015		FDP	DONE		
50043	013100000000		XCA			
50044	024100050016		FDP	ZERO		
50045	013100000000		XCA			
50046	024100050017		FDP	ONE		
50047	460000050110		STQ	TEM		
50050	050000050110		CLA	TEM		
50051	060100050000		STO	COUNT		
50052	002000050036		TRA	COMP	USE OF SYMBOL DEFINED BY COMP.	
		COMP	COUNT,1 = WORD,2 - DONE,4			TSTCAP30
50053	050000050022		CLA	WORD,2		
50054	030200050015		FSB	DONE,4		
50055	060100050000		STO	COUNT,1		
		COMP	WORD = (BITS+THSX*(ONE+THSX*(ZERO+THSX*(DONE+THSX*NO))))			TSTCAP31
50056	056000050020		LDQ	THSX		
50057	026000050013		FMP	NO		
50060	060100050110		STO	TEM		
50061	050000050015		CLA	CONE		
50062	030000050110		FAD	TEM		
50063	060100050111		STO	TEM+1		
50064	056000050020		LDQ	THSX		
50065	026000050111		FMP	TEM+1		
50066	060100050112		STO	TEM+2		

50067	050000050016	CLA	ZERO
50070	030000050112	FAD	TEM+2
50071	060100050113	STO	TEM+3
50072	056000050020	LDQ	THSX
50073	026000050113	FMP	TEM+3
50074	060100050114	STO	TEM+4
50075	050000050017	CLA	ONE
50076	030000050114	FAD	TEM+4
50077	060100050115	STO	TEM+5
50100	056000050020	LDQ	THSX
50101	026000050115	FMP	TEM+5
50102	060100050116	STO	TEM+6
50103	050000050021	CLA	BITS
50104	030000050116	FAD	TEM+6
50105	060100050117	STO	TEM+7
50106	050000050117	CLA	TEM+7
50107	060100050022	STO	WORD
		TEM	REM TEMPORARY STORAGE AREA BEGINS HERE.
	50000	END	COUNT FINALLY THE END.

TSTCAP33

RETURN FROM CAP, ENTRY POINT IS 50000.



## Appendix B

### PROGRAMS TO ALLOW USE OF CAP IN THE LABORATORY

This appendix contains FAP assembly listings of subprograms of the execution monitor and the I/O simulator used when CAP is used as a laboratory exercise. The listings are followed by a typical student output when running under the execution monitor. This output includes a storage map, CAP assembly listing, and postmortem.

<u>Index to Appendix B</u>	<u>Page</u>
Main program to call execution monitor	104
TESTS	105
TESTS) and associated entry points	106
RIP, WCT1, REWIND, READ2, PRINT, PPRØG, PCT1, READ1	143
PRØG	152
Typical output listing	155

## MAIN PROGRAM FOR CAP.

PCC			MAIN0010
COUNT	8		MAIN0020
LBL	MAIN	BINARY CARD LABEL.	MAIN0030

TRANSFER VECTOR  
00000 632562636260 TESTS

00001 0074 00 4 00000	TSX \$TESTS,4	GO TO TESTS WITH INDEX.	MAIN0050
00002 00002	DUP 1,3	THESE CARDS CANNOT BE DUPLICATED.	MAIN0060
00002 -3 77777 7 77777	SVN -1,7,-1	..	MAIN0070
00003 -3 77777 7 77777			
00004 -3 77777 7 77777	END		MAIN0080

## POST PROCESSOR ASSEMBLY DATA

5 IS THE FIRST LOCATION NOT USED BY THIS PROGRAM

REFERENCES TO DEFINED SYMBOLS  
0 TESTS 1

NO ERROR IN ABOVE ASSEMBLY.  
\*TIME SPENT IN FAP.. 000002 IN HUNDREDS OF MINUTES.

TESTS FOR CAP, SWITCH FOR INTERVAL TIMER.

	PCC			
	COUNT	12		TESTS010
00004	LBL	TESTS	BINARY CARD LABEL.	TESTS020
	ENTRY	TESTS	INTERLUCE TO TESTS).	TESTS030
				TESTS050
				TESTS060
TRANSFER VECTOR				
00000	633163606060	TIT		
00001	632562636234	TESTS)		
LINKAGE DIRECTOR				
00002	000000000000			TESTS070
00003	632562636260			TESTS080
00004	0760 00 0 00161	TESTS	SWT 1	TESTS090
00005	-0625 60 0 00000	STL*	\$TIT	TESTS100
00006	0772 00 0 01206	REWA	6	TESTS110
00007	0021 60 0 00001	TTR*	\$TESTS)	TESTS120
		END		

TEST SWITCH ONE FOR INTERVAL TIMER USE.  
SWITCH ONE UP, USE CORE CLOCK.  
REWIND UPDATE INPUT TAPE.  
THEN GO DIRECTLY TO TESTS).

POST PROCESSOR ASSEMBLY DATA

10 IS THE FIRST LOCATION NOT USED BY THIS PROGRAM

REFERENCES TO DEFINED SYMBOLS  
0 TIT 5  
4 TESTS  
1 TESTS) 7

NO ERROR IN ABOVE ASSEMBLY.  
\*TIME SPENT IN FAP.. 000002 IN HUNDREDTHS OF MINUTES.

## TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.

	PCC COUNT LBL	TESTS) TESTS)	BINARY CARD LABEL.	
00007	ENTRY	TESTS)	PRIMARY NAME OF MONITOR.	TTJ00010
00702	ENTRY	BACK	RETURN POINT IN CASE OF ERROR.	TTJ00020
00235	ENTRY	TIT	TEST LOCATION TO USE INTERVAL TIMER.	TTJ00030
00663	ENTRY	LSTM	LEAVE-SELECT-TRAPPING MODE.	TTJ00050
01145	ENTRY	SX4	ENTRY TO SAVE IR4 FOR POST MORTEM.	TTJ00060
01146	ENTRY	SVCON	ENTRY TO SAVE CONSOLE FOR POST MORTEM.	TTJ00070
02407	ENTRY	WOT	WRITE-OUTPUT-TAPE, A3.	TTJ00080
02520	ENTRY	NPRINT	ON LINE PRINT UNDER CARRIAGE CONTROL.	TTJ00090
01026	ENTRY	EPMR	ENTRY TO MARK ERROR POST MORTEM.	TTJ00100
01260	ENTRY	OCT)	FULL WORD OCTAL-BCI CONVERTER.	TTJ00110
01173	ENTRY	OCTADR	OCTAL ADDRESS TO BCI CONVERTER.	TTJ00120
01233	ENTRY	COMADR	COMPLEMENT ADDRESS TO BCI CONVERTER.	TTJ00130
01207	ENTRY	TABBLK	TABLE FOR DELETION OF BLANKS WITH CRQ.	TTJ00140
01301	ENTRY	BCDTAB	ENTRY TO REMOVE ILLEGAL BCI CHARACTERS.	TTJ00150

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
SECTION 1, SETUP LOWER CORE AND PRINT STORAGE MAP.

	TTL	SECTION 1, SETUP LOWER CORE AND PRINT STORAGE MAP.	TT)10000
TRANSFER VECTOR			
00000	444665312534	MOVIE)	
00001	513147606060	RIP	
00002	232147606060	CAP	
00003	474751462760	PPROG	
00004	472363016060	PCT1	
LINKAGE DIRECTOR			
00005	000000000000		
00006	632562636234		
00007	-0760 00 0 00007	TESTS) LTM	
00010	-0760 00 0 00002	EFTM	JUST IN CASE.
00011	-0760 00 0 00010	LSNM	..
00012	0600 00 0 00005	STZ	..
00013	0760 00 0 00012	DCT	RESET INTERVAL TIMER.
00014	0761 00 0 00000	NOP	TURN OFF DCT LIGHT.
00015	0140 00 0 00016	TOV	..
00016	0441 00 0 03125	LDI	TURN OFF OVERFLOW LIGHT.
00017	0760 00 0 00140	SLF	CLEAR INDICATORS.
00020	0774 00 4 00144	AXT	TURN OFF SENSE LIGHTS.
00021	0600 00 4 00144	STZ	WIPE OUT LOWER CORE.
00022	0600 00 4 00145	STZ	..
00023	2 00002 4 00021	TIK	..
00024	-0500 00 0 00026	CAL	SET THE INITIAL TRAP WITH AN ENABLE.
00025	0602 00 0 00015	SLW	..
00026	0564 00 0 03127	ENB	THIS MAY TRAP.
00027	-0500 00 0 00167	CAL	SETUP LOWER CORE, ETM RETURN.
00030	0602 00 0 00001	SLW	..
00031	-0500 00 0 00170	CAL	STR RETURN.
00032	0602 00 0 00002	SLW	..
00033	-0500 00 0 00171	CAL	SET INTERVAL TIMER RETURN.
00034	0602 00 0 00007	SLW	..
00035	-0500 00 0 00172	CAL	FPT RETURN.
00036	0602 00 0 00010	SLW	..
00037	-0500 00 0 00173	CAL	CHANNEL B TRAP RETURN.
00040	0602 00 0 00015	SLW	..
00041	-0500 00 0 00174	CAL	SELECT TRAP RETURN.
00042	0602 00 0 40001	SLW	=/4C001.
00043	0602 00 0 40002	SLW	=/40002.
00044	0764 00 0 01203	BSRA	REMOVE MONITOR COMMENT OF EXECUTION.
00045	0060 00 0 00045	TCOA	WAIT FOR DSC A.
00046	0760 00 0 00005	IOT	TURN OFF I/O CHECK LIGHT.
00047	0761 00 0 00000	NOP	..
00050	-0760 00 0 01000	ETTA	TURN OFF EOT LIGHT.
00051	0761 00 0 00000	NOP	..
SPACE			
		2	TT)10360
		PRINT STORAGE MAP UP TO TESTS.	TT)10370
00052	-0500 60 0 00000	MAP	GET CONTROL WORD OF MOVIE).
00053	0771 00 0 00022	CAL*	TT)10380
		ARS	CALCULATE LAST ADDRESS + 1.
		18	TT)10390
			TT)10400

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
SECTION 1, SETUP LOWER CORE AND PRINT STORAGE MAP.

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
 SECTION 1, SETUP LOWER CORE AND PRINT STORAGE MAP.

00142	462751214460				
00143	626346512127				
00144	256044214760				
00145	264643434666				
00146	623360606060				
00147	006060606060	XMAP02 BCI	4,0	NAME ORIGIN ENTRY	TT)10960
00150	452144256060				
00151	465131273145				
00152	602545635170				
00153	006060606060	XMAP03 BCI	4,0		TT)10970
00154	606060606060				
00155	606060606060				
00156	606060606060				
00157	006270442246	XMAP04 BCI	4,0	SYMBOL TABLE EXCEEDED.	TT)10980
00160	436063212243				
00161	256025672325				
00162	252425243360				
00163	002545246046	XMAP05 BCI	4,0	END OF STORAGE MAP.	TT)10990
00164	266062634651				
00165	212725604421				
00166	473360606060				
00167	0021 00 0 00262	C(1) TTR	TRAPR	ETM TRAP RETURN.	TT)11000
00170	0021 00 0 00314	C(2) TTR	STRR	STR RETURN.	TT)11010
00171	0021 00 0 00524	C(7) TTR	TIMR	INTERVAL TIMER RETURN.	TT)11020
00172	0021 00 0 00404	C(8) TTR	FPTR	FPT RETURN.	TT)11030
00173	0021 00 0 00533	C(13) TTR	SLR	STOP-LOOP RETURN.	TT)11040
00174	0021 00 0 00627	C(ST) TTR	IOTMR	SELECT TRAP RETURN.	TT)11050
					TT)11060
					TT)11070
02223	T	TAPENO	B3B	TAPE FOR TIMER.	

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
SECTION 2, SET TRAPS, TIME AND EXIT TO CAP.

TTL SECTION 2, SET TRAPS, TIME AND EXIT TO CAP.						
00175	0074 00 4 02407	EVAL	TSX	WOT,4	EXECUTION COMMENT.	TT120000
00176	0 00007 0 00241		PZE	TCAP,0,7	..	TT120010
00177	0074 00 4 02407		TSX	WOT,4	BLANK LINE.	TT120020
00200	0 00001 0 03160		PZE	=H ,0,1	..	TT120030
00201	0074 00 4 00001		TSX	\$RIP,4	GO SET UP READ PROGRAMS.	TT120040
00202	0520 00 0 00235		ZET	TIT	TEST FOR INTERVAL TIMER.	TT120050
00203	0020 00 0 00207		TRA	ITIM	GO TO INTERVAL TIMER.	TT120060
00204	0766 00 0 02223		WTBT		TAPE TIMER, SELECT TIMER TAPE.	TT120070
00205	-0540 00 0 00237		RCHT	TIME	LOAD WITH TIME.	TT120080
00206	0020 00 0 00213		TRA	ESTM	GO TO SET TRAP.	TT120090
00207	-0500 00 0 03136	ITIM	CAL	=300	SET INTERVAL TIMER FOR FIVE SECONDS.	TT120100
00210	0760 00 0 00006		COM		..	TT120110
00211	0601 00 0 00005		STO	5	INSERT IN TRAP LOCATION.	TT120120
00212	0600 00 0 00006		STZ	6	CLEAR LOCATION RETURN.	TT120130
00213	-0760 00 0 00005	ESTM	ESTM		SET TRAP.	TT120140
00214	-0500 00 0 00234		CAL	ORG	SET ORIGIN.	TT120150
00215	0074 00 4 00002		TSX	\$CAP,4	GO TO CAP.	TT120160
00216	0621 00 0 00236		STA	EXEC	SAVE ENTRY POINT.	TT120170
00217	-0760 00 0 00007		LTM		JUST IN CASE.	TT120180
00220	0634 00 4 01166		SXA	IR4,4	SAVE IR4.	TT120190
00221	0074 00 4 01146		TSX	SVCON,4	SAVE CONSOLE.	TT120200
00222	0560 00 0 00236		LDQ	EXEC	CONVERT ENTRY TO OCTAL-BCI.	TT120210
00223	0074 00 4 01173		TSX	OCTADR,4	..	TT120220
00224	-0754 00 0 00000		PXD	0,0	SHIFT AND OR TO COMMENT.	TT120230
00225	-0763 00 0 00036		LGL	30	..	TT120240
00226	-0602 00 0 00257		ORS	WEP+7	..	TT120250
00227	-0130 00 0 00000		XCL		..	TT120260
00230	-0602 00 0 00260		ORS	WEP+8	..	TT120270
00231	0074 00 4 02407		TSX	WOT,4	COMMENT, ENTRY POINT.	TT120280
00232	0 00011 0 00250		PZE	WEP,0,9	..	TT120290
00233	0020 00 0 00702		TRA	BACK	NO PROVISION FOR EXECUTION FOR NOW.	TT120300
00234	+000000050000	ORG	OCT	50000	CAP PROGRAM ORIGIN.	TT120310
00235	0 00000 0 00000	TIT	PZE		LOCATION TO TEST FOR INTERVAL TIMER.	TT120320
00236	0 00000 0 00000	EXEC	PZE		DUMMY TRA TO ASSEMBLED PROGRAM.	TT120330
00237	-0 60650 0 17130	TIME	IDCP	-25000,0,25000	TIMED FOR ABOUT 5 SECONDS.	TT120340
00240	-1 60650 0 17130		IOCT	-25000,0,25000	..	TT120350
00241	016060606060	TCAP	BCI	7,1	TEST OF CAP, BEGIN ASSEMBLY.	TT120360
00242	606060606060					TT120370
00243	632562636046					TT120380
00244	266023214773					TT120390
00245	602225273145					
00246	602162622544					
00247	224370336060					
00250	006060606060	WEP	BCI	9,0	RETURN FROM CAP, ENTRY POINT IS 00000.	TT120400
00251	606060606060					
00252	512563645145					
00253	602651464460					
00254	232147736025					
00255	456351706047					
00256	463145636031					
00257	626000000000					
00260	003360606060					

TESTS FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
SECTION 3, TRAP RETURNS AND LSTM.

		TTL	SECTION 3, TRAP RETURNS AND LSTM.			
00261	0 00000 0 00000	QUIT	IOCD	0,0,0	COMMAND TO DISCONNECT CHANNEL.	TT)30000 TT)30010 TT)30020
		SPACE	2	TRAPPING MODE RETURN.		TT)30030 TT)30040 TT)30050
00262	-0760 00 0 00007	TRAPR	LTM		RETURN FROM TRANSFER TRAP.	TT)30060
00263	0634 00 4 01166	SXA	IR4,4		SAVE IR4.	TT)30070
00264	0074 00 4 01146	TSX	SVCON,4		SAVE CONSOLE.	TT)30080
00265	-0520 00 0 00000	NZT	0		IF LOCATION 0 NOT SET,	TT)30090
00266	0020 00 0 00361	TRA	SEQR		MUST BE A WILD TRANSFER.	TT)30100
00267	0560 00 0 00000	LDQ	0		GET ADDRESS OF TRANSFER INSTRUCTION.	TT)30110
00270	0074 00 4 01173	TSX	OCTADR,4		CONVERT TO OCTAL-BCD.	TT)30120
00271	-0754 00 0 00000	PXD	0,0		..	TT)30130
00272	-0763 00 0 00022	LGL	18		SHIFT AND OR TO COMMENT.	TT)30140
00273	-0602 00 0 00307	ORS	XTRAP+5		..	TT)30150
00274	-0130 00 0 00000	XCL			..	TT)30160
00275	-0602 00 0 00310	ORS	XTRAP+6		..	TT)30170
00276	0074 00 4 02407	TSX	WOT,4		COMMENT.	TT)30180
00277	0 00012 1 00302	PZE	XTRAP,1,10		..	TT)30190
00300	-0625 00 0 01026	STL	EPMR		SET TO GIVE ERROR POST MORTEM.	TT)30200
00301	0020 00 0 00702	TRA	BACK		EXIT TO POST MORTEM SECTION.	TT)30210
						TT)30220
00302	006351214562	XTRAP	BC I	9,0	TRANSFER INSTRUCTION IN LOCATION 00000 HAS BEEN TRAPP	TT)30230
00303	262551603145					
00304	626351642363					
00305	314645603145					
00306	604346232163					
00307	314645600000					
00310	000000603021					
00311	626022252545					
00312	606351214747					
00313	252433606060		BC I	1,ED.		TT)30240
		SPACE	2	STR RETURN.		TT)30250 TT)30260 TT)30270
00314	-0760 00 0 00007	STRR	LTM		RETURN FOR TRAPPED STR.	TT)30280
00315	0634 00 4 01166	SXA	IR4,4		SAVE IR4.	TT)30290
00316	0074 00 4 01146	TSX	SVCON,4		SAVE CONSOLE.	TT)30300
00317	-0520 00 0 00000	NZT	0		IF LOCATION 0 NOT SET,	TT)30310
00320	0020 00 0 00361	TRA	SEQR		MUST BE A WILD TRANSFER.	TT)30320
00321	0534 00 4 00000	LXA	0,4		GET A(STR)+1.	TT)30330
00322	1 77777 4 00323	TXI	*+1,4,-1		DECREMENT IT.	TT)30340
00323	0634 00 4 00324	SXA	*+1,4		..	TT)30350
00324	0560 00 0 00000	LDQ	0		CHECK FOR PROGRAMMED STR.	TT)30360
00325	-0754 00 0 00000	PXD	0,C		..	TT)30370
00326	-0763 00 0 00003	LGL	3		..	TT)30380
00327	0402 00 0 03131	SUB	=5		..	TT)30390
00330	0100 00 0 00334	TZE	*+4		YES.	TT)30400
00331	-0500 00 0 00000	CAL	0		IF NOT, STOP OR LOOP.	TT)30410
00332	0621 00 0 00610	STA	SADR			TT)30420

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
 SECTION 3, TRAP RETURNS AND LSTM.

00333	0020 00 0 00541	TRA	SLR1	..	TTI30430	
00334	0754 00 4 00000	PXA	0,4	PROGRAMMED STR.	TTI30440	
00335	-0130 00 0 00000	XCL		..	TTI30450	
00336	0074 00 4 01173	TSX	OCTADR,4	CONVERT TO OCTAL-BCD.	TTI30460	
00337	-0754 00 0 00000	PXD	0,0	..	TTI30470	
00340	-0763 00 0 00014	LGL	12	SHIFT AND OR TO COMMENT.	TTI30480	
00341	-0602 00 0 00354	ORS	XSTR+4	..	TTI30490	
00342	-0130 00 0 00000	XCL		..	TTI30500	
00343	-0602 00 0 00355	ORS	XSTR+5	..	TTI30510	
00344	0074 00 4 02407	TSX	WOT,4	COMMENT.	TTI30520	
00345	0 00011 1 00350	PZE	XSTR,1,9	..	TTI30530	
00346	-0625 00 0 01026	STL	EPMR	SET TO GIVE ERROR POST MORTEM.	TTI30540	
00347	0020 00 0 00702	TRA	BACK	EXIT TO POST MORTEM SECTION.	TTI30550	
00350	006263516031	XSTR	BCI	9,0STR INSTRUCTION IN LOCATION 00000 HAS BEEN TRAPPED.	TTI30560	
00351	456263516423				TTI30570	
00352	633146456031				TTI30580	
00353	456043462321					
00354	633146456000					
00355	000000006030					
00356	216260222525					
00357	456063512147					
00360	472524336060					
		SPACE	2		TTI30590	
			ENTRY FOR SEQUENCING ERROR.		TTI30600	
00361	0074 00 4 02407	SEQR	TSX	WOT,4	COMMENT FOR BAD CALLING SEQUENCE.	TTI30610
00362	0 00017 1 00365		PZE	XSEQR,1,15	..	TTI30620
00363	-0625 00 0 01026		STL	EPMR	SET TO GIVE ERROR POST MORTEM.	TTI30630
00364	0020 00 0 00702		TRA	BACK	EXIT TO POST MORTEM SECTION.	TTI30640
00365	006351214562	XSEQR	BCI	9,0TRANSFER TO LOWER CORE. PROBABLY IR4 NOT RESET, OR TA	TTI30650	
00366	262551606346				TTI30660	
00367	604346662551					
00370	602346512533					
00371	604751462221					
00372	224370603151					
00373	046045466360					
00374	512562256373					
00375	604651606321					
00376	276044316262	BCI		6,G MISSING FROM TRANSFER INSTRUCTION.	TTI30670	
00377	314527602651					
00400	464460635121					
00401	456226255160					
00402	314562635164					
00403	236331464533					
		SPACE	2		TTI30680	
			FLOATING POINT TRAP RETURN.		TTI30690	
00404	-0520 00 0 00000	FPTR	NZT	0 IF LOCATION 0 NOT SET,	TTI30700	
					TTI30710	
					TTI30720	

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
SECTION 3, TRAP RETURNS AND LSTM.

00405	0021 00 0 00425		TTR	TR8	MUST BE A WILD TRANSFER.	TTJ30730
00406	0604 00 0 00473		STI	SSI	SAVE THE INDICATORS.	TTJ30740
00407	0441 00 0 00000		LDI	0	GET SPILL CODE.	TTJ30750
00410	-0054 00 0 00004		LFT	4	CHECK FOR OVERFLOW.	TTJ30760
00411	0021 00 0 00431		TTR	FPER	OVERFLOW, EXIT.	TTJ30770
00412	-0054 00 0 00002		LFT	2	AC UNDERFLOW.	TTJ30780
00413	0500 00 0 03125		CLA	=0	YES, RESET AC.	TTJ30790
00414	-0054 00 0 00001		LFT	1	MQ UNDERFLOW.	TTJ30800
00415	0560 00 0 03125		LDQ	=0	YES, RESET MQ.	TTJ30810
00416	0441 00 0 00473		LDI	SSI	RESTORE ORIGINAL INDICATORS.	TTJ30820
00417	0634 00 4 00422		SXA	*+3,4	SAVE IR4.	TTJ30830
00420	0534 00 4 00000		LXA	0,4	PICKUP 0.	TTJ30840
00421	0634 00 4 00424		SXA	*+3,4	INSERT RETURN ADDRESS.	TTJ30850
00422	0774 00 4 00000		AXT	**,4	RESTORE IR4.	TTJ30860
00423	0600 00 0 00000		STZ	0	CLEAR LOCATION 0.	TTJ30870
00424	0021 00 0 00000		TTR	**	RETURN TO CALLER.	TTJ30880
00425	-0760 00 0 00007	TR8	LTM		JUST IN CASE.	TTJ30890
00426	0634 00 4 01166		SXA	IR4,4	SAVE IR4 FOR POST MORTEM.	TTJ30900
00427	0074 00 4 01146		TSX	SVCON,4	GO SAVE CONSOLE AND RESET TRAPS.	TTJ30910
00430	0020 00 0 00361		TRA	SEQR	GO TO SEQR ROUTINE.	TTJ30920
00431	-0760 00 0 00007	FPER	LTM		JUST IN CASE.	TTJ30930
00432	0634 00 4 01166		SXA	IR4,4	SAVE IR4.	TTJ30940
00433	0441 00 0 00473		LDI	SSI	RESTORE INDICATORS.	TTJ30950
00434	0074 00 4 01146		TSX	SVCON,4	SAVE CONSOLE.	TTJ30960
00435	0441 00 0 00000		LDI	0	GET SPILL CODE AND ADDRESS OF INSTRUCTION.	TTJ30970
00436	-0056 00 0 00010		LNT	10	DIVISION ERROR.	TTJ30980
00437	0020 00 0 00443		TRA	**4	NO, SKIP.	TTJ31000
00440	0074 00 4 02407		TSX	WOT,4	YES, COMMENT.	TTJ31010
00441	0 00003 1 00474		PZE	WDVER,1,3	..	TTJ31020
00442	0020 00 0 00453		TRA	SPER	EXIT.	TTJ31030
00443	-0056 00 0 00002		LNT	2	ACCUMULATOR OVERFLOW.	TTJ31040
00444	0020 00 0 00447		TRA	**3	NO, SKIP.	TTJ31050
00445	0074 00 4 02407		TSX	WOT,4	YES, COMMENT.	TTJ31060
00446	0 00004 1 00477		PZE	WACO,1,4	..	TTJ31070
00447	-0056 00 0 00001		LNT	1	MQ OVERFLOW.	TTJ31080
00450	0020 00 0 00453		TRA	SPER	NO, EXIT.	TTJ31090
00451	0074 00 4 02407		TSX	WOT,4	YES, COMMENT.	TTJ31100
00452	0 00005 1 00503		PZE	WMQO,1,5	..	TTJ31110
00453	-0500 00 0 00000	SPER	CAL	0	GET SPILL CODE.	TTJ31120
00454	-0320 00 0 03141		ANA	=0C00017000000	MASK OUT JUNK.	TTJ31130
00455	-0765 00 0 00025		LGR	21	CONVERT TO OCTAL.	TTJ31140
00456	0767 00 0 00003		ALS	3	SHIFT AND OR TO COMMENT.	TTJ31150
00457	-0763 00 0 00003		LGL	3	..	TTJ31160
00460	-0602 00 0 00522		ORS	XFPT+10	..	TTJ31170
00461	-0500 00 0 00000		CAL	0	GET ADDRESS OF TRAPPED INSTRUCTION.	TTJ31180
00462	0402 00 0 03126		SUB	=1	..	TTJ31190
00463	-0130 00 0 00000		XCL		..	TTJ31200
00464	0074 00 4 01173		TSX	OCTADR,4	CONVERT TO OCTAL-BCD.	TTJ31210
00465	-0130 00 0 00000		XCL		OR TO COMMENT.	TTJ31220
00466	-0602 00 0 00517		ORS	XFPT+7	..	TTJ31230
00467	0074 00 4 02407		TSX	WOT,4	COMMENT.	TTJ31240
00470	0 00014 1 00510		PZE	XFPT,1,12	..	TTJ31250
00471	-0625 00 0 01026		STL	EPMR	SET TO GIVE ERROR POST MORTEM.	TTJ31260
						TTJ31270

TESTS FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
SECTION 3, TRAP RETURNS AND LSTM.

00472	0020 00 0 00702		TRA	BACK	EXIT TO POST MORTEM SECTION.	TT)31280
00473	0 00000 0 00000	SSI	PZE		TEMPORARY STORAGE FOR SI.	TT)31290
00474	002431653162	WDVER	BCI		3,0DIVISION ERROR.	TT)31300
00475	314645602551					TT)31310
C0476	514651336060					
00477	002123236444		WACO	BCI	4,0ACCUMULATOR OVERFLOW.	TT)31320
00500	644321634651					
00501	604665255126					
00502	434666336060					
00503	004464436331	WMQD	BCI		5,0MULTIPLIER-QUOTIENT OVERFLOW.	TT)31330
00504	474331255140					
00505	506446633125					
00506	456360466525					
00507	512643466633					
00510	002643462163	XFPT	BCI		9,0FLOATING POINT SPILL OCCURRED IN LOCATION 00000, SPIL TT)31340	
00511	314527604746					
00512	314563606247					
00513	314343604623					
00514	236451512524					
00515	603145604346					
00516	232163314645					
00517	600000000000					
00520	736062473143					
00521	436023462425		BCI		3,L CODE IS 00.	TT)31350
00522	603162600000					
00523	336060606060					

		SPACE	2		TT)31360	
			INTERVAL TIMER RETURN.		TT)31370	
					TT)31380	
00524	-0760 00 0 00007	TIMR	LTM		JUST IN CASE.	TT)31390
00525	0634 00 4 01166	SXA	IR4,4		SAVE IR4 FOR POST MORTEM.	TT)31400
00526	0074 00 4 01146	TSX	SVCON,4		SAVE CONSOLE AND RESET TRAPS.	TT)31410
00527	-0500 00 0 00006	CAL	6		PICKUP TRAP LOCATION.	TT)31420
00530	0100 00 0 00361	TZE	SEQR		IF ZERO, MUST BE WILD TRANSFER.	TT)31430
00531	0621 00 0 00610	STA	SADR			TT)31440
00532	0020 00 0 00541	TRA	SLR1		GO TO ANALYZE.	TT)31450

		SPACE	2		TT)31460	
			TAPE TIMER RETURN.		TT)31470	
					TT)31480	
00533	-0760 00 0 00007	SLR	LTM		STOP-LOOP TRAPPED RETURN.	TT)31490
00534	0634 00 4 01166	SXA	IR4,4		SAVE IR4.	TT)31500
00535	0074 00 4 01146	TSX	SVCON,4		SAVE CONSOLE.	TT)31510
00536	-0500 00 0 00014	CAL	12			TT)31520
00537	0100 00 0 00361	TZE	SEQR			TT)31530
00540	0621 00 0 00610	STA	SADR			TT)31540
00541	-0500 60 0 00610	SLR1	CAL*		SADR	TT)31550
00542	-0320 00 0 03152	ANA	=0377700000000		MASK IT.	TT)31560
00543	0100 00 0 00571	TZE	PSTOP		IF HTR OR FOR, CALL IT A STOP.	TT)31570
00544	-0500 00 0 00610	CAL	SADR			TT)31580
00545	0402 00 0 03126	SUB	=1		REDUCE C(ILC) BY 1.	TT)31590

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
SECTION 3, TRAP RETURNS AND LSTHM.

00546	0621 00 0 00610		STA	SADR	..		TTJ31600
00547	-0500 60 0 00610		CAL*	SADR	GET TRAPPED INSTRUCTION.		TTJ31610
00550	-0320 00 0 03165		ANA	=07777000000000	MASK IT.		TTJ31620
00551	0774 00 4 00004		AXT	4,4	COMPARE WITH TRUE STOPS.		TTJ31630
00552	-0340 00 4 00610		LAS	PSTOP+4,4	..		TTJ31640
00553	0020 00 0 00555		TRA	*+2	NO.		TTJ31650
00554	0020 00 0 00571		TRA	PSTOP	TRUE STOP.		TTJ31660
00555	2 00001 4 00552		TIX	*-3,4,1	NO, INDEX.		TTJ31670
00556	0560 00 0 00610	LOOP	LDQ	SADR			TTJ31680
00557	0074 00 4 01173		TSX	OCTADR,4	CONVERT TO OCTAL BCD.		TTJ31690
00560	-0754 00 0 00000		PXD	0,0	..		TTJ31700
00561	-0763 00 0 00030		LGL	24	SHIFT AND OR TO COMMENT.		TTJ31710
00562	-0602 00 0 00617		ORS	XLCOP+6	..		TTJ31720
00563	-0130 00 0 00000		XCL		..		TTJ31730
00564	-0602 00 0 00620		ORS	XLCOP+7	..		TTJ31740
00565	0074 00 4 02407		TSX	WOT,4	COMMENT.		TTJ31750
00566	0 00010 1 00611		PZE	XLOOP,1,8	..		TTJ31760
00567	-0625 00 0 01026		STL	EPMR	SET TO GIVE ERROR POST MORTEM.		TTJ31770
00570	0020 00 0 00702		TRA	BACK	EXIT TO POST MORTEM SECTION.		TTJ31780
00571	0560 00 0 00610	PSTOP	LDQ	SADR	TRUE STOP, GET ADDRESS OF TRAPPED		TTJ31800
00572	0074 00 4 01173		TSX	OCTADR,4	INSTRUCTION AND CONVERT TO OCTAL-BCD.		TTJ31810
00573	-0754 00 0 00000		PXD	0,0	..		TTJ31820
00574	-0763 00 0 00036		LGL	30	SHIFT AND OR TO COMMENT.		TTJ31830
00575	-0602 00 0 00625		ORS	XPSTOP+4	..		TTJ31840
00576	-0130 00 0 00000		XCL		..		TTJ31850
00577	-0602 00 0 00626		ORS	XPSTOP+5	..		TTJ31860
00600	0074 00 4 02407		TSX	WOT,4	COMMENT.		TTJ31870
00601	0 00006 1 00621		PZE	XPSTOP,1,6	..		TTJ31880
00602	-0625 00 0 01026		STL	EPMR	SET TO GIVE ERROR POST MORTEM.		TTJ31890
00603	0020 00 0 00702		TRA	BACK	EXIT TO POST MORTEM SECTION.		TTJ31900
00604	0220 00 0 00000	PSTOP	DVH	-	LIST OF STOPS.		TTJ31920
00605	0224 00 0 00000		VDH	-,-	..		TTJ31930
00606	0240 00 0 00000		FDH	-	..		TTJ31940
00607	0420 00 0 00000		HPR		..		TTJ31950
00610	0 00000 0 00000	SADR	PZE		..		TTJ31960
00611	004751462221	XLOOP	BCI		ADDRESS OF STOP.		TTJ31970
00612	224325602545				8,0PROBABLE ENDLESS LCOP AROUND LOCATION 00000.		TTJ31980
00613	244325626260						
00614	434646476021						
00615	514664452460						
00616	434623216331						
00617	464560000000						
00620	000033606060						
00621	004751462751	XPSTOP	BCI		6,0PROGRAM STOP AT LOCATION 00000.		TTJ31990
00622	214460626346						
00623	476021636043						
00624	462321633146						
00625	456000000000						
00626	003360606060						

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
SECTION 3, TRAP RETURNS AND LSTM.

		SPACE	2	SELECT OR COPY TRAP RETURN.	
00627	-0760 00 0 00007	IOTMR	LTM	JUST IN CASE.	TTI32000
00630	0634 00 4 01166	SXA	IR4,4	SAVE IR4.	TTI32010
00631	0074 00 4 01146	TSX	SVCON,4	SAVE THE CONSOLE.	TTI32020
00632	-0760 00 0 00010	LSNM		JUST IN CASE.	TTI32030
00633	0534 00 4 40000	LXA	16384,4	GET (ADDRESS+1) OF TRAPPED INSTRUCTION.	TTI32040
00634	1 77777 4 00635	TXI	*+1,4,-1	SET TO ADDRESS OF TRAPPED INSTRUCTION.	TTI32050
00635	0754 00 4 00000	PXA	0,4	TO AC.	TTI32060
00636	-0130 00 0 00000	XCL		TO MQ.	TTI32070
00637	0074 00 4 01173	TSX	OCTADR,4	CONVERT TO OCTAL-BCD.	TTI32080
00638				INSERT IN COMMENT.	TTI32090
00639	-0754 00 0 00000	ZAC			TTI32100
00640	-0763 00 0 00022	LGL	18	..	TTI32110
00641	-0602 00 0 00661	DRS	XIOBD+8	..	TTI32120
00642	-0602 00 0 00661	XCL		..	TTI32130
00643	-0130 00 0 00000	DRS	XICBD+9	..	TTI32140
00644	-0602 00 0 00662	TSX	WOT,4	COMMENT.	TTI32150
00645	0074 00 4 02407	XIOBD,1,10		..	TTI32160
00646	0 00012 1 00651	PZE	EPMR	SET TO GIVE ERROR POST MORTEM.	TTI32170
00647	-0625 00 0 01026	STL		SET TO GIVE ERROR POST MORTEM.	TTI32180
00650	0020 00 0 00702	TRA	BACK	EXIT TO POST MORTEM SECTION.	TTI32190
					TTI32200
					TTI32210
					TTI32220
00651	002163632544	XIOBD	BCI	9,0 ATTEMPT TO USE ILLEGAL I/O INSTRUCTION IN LOCATION 00	TTI32220
00652	476360634660				
00653	646225603143				
00654	432527214360				
00655	316146603145				
00656	626351642363				
00657	314645603145				
00660	604346232163				
00661	314645600000				
00662	000000336060		BCI	1,000.	TTI32230
		SPACE	2	ROUTINE TO LEAVE SELECT TRAPPING MODE.	
00663	-0600 00 0 00677	LSTM	STQ	SAVE MQ.	TTI32240
00664	-0760 00 0 00010	LSNM		JUST IN CASE.	TTI32250
00665	0560 00 0 40001	LDQ	16385	SAVE TRAP RETURN.	TTI32260
00666	-0600 00 0 00700	STQ	SLSTM+1	..	TTI32270
00667	0560 00 0 00701	LDQ	TLSTM	SET TRAP.	TTI32280
00670	-0600 00 0 40001	STQ	16385	..	TTI32290
00671	0766 00 0 01204	WTDA	4	SELECT INSTRUCTION.	TTI32300
00672	0540 00 0 00261	RCHA	QUIT	NIL COMMAND.	TTI32310
00673	0560 00 0 00700	RLSTM	LDQ	RESTORE ORIGINAL TRAP.	TTI32320
00674	-0600 00 0 40001	STQ	SLSTM+1	..	TTI32330
00675	0560 00 0 00677	LDQ	16385	RESTORE ORIGINAL MQ.	TTI32340
00676	0020 00 4 00001	TRA	SLSTM	RETURN.	TTI32350
					TTI32360
00677	0 00000 0 00000	SLSTM	PZE	MQ STORAGE.	TTI32370
00700	0 00000 0 00000	PZE		TRAP RETURN STORAGE.	TTI32380
00701	0021 00 0 00673	TLSTM	TTR	SELECT TRAP RETURN.	TTI32390
					TTI32400
					TTI32410
					TTI32420

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
SECTION 4, WIND UP THIS RUN.

		TTL	SECTION 4, WIND UP THIS RUN.			
00702	-0760 00 0 00007	BACK	LTM	TTI40000		
00703	0600 00 0 00005	STZ	5	TTI40010		
00704	-0061 00 0 00706	TCNT	*+2	TTI40020		
00705	-0540 00 0 00261	RCHT	QUIT	TTI40030		
00706	0074 00 4 00663	TSX	LSTM,4	TTI40040		
00707	-0520 00 0 00235	NZT	TIT	TTI40050		
00710	0772 00 0 02223	REWT		TTI40060		
00711	0520 00 0 01026	ZET	EPMR	TTI40070		
00712	0020 00 0 01401	TRA	PMR	TTI40080		
00713	0020 00 0 01403	TRA	PMR+2	TTI40090		
			YES, EXIT.	TTI40100		
			POST MORTEM IN ANY CASE.	TTI40110		
			SECTION TO GIVE FINAL EXIT TO MONITOR.	TTI40120		
				TTI40130		
				TTI40140		
00714	0074 00 4 02407	FINIS	TSX	WOT,4	END OF RUN COMMENT.	TTI40150
00715	0 00002 1 01027	PZE	ENCRN,1,2	..	..	TTI40160
00716	0760 00 0 00004	ENK		CHECK CONSOLE KEYS.	..	TTI40170
00717	-0130 00 0 00000	XCL		..	..	TTI40180
00720	0044 00 0 00000	PAI		..	..	TTI40190
00721	-0056 00 0 040000	LNT	040000	IF KEY 3 IS UP,	..	TTI40200
00722	0020 00 0 00765	TRA	DOOR	DONT CHECK KEYS AT ALL.	..	TTI40210
00723	0056 00 0 00002	STOP	RNT	2	CHECK FOR STOP INSTRUCTION.	TTI40220
00724	0020 00 0 00732	TRA	FILE	NO, CHECK FOR REQUEST FOR EOF ON A3.	..	TTI40230
00725	0074 00 4 02520	TSX	PRINT,4	YES, COMMENT.	..	TTI40240
00726	-0 00014 0 01031	MZE	XSTOP,0,12	..	..	TTI40250
00727	0760 00 0 00004	ENK		GET THE KEYS.	..	TTI40260
00730	-0130 00 0 00000	XCL		PLACE IN AC,	..	TTI40270
00731	0044 00 0 00000	PAI		PLACE IN SI.	..	TTI40280
00732	0056 00 0 00004	FILE	RNT	4	CHECK FOR EOF ON A3 REQUEST.	TTI40290
00733	0020 00 0 00742	TRA	CLOSE	NO, CHECK FOR CLOSE TAPE INSTRUCTION.	..	TTI40300
00734	0770 00 0 01203	WEFA	3	YES, WRITE EOF ON A3.	..	TTI40310
00735	0074 00 4 02520	TSX	PRINT,4	COMMENT.	..	TTI40320
00736	-0 00014 0 01045	MZE	XFILE,0,12	..	..	TTI40330
00737	0760 00 0 00004	ENK		GET THE KEYS.	..	TTI40340
00740	-0130 00 0 00000	XCL		PLACE IN AC,	..	TTI40350
00741	0044 00 0 00000	PAI		PLACE IN SI.	..	TTI40360
00742	0056 00 0 00001	CLOSE	RNT	1	CHECK FOR CLOSE OUTPUT TAPE INSTRUCTION.	TTI40370
00743	0020 00 0 00765	TRA	DOOR	NO, GO TO DOOR.	..	TTI40380
00744	0774 00 1 00012	AXT	10,1	SET TO COMMENT 10 TIMES.	..	TTI40390
00745	0074 00 4 02407	TSX	WOT,4	YES, WRITE (END OF TAPE.) AND	..	TTI40400
00746	0 00003 0 01077	PZE	ENCTP,0,3	..	..	TTI40410
00747	0074 00 4 02407	TSX	WOT,4	SKIP TO CHANNEL FOUR.	..	TTI40420
00750	0 00001 0 03147	PZE	=H4 ,0,1	..	..	TTI40430
00751	0770 00 0 01203	WEFA	3	THEN AN EOF MARK.	..	TTI40440
00752	2 00001 1 00745	TIX	*-5,1,1	..	..	TTI40450
00753	0074 00 4 02407	TSX	WOT,4	COMMENT, ITS REALLY THE END.	..	TTI40460
00754	0 00011 0 01102	PZE	RENDTP,0,9	..	..	TTI40470
00755	0074 00 4 02407	TSX	WOT,4	SKIP TO CHANNEL FOUR.	..	TTI40480
00756	0 00001 0 03147	PZE	=H4 ,0,1	..	..	TTI40490
00757	0774 00 4 00012	AXT	10,4	TEN EOF'S ON A3.	..	TTI40500
00760	0770 00 0 01203	WEFA	3	..	..	TTI40510

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
SECTION 4, WIND UP THIS RUN.

00761	2 00001 4 00760	TIX	*-1,4,1	..	TT140550	
00762	-0772 00 0 01203	RUNA	3	THEN RUN OUTPUT TAPE.	TT140560	
00763	0074 00 4 02520	TSX	PRINT,4	COMMENT.	TT140570	
00764	-0 00016 0 01061	MZE	XCLOSE,0,14	..	TT140580	
00765	060C 00 0 03125	DOOR	STZ	=0	MAKE A ZERO LOCATION.	TT140590
00766	0564 00 0 03125	ENB	=0	RESET THE TRAPS.	TT140600	
00767	-0760 00 0 00007	LTM		JUST IN CASE.	TT140610	
00770	0074 00 4 00663	TSX	LSTM,4	..	TT140620	
00771	-0760 00 0 00010	LSNM		..	TT140630	
00772	0760 00 0 00004	ENK		GET CONSOLE KEYS.	TT140640	
00773	-0130 00 0 00000	XCL		PLACE IN AC.	TT140650	
00774	0044 00 0 00000	PAI		PLACE IN INDICATORS.	TT140660	
00775	-0056 00 0 00001	LNT	1	CHECK IF OPERATOR WANTS TO STOP.	TT140670	
00776	0020 00 0 01002	TRA	DOOR1	NO.	TT140680	
00777	0074 00 4 02520	TSX	PRINT,4	YES, COMMENT.	TT140690	
01000	-0 00013 0 01113	MZE	SEXIT,0,11	..	TT140700	
01001	0020 00 0 00765	TRA	DOOR	GO BACK TO CHECK KEYS.	TT140710	
01002	0022 00 0 01003	DOOR1	TRCA	**+1	TURN OFF RC LIGHT.	TT140720
01003	0774 00 1 00005	AXT	5,1	SET UP FOR 5 TRIES.	TT140730	
01004	0772 00 0 01201	REWA	1	REWIND THE SYSTEMS TAPE.	TT140740	
01005	0762 00 0 01221	RTBA	1	SELECT.	TT140750	
01006	0540 00 0 01024	RCHA	LOAD	LOAD SEQUENCE OF CHANNEL COMMANDS.	TT140760	
01007	-0054 00 0 00002	LFT	2	MISTART OR EXITM.	TT140770	
01010	0020 00 0 01013	TRA	**+3	MISTART.	TT140780	
01011	0762 00 0 01221	RTBA	1	EXITM, SKIP TWO RECORDS.	TT140790	
01012	0762 00 0 01221	RTBA	1	..	TT140800	
01013	0060 00 0 01013	TCOA	*	WAIT FOR DSCA.	TT140810	
01014	0022 00 0 01020	TRCA	**+4	EXIT FOR READ ERROR.	TT140820	
01015	-0500 00 0 01015	CAL	*	SET PREFIX OF 34 TO MZE.	TT140830	
01016	0630 00 0 00042	STP	34	..	TT140840	
01017	0020 00 0 00001	TRA	1	THEN RETURN TO MONITOR.	TT140850	
01020	2 00001 1 01004	TIX	DOOR1+2,1,1	READING ERROR, INDEX AND TRY AGAIN.	TT140860	
01021	0074 00 4 02520	TSX	PRINT,4	FIVE REDUNDANCY FAILURES, COMMENT.	TT140870	
01022	-0 00017 0 01126	MZE	XRCA1,0,15	..	TT140880	
01023	0020 00 0 00765	TRA	DOOR	GO TRY FIVE MORE TIMES.	TT140890	
01024	-0 00003 0 00000	LOAD	IOCP	0,0,3	CHANNEL COMMANDS.	TT140900
01025	1 00000 0 00000	TCH	0	..	TT140910	
01026	0 00000 0 00000	EPMR	PZE	TEST CELL FOR ERROR POST MORTEM.	TT140920	

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
SECTION 4, WIND UP THIS RUN.

		EJECT TITLE	SUPPRESS GENERATED OCTAL LISTING. COMMENTS.	
01027	002545246046	ENDRN BCI	2,END OF RUN.	TT)40970
01031	004225706003	XSTOP BCI	9,CKEY 34 DOWN, STOP COMMAND WHILE CHECKING KEYS, PRESS	TT)40980
01042	626321516360	BCI	3,START TO CONTINUE.	TT)40990
01045	004225706003	XFILE BCI	9,0KEY 33 DOWN, AN EOF HAS BEEN WRITTEN ON A3, PRESS STA	TT)41000
01056	516360634660	BCI	3,RT TO CONTINUE.	TT)41010
01061	004225706003	XCLOSE BCI	9,0KEY 35 DOWN, TAPE A3 HAS BEEN CLOSED, CHANGE TAPE AND	TT)41020
01072	604751256262	BCI	5, PRESS START TO CONTINUE.	TT)41030
01077	012545246046	ENDTP BCI	3,1END OF TAPE.	TT)41040
01102	006330255125	RENDTP BCI	9,C THERE REALLY ISN'T ANY MORE ON THIS TAPE - HONEST.	TT)41050
01113	004225706001	SEXIT BCI	9,0KEY 17 DOWN, STOP COMMAND BEFORE EXIT, PRESS START TO	TT)41060
01124	602346456331	BCI	2, CONTINUE.	TT)41070
01126	002631652560	XRCA1 BCI	9,0FIVE CONSECUTIVE REDUNDANCY FAILURES IN READING A1. P	TT)41080
01137	512562626062	BCI	6,RESS START FOR FIVE MORE TRIES.	TT)41090
		DETAIL	RETURN TO NORMAL LISTING MODE.	TT)41100
				TT)41110
				TT)41120
				TT)41130
				TT)41140
				TT)41150
				TT)41160
				TT)41170
				TT)41180
				TT)41190
				TT)41200
				TT)41210
				TT)41220
				TT)41230
				TT)41240
				TT)41250
				TT)41260
				TT)41270
				TT)41280

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
SECTION 5, SVCON, PMR, OCT, OCTADR, AND TABBLK.

120

TTL SECTION 5, SVCON, PMR, OCT, OCTADR, AND TABBLK.						
						TT150000
						TT150010
01145 0634 00 4 01166 SX4 SXA IR4,4 ENTRY TO SAVE IR4 FOR PMR USE.						TT150020
			SPACE	2		TT150030
				CONSOLE LIGHTS SAVING ROUTINE.		TT150040
						TT150050
01146 0600 00 0 00005	SVCON	STZ	5	RESET INTERVAL TIMER.		TT150060
01147 -0061 00 0 01151		TCNT	**+2	IF TAPE TIMER IN USE,		TT150070
01150 -0540 00 0 00261		RCHT	QUIT	RESET TAPE TIMER.		TT150080
01151 0634 00 4 01153		SXA	**+2,4	SAVE IR4.		TT150090
01152 0074 00 4 00663		TSX	LSTM,4	RESET TRAP.		TT150100
01153 0774 00 4 00000		AXT	**,4	RESTORE IR4.		TT150110
01154 0634 00 1 01164		SXA	IR1,1	SAVE IR1.		TT150120
01155 0634 00 2 01165		SXA	IR2,2	SAVE IR2.		TT150130
01156 -0600 00 0 01171		STQ	MQ	SAVE THE MQ.		TT150140
01157 0602 00 0 01170		SLW	AC	SAVE THE AC.		TT150150
01160 0765 00 0 00045		LRS	37	GET S,Q,P BITS.		TT150160
01161 -0600 00 0 01172		STQ	SVPQ	SAVE.		TT150170
01162 0604 00 0 01167		STI	SIND	SAVE INDICATORS.		TT150180
01163 0020 00 4 00001		TRA	1,4	RETURN.		TT150190
				CONSOLE STORAGE.		TT150200
01164 0 00000 0 00000	IR1	PZE				TT150210
01165 0 00000 0 00000	IR2	PZE		..		TT150220
01166 0 00000 0 00000	IR4	PZE		..		TT150230
01167 0 00000 0 00000	SIND	PZE		..		TT150240
01170 0 00000 0 00000	AC	PZE		..		TT150250
01171 0 00000 0 00000	MQ	PZE		..		TT150260
01172 0 00000 0 00000	SVPQ	PZE		..		TT150270
		SPACE	2			TT150280
				ADDRESS TO OCTAL CONVERTER, DELETE LEADING ZEROES.		TT150290
						TT150300
01173 -0763 00 0 00025	OCTADR	LGL	21	WORD IN MQ.		TT150310
01174 -0754 00 0 00000		PXD	0,0	CLEAR AC.		TT150320
01175 0634 00 4 01205		SXA	**+8,4	SAVE IR4.		TT150330
01176 0774 00 4 00005		AXT	5,4	SET UP LOOP.		TT150340
01177 0767 00 0 00003		ALS	3	INSERT 000 BETWEEN GROUPS OF THREE BITS.		TT150350
01200 -0763 00 0 00003		LGL	3	..		TT150360
01201 2 00001 4 01177		TIX	**-2,4,1	..		TT150370
01202 -0130 00 0 00000		XCL		ANSWER IN MQ.		TT150380
01203 -0154 05 0 01207		CRQ	TABBLK,0,5	DELETE LEADING ZEROES.		TT150390
01204 -0773 00 0 00006		RQL	6	LAST ZERO.		TT150400
01205 0774 00 4 00000		AXT	**,4	RESTORE IR4.		TT150410
01206 0020 00 4 00001		TRA	1,4	RETURN.		TT150420
		SPACE	2			TT150430
				TABLE FOR DELETING LEADING ZEROES.		TT150440
						TT150450
01207 600000001207	TABBLK	VFD	06/60,15/0,15/TABBLK			TT150460
01210 010000001221		VFD	H6/1,15/0,15/TABBLK+10			TT150470
01211 020000001221		VFD	H6/2,15/0,15/TABBLK+10			TT150480

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
SECTION 5, SVCON, PMR, OCT, OCTADR, AND TABBLK.

01212	030000001221	VFD	H6/3,15/0,15/TABBLK+10	TT)50490
01213	040000001221	VFD	H6/4,15/0,15/TABBLK+10	TT)50500
01214	050000001221	VFD	H6/5,15/0,15/TABBLK+10	TT)50510
01215	060000001221	VFD	H6/6,15/0,15/TABBLK+10	TT)50520
01216	070000001221	VFD	H6/7,15/0,15/TABBLK+10	TT)50530
01217	100000001221	VFD	H6/8,15/0,15/TABBLK+10	TT)50540
01220	110000001221	VFD	H6/9,15/0,15/TABBLK+10	TT)50550
01221	000000001221	VFD	H6/0,15/0,15/TABBLK+10	TT)50560
01222	010000001221	VFD	H6/1,15/0,15/TABBLK+10	TT)50570
01223	020000001221	VFD	H6/2,15/0,15/TABBLK+10	TT)50580
01224	030000001221	VFD	H6/3,15/0,15/TABBLK+10	TT)50590
01225	040000001221	VFD	H6/4,15/0,15/TABBLK+10	TT)50600
01226	050000001221	VFD	H6/5,15/0,15/TABBLK+10	TT)50610
01227	060000001221	VFD	H6/6,15/0,15/TABBLK+10	TT)50620
01230	070000001221	VFD	H6/7,15/0,15/TABBLK+10	TT)50630
01231	100000001221	VFD	H6/8,15/0,15/TABBLK+10	TT)50640
01232	110000001221	VFD	H6/9,15/0,15/TABBLK+10	TT)50650

SPACE 2  
COMPLEMENT ADDRESS TO OCTAL-BCI CONVERTER. TT)50660  
TT)50670

01233	0634 00 4 01256	COMADR	SXA	COMRT,4	SAVE IR4.	TT)50680
01234	0774 00 4 01251		AXT	COMSW+1,4	RESET SWITCH.	TT)50690
01235	0634 00 4 01250		SXA	COMSW,4	..	TT)50700
01236	-0130 00 0 00000		XCL		..	TT)50710
01237	-0100 00 0 01242		TNZ	*+3	IF ZERO, SET.	TT)50720
01240	0560 00 0 03157		LDQ	=H -0	..	TT)50730
01241	0020 00 0 01256		TRA	COMRT	AND EXIT.	TT)50740
01242	0737 00 4 00000		PAC	0,4	..	TT)50750
01243	0754 00 4 00000		PXA	0,4	..	TT)50760
01244	-0765 00 0 00017		LGR	15	..	TT)50770
01245	0774 00 4 00005		AXT	5,4	..	TT)50780
01246	0767 00 0 00003		ALS	3	..	TT)50790
01247	-0763 00 0 00003		LGL	3	..	TT)50800
01250	0020 00 0 01251	COMSW	TRA	*+1	SWITCH AFTER FIRST NON-ZERO DIGIT.	TT)50810
01251	0100 00 0 01254		TZE	*+3	..	TT)50820
C1252	-0501 00 0 03157		ORA	=H -0	..	TT)50830
01253	-0625 00 0 01250		STL	COMSW	SET SWITCH.	TT)50840
01254	2 00001 4 01246		TIX	*-6,4,1	..	TT)50850
01255	-0130 00 0 00000		XCL		..	TT)50860
01256	0774 00 4 00000	COMRT	AXT	**,4	RESTORE IR4.	TT)50870
01257	0020 00 4 00001		TRA	1,4	RETURN.	TT)50880
						TT)50890

SPACE 2  
FULL WORD BINARY TO OCTAL-BCI CONVERTER. TT)50900  
TT)50910

01260	0634 00 4 01276	OCT	SXA	*+14,4	WORD IN MQ.	TT)50920
01261	0774 00 4 00006		AXT	6,4	CONVERT LEFT HALF.	TT)50930
01262	-0754 00 0 00000		PXD	0,0	..	TT)50940
01263	0767 00 0 00003		ALS	3	..	TT)50950
01264	-0763 00 0 00003		LGL	3	..	TT)50960
C1265	2 00001 4 01263		TIX	*-2,4,1	..	TT)50970
01266	0602 00 0 01300		SLW	*+10	..	TT)50980
						TT)50990

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
 SECTION 5, SVCON, PMR, OCT, OCTADR, AND TABBLK.

01267	0774 00 4 00006	AXT	6,4	CONVERT RIGHT HALF.	TT)51000
01270	-0754 00 0 00000	PXD	0,0	..	TT)51010
01271	0767 00 0 00003	ALS	3	..	TT)51020
01272	-0763 00 0 00003	LGL	3	..	TT)51030
01273	2 00001 4 01271	TIX	*-2,4,1	..	TT)51040
01274	-0130 00 0 00000	XCL	*+3	LOAD COMPLETED WORD.	TT)51050
01275	-0500 00 0 01300	CAL	**+,4	..	TT)51060
01276	0774 00 4 00000	AXT	**+,4	RESTORE IR4.	TT)51070
01277	0020 00 4 00001	TRA	1,4	RETURN TO CALLER.	TT)51080
01300	0 00000 0 00000	PZE		TEMPORARY STORAGE.	TT)51090
01260	OCT)	SYN	OCT	EXTERNAL NAME FOR OCT.	TT)51100
					TT)51110

SPACE 2  
 TABLE FOR DELETING ILLEGAL BCI CHARACTERS.

01301	000000001301	BCDTAB	VFD	H6/0,15/0,15/BCDTAB	00	TT)51120
01302	010000001301		VFD	H6/1,15/0,15/BCDTAB	01	TT)51130
01303	020000001301		VFD	H6/2,15/0,15/BCDTAB	02	TT)51140
01304	030000001301		VFD	H6/3,15/0,15/BCDTAB	03	TT)51150
01305	040000001301		VFD	H6/4,15/0,15/BCDTAB	04	TT)51160
01306	050000001301		VFD	H6/5,15/0,15/BCDTAB	05	TT)51170
01307	060000001301		VFD	H6/6,15/0,15/BCDTAB	06	TT)51180
01310	070000001301		VFD	H6/7,15/0,15/BCDTAB	07	TT)51190
01311	100000001301		VFD	H6/8,15/0,15/BCDTAB	10	TT)51200
01312	110000001301		VFD	H6/9,15/0,15/BCDTAB	11	TT)51210
01313	540000001301		VFD	H6/*,15/0,15/BCDTAB	12	TT)51220
01314	130000001301		VFD	H6/=,15/0,15/BCDTAB	13	TT)51230
01315	140000001301		VFD	H6/*,15/0,15/BCDTAB	14	TT)51240
01316	540000001301		VFD	H6/*,15/0,15/BCDTAB	15	TT)51250
01317	540000001301		VFD	H6/*,15/0,15/BCDTAB	16	TT)51260
01320	540000001301		VFD	H6/*,15/0,15/BCDTAB	17	TT)51270
01321	200000001301		VFD	H6/+,15/0,15/BCDTAB	20	TT)51280
01322	210000001301		VFD	H6/A,15/0,15/BCDTAB	21	TT)51290
01323	220000001301		VFD	H6/B,15/0,15/BCDTAB	22	TT)51300
01324	230000001301		VFD	H6/C,15/0,15/BCDTAB	23	TT)51310
01325	240000001301		VFD	H6/D,15/0,15/BCDTAB	24	TT)51320
01326	250000001301		VFD	H6/E,15/0,15/BCDTAB	25	TT)51330
01327	260000001301		VFD	H6/F,15/0,15/BCDTAB	26	TT)51340
01330	270000001301		VFD	H6/G,15/0,15/BCDTAB	27	TT)51350
01331	300000001301		VFD	H6/H,15/0,15/BCDTAB	30	TT)51360
01332	310000001301		VFD	H6/I,15/0,15/BCDTAB	31	TT)51370
01333	540000001301		VFD	H6/*,15/0,15/BCDTAB	32	TT)51380
01334	330000001301		VFD	H6/.,15/0,15/BCDTAB	33	TT)51390
01335	340000001301		VFD	H6/),15/0,15/BCDTAB	34	TT)51400
01336	540000001301		VFD	H6/*,15/0,15/BCDTAB	35	TT)51410
01337	540000001301		VFD	H6/*,15/0,15/BCDTAB	36	TT)51420
01340	540000001301		VFD	H6/*,15/0,15/BCDTAB	37	TT)51430
01341	400000001301		VFD	H6/-,15/0,15/BCDTAB	40	TT)51440
01342	410000001301		VFD	H6/J,15/0,15/BCDTAB	41	TT)51450
01343	420000001301		VFD	H6/K,15/0,15/BCDTAB	42	TT)51460
01344	430000001301		VFD	H6/L,15/0,15/BCDTAB	43	TT)51470
01345	440000001301		VFD	H6/M,15/0,15/BCDTAB	44	TT)51480
01346	450000001301		VFD	H6/N,15/0,15/BCDTAB	45	TT)51490

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
SECTION 5, SVCON, PMR, OCT, OCTADR, AND TABBLK.

01347	460000001301	VFD	H6/Q,15/0,15/BCDTAB	* 46		TT)51530
01350	470000001301	VFD	H6/P,15/0,15/BCDTAB	* 47		TT)51540
01351	500000001301	VFD	H6/Q,15/0,15/BCDTAB	50		TT)51550
01352	510000001301	VFD	H6/R,15/0,15/BCDTAB	51		TT)51560
01353	540000001301	VFD	H6/*,15/0,15/BCDTAB	52		TT)51570
01354	530000001301	VFD	H6/\$,15/0,15/BCDTAB	53		TT)51580
01355	540000001301	VFD	H6/*,15/0,15/BCDTAB	54		TT)51590
01356	540000001301	VFD	H6/*,15/0,15/BCDTAB	55		TT)51600
01357	540000001301	VFD	H6/*,15/0,15/BCDTAB	56		TT)51610
01360	540000001301	VFD	H6/*,15/0,15/BCDTAB	57		TT)51620
01361	600000001301	VFD	O6/60,15/0,15/BCDTAB	60 NO BLANKS ALLOWED IN VFD.		TT)51630
01362	610000001301	VFD	H6//,15/0,15/BCDTAB	61		TT)51640
01363	620000001301	VFD	H6/S,15/0,15/BCDTAB	62		TT)51650
01364	630000001301	VFD	H6/T,15/0,15/BCDTAB	63		TT)51660
01365	640000001301	VFD	H6/U,15/0,15/BCDTAB	64		TT)51670
01366	650000001301	VFD	H6/V,15/0,15/BCDTAB	65		TT)51680
01367	660000001301	VFD	H6/W,15/0,15/BCDTAB	66		TT)51690
01370	670000001301	VFD	H6/X,15/0,15/BCDTAB	67		TT)51700
01371	700000001301	VFD	H6/Y,15/0,15/BCDTAB	70		TT)51710
01372	710000001301	VFD	H6/Z,15/0,15/BCDTAB	71		TT)51720
01373	540000001301	VFD	H6/*,15/0,15/BCDTAB	72		TT)51730
01374	730000001301	VFD	O6/73,15/0,15/BCDTAB	73 NO COMMAS ALLOWED IN VFD.		TT)51740
01375	740000001301	VFD	H6/I,15/0,15/BCDTAB	74		TT)51750
01376	540000001301	VFD	H6/*,15/0,15/BCDTAB	75		TT)51760
01377	540000001301	VFD	H6/*,15/0,15/BCDTAB	76		TT)51770
01400	540000001301	VFD	H6/*,15/0,15/BCDTAB	77		TT)51780

SPACE	2					
	POST MORTEM SECTION.					
01401	0074 00 4 02407	PMR	TSX	WOT,4	COMMENT ERROR IN OBJECT PROGRAM.	TT)51790
01402	0 00007 0 01474		PZE	PROER,0,7	..	TT)51800
01403	0760 00 0 00141		SLN	1	SENSE LIGHTS ON MEANS POST MORTEM.	TT)51810
01404	0760 00 0 00142		SLN	2	..	TT)51820
01405	0760 00 0 00143		SLN	3	..	TT)51830
01406	0760 00 0 00144		SLN	4	..	TT)51840
01407	0074 00 4 00003		TSX	\$PPROG,4	DUMP SYMBOLIC PROGRAM.	TT)51850
01410	0074 00 4 00004		TSX	\$PCT1,4	DUMP COLLATION TAPE.	TT)51860
01411	0074 00 4 01523		TSX	DCON,4	GO TO PRINT CONSOLE.	TT)51870
01412	0774 00 2 00036	SLPM	AXT	NSYM,2	SET UP SYMBOL TABLE SEARCH.	TT)51880
01413	-0500 00 2 03067		CAL	ORIGIN+NSYM,2	GET NEXT ORIGIN.	TT)51890
01414	0621 00 0 01445		STA	COD1	PLACE IN CALLING SEQUENCE.	TT)51900
01415	0402 00 2 03070		SUB	ORIGIN+NSYM+1,2	COUNT IN ADDRESS.	TT)51910
01416	0767 00 0 00022		ALS	18	PLACE IN DECREMENT.	TT)51920
01417	0622 00 0 01445		STD	COD1	PLACE IN CALLING SEQUENCE.	TT)51930
01420	0560 00 2 03031		LDQ	NAME+NSYM,2	GET THE NAME OF THIS PROGRAM.	TT)51940
01421	-0754 00 0 00000		PXD	0,C	SHIFT AND OR TO COMMENT.	TT)51950
01422	-0763 00 0 00022		LGL	18	..	TT)51960
01423	-0501 00 0 03154		ORA	=HOF 000	..	TT)51970
01424	0602 00 0 01505		SLW	PMH+2	..	TT)51980
01425	-0130 00 0 00000		XCL		..	TT)51990
01426	-0501 00 0 03137		ORA	=H000 FO	..	TT)52000
01427	0602 00 0 01506		SLW	PMH+3	..	TT)52010

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
 SECTION 5, SVCON, PMR, OCT, OCTADR, AND TABBLK.

01430	0560 00 0 03142	LDQ	=HOOCTAL	ASSUME DOUBLE SPACE FOR HEADING.	TT152060	
01431	0500 00 0 02022	CLA	PMCNT	GET PM LINE COUNT.	TT152070	
01432	0402 00 0 03131	SUB	=5	AT LEAST FIVE LINES LEFT.	TT152080	
01433	0120 00 0 01437	TPL	*+4	IF PLUS, OK, SKIP.	TT152090	
01434	0560 00 0 03145	LDQ	=H1OCTAL	SET TO EJECT PAGE.	TT152100	
01435	050C 00 0 03135	CLA	=59	RESET LINE COUNT.	TT152110	
01436	0020 00 0 01440	TRA	*+2	SKIP ADDITION.	TT152120	
01437	0400 00 0 03130	ADD	=3	NORMALLY TWO LINES FOR HEADING.	TT152130	
01440	0601 00 0 02022	STO	PMCNT	SAVE PM LINE COUNT.	TT152140	
01441	-0600 00 0 01503	STQ	PMH	INSERT CARRAIGE CONTROL.	TT152150	
01442	0074 00 4 02407	TSX	WOT,4	PRINT HEADING.	TT152160	
01443	0 00005 0 01503	PZE	PMH,0,5	..	TT152170	
01444	0074 00 4 01640	TSX	OCTDMP,4	EXIT TO GIVE POST MORTEM.	TT152180	
01445	0 00000 0 00000	COD1	PZE	**,0,**	TT152190	
01446	1 77777 2 01447	TXI	*+1,2,-1	INDEX.	TT152200	
01447	3 00000 2 01413	LSUB	TXH	SLPM+1,2,**	COUNT INSERTED BY MAP, NEXT POST MORTEM.	TT152210
					TT152220	
01450	0560 00 0 03142	LDQ	=HOOCTAL	ASSUME DOUBLE SPACE FOR HEADING.	TT152230	
01451	0500 00 0 02022	CLA	PMCNT	GET PM LINE COUNT.	TT152240	
01452	0402 00 0 03131	SUB	=5	AT LEAST FIVE LINES LEFT.	TT152250	
01453	0120 00 0 01457	TPL	*+4	IF PLUS, OK, SKIP.	TT152260	
01454	0560 00 0 03145	LDQ	=H1OCTAL	SET TO EJECT PAGE.	TT152270	
01455	0500 00 0 03135	CLA	=59	RESET LINE COUNT.	TT152280	
01456	0020 00 0 01460	TRA	*+2	SKIP ADDITION.	TT152290	
01457	0400 00 0 03130	ADD	=3	NORMALLY TWO LINES FOR HEADING.	TT152300	
01460	0601 00 0 02022	STO	PMCNT	SAVE PM LINE COUNT.	TT152310	
01461	-0600 00 0 01503	STQ	PMH	INSERT CARRAIGE CONTROL.	TT152320	
01462	0074 00 4 02407	TSX	WOT,4	PRINT HEADING.	TT152330	
01463	0 00007 0 01510	PZE	PMBP,0,7	..	TT152340	
01464	-0500 00 0 00234	CAL	ORG	SET ORIGIN OF ASSEMBLED PROGRAM.	TT152350	
01465	0621 00 0 01467	STA	*+2	..	TT152360	
01466	0074 00 4 01640	TSX	OCTDMP,4	..	TT152370	
01467	0 00400 0 00000	PZE	**,0,256	END OF POST MORTEM, COMMENT.	TT152380	
01470	0074 00 4 02407	TSX	WOT,4	..	TT152390	
01471	0 00004 0 01517	PZE	ENDPM,0,4	TURN OFF SL AFTER POST MORTEM.	TT152400	
01472	0760 00 0 00140	SLF		..	TT152410	
01473	0020 00 0 00714	TRA	FINIS	RETURN.	TT152420	
					TT152430	
01474	004622412523	PROER	BCI	7,00BJECT PROGRAM ERROR, PROGRAM TERMINATED.	TT152440	
01475	636047514627					
01476	512144602551					
01477	514651736047					
01500	514627512144					
01501	606325514431					
01502	452163252433					
01503	004623632143	PMH	BCI	5,OCOTAL DUMP OF 000000 FOLLOWS.	TT152450	
01504	602464444760					
01505	462660000000					
01506	000000602646					
01507	434346666233					
01510	004623632143	PMBP	BCI	7,0OCTAL DUMP OF ASSEMBLED PROGRAM FOLLOWS.	TT152460	
01511	602464444760					
01512	462660216262					
01513	254422432524					
01514	604751462751					

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
SECTION 5, SVCON, PMR, OCT, OCTADR, AND TABBLK.

01515	214460264643			
01516	434666623360			
01517	002545246046	ENDPM BC I	4,0END OF POST MORTEM.	TT152470
01520	266047466263			
01521	604446516325			
01522	443360606060			

		SPACE	2		
			USE RESULTS OF SVCON TO DUMP CONSOLE LIGHTS.	TT152480	
				TT152490	
01523	0634 00 4 01602	DCON	SXA DCNX4,4	SAVE IR4.	TT152500
01524	0560 00 0 01172	LDQ	SVPQ	S,Q,P.	TT152510
01525	-0754 00 0 00000	PXD	0,0	CLEAR AC.	TT152520
01526	-0763 00 0 00001	LGL	1	..	TT152530
01527	0767 00 0 00013	ALS	11	..	TT152540
01530	-0763 00 0 00001	LGL	1	..	TT152550
01531	0767 00 0 00013	ALS	11	..	TT152560
01532	-0763 00 0 00001	LGL	1	..	TT152570
01533	-0501 00 0 03155	ORA	=H 0,0,0	PUT IN COMMAS.	TT152580
01534	0602 00 C 01612	SLW	HEAD02+2	INSERT.	TT152590
01535	0560 00 0 01170	LDQ	AC	CONVERT AC TO OCTAL.	TT152600
01536	0074 00 4 01260	TSX	OCT,4	..	TT152610
01537	0602 00 0 01615	SLW	HEAD03+2	INSERT.	TT152620
01540	-0600 00 0 01616	STQ	HEAD03+3	..	TT152630
01541	0560 00 0 01171	LDQ	MQ	CONVERT MQ TO OCTAL.	TT152640
01542	0074 00 4 01260	TSX	OCT,4	..	TT152650
01543	0602 00 0 01621	SLW	HEAD04+2	INSERT.	TT152660
01544	-0600 00 0 01622	STQ	HEAD04+3	..	TT152670
01545	0560 00 0 01167	LDQ	SIND	CONVERT SI TO OCTAL.	TT152680
01546	0074 00 4 01260	TSX	OCT,4	..	TT152690
01547	0602 00 0 01625	SLW	HEAD05+2	INSERT.	TT152700
01550	-0600 00 0 01626	STQ	HEAD05+3	..	TT152710
01551	0560 00 0 01164	LDQ	IR1	CONVERT IR1.	TT152720
01552	0074 00 4 01173	TSX	OCTADR,4	..	TT152730
C1553	-0600 00 0 01631	STQ	HEAD06+2	INSERT.	TT152740
01554	0560 00 0 01165	LDQ	IR2	CONVERT IR2.	TT152750
01555	0074 00 4 01173	TSX	OCTADR,4	..	TT152760
01556	-0600 00 0 01634	STQ	HEAD07+2	..	TT152770
01557	0560 00 0 01166	LDQ	IR4	CONVERT IR4.	TT152780
01560	0074 00 4 01173	TSX	OCTADR,4	..	TT152790
01561	-0600 00 0 01637	STQ	HEAD08+2	INSERT.	TT152800
01562	0074 00 4 02407	TSX	WOT,4	PRINT CONSOLE.	TT152810
01563	0 00004 0 01604	PZE	HEAD01,0,4	..	TT152820
01564	0074 00 4 02407	TSX	WOT,4	..	TT152830
01565	0 00003 0 01610	PZE	HEAD02,0,3	..	TT152840
01566	0074 00 4 02407	TSX	WOT,4	..	TT152850
01567	0 00004 0 01613	PZE	HEAD03,0,4	..	TT152860
01570	0074 00 4 02407	TSX	WOT,4	..	TT152870
01571	0 00004 0 01617	PZE	HEAD04,0,4	..	TT152880
01572	0074 00 4 02407	TSX	WOT,4	..	TT152890
01573	0 00004 0 01623	PZE	HEAD05,0,4	..	TT152900
01574	0074 00 4 02407	TSX	WOT,4	..	TT152910
01575	0 00003 0 01627	PZE	HEAD06,0,3	..	TT152920
01576	0074 00 4 02407	TSX	WOT,4	..	TT152930
				TT152940	

TESTS FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
SECTION 5, SVCON, PMR, OCT, OCTADR, AND TABBLK.

01577	0 00003 0 01632	PZE	HEAD07,0,3	..	TT152950
01600	0074 00 4 02407	TSX	WOT,4	..	TT152960
01601	0 00003 0 01635	PZE	HEAD08,0,3	..	TT152970
01602	0774 00 4 00000	CCNX4 AXT	**,4	RESTORE IR4.	TT152980
01603	0020 00 4 00001	TRA	1,4	RETURN.	TT152990
01604	014746626360	HEAD01 BCI	4,1	POST MORTEM OF CONSOLE.	TT153000
01605	444651632544				TT153010
01606	604626602346				
01607	456246432533				
01610	006060606060	HEAD02 BCI	3,0	S,Q,P= 0,0,0	TT153020
01611	627350734713				
01612	600073007300	HEAD03 BCI	4,C	AC = 000000000000	TT153030
01613	006060606060				
01614	212360136060				
01615	000000000000				
01616	000000000000				
01617	006060606060	HEAD04 BCI	4,0	MQ = 000000000000	TT153040
01620	445060136060				
01621	000000000000				
01622	000000000000				
01623	006060606060	HEAD05 BCI	4,0	SI = 000000000000	TT153050
01624	623160136060				
01625	000000000000				
01626	000000000000				
01627	006060606060	HEAD06 BCI	3,0	IR1= 000000	TT153060
01630	315101136060				
01631	000000000000				
01632	006060606060	HEAD07 BCI	3,0	IR2= 000000	TT153070
01633	315102136060				
01634	000000000000				
01635	006060606060	HEAD08 BCI	3,0	IR4= 000000	TT153080
01636	315104136060				
01637	000000000000				

		SPACE	2	OCTDMP, OCTAL DUMP WITH MNEMONICS.	TT153090
					TT153100
					TT153110
					TT153120
01640	0634 00 4 02016	OCTDMP SXA	DX4,4	SAVE IRS.	TT153130
01641	0634 00 2 02017	SXA	DX2,2	..	TT153140
01642	0634 00 1 02020	SXA	DX1,1	..	TT153150
01643	-0500 00 4 00001	CAL	1,4	GET CALLING SEQUENCE.	TT153160
01644	-0734 00 1 00000	PDX	0,1	COUNT TO IR1.	TT153170
01645	0621 00 0 02023	STA	ILC	FIRST LOCATION.	TT153180
01646	0771 00 0 00022	ARS	18	FIRST + N = LAST.	TT153190
01647	0361 00 4 00001	ACL	1,4	COMPUTE END ADDRESS.	TT153200
01650	0621 00 0 01660	STA	LOOP1	SET UP LOOP.	TT153210
01651	0621 00 0 01664	STA	LOOP1+4	..	TT153220
01652	0621 00 0 01742	STA	REG+2	..	TT153230
01653	0560 00 0 02023	ADR	LDQ ILC	GET ILC AND CONVERT.	TT153240
01654	0074 00 4 01173	TSX	OCTADR,4	..	TT153250
01655	-0773 00 0 00006	RQL	6	PUT BLANK AT END.	TT153260
01656	-0600 00 0 02746	STQ	OUT+1	INSERT.	TT153270
01657	0774 00 2 00022	LOOP2 AXT	18,2	SET WORD COUNT.	

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
SECTION 5, SVCON, PMR, OCT, OCTADR, AND TABBLK.

01660 -0500 00 1 00000	LOOP1	CAL	**,1	GET WORD.	
01661 -3 00017 2 01740	TXL	REG,2,15		IF FIRST WORD, CHECK FOR REPEATS.	TT153280
01662 0602 00 0 02024	SLW	LWORD		SAVE WORD.	TT153290
01663 0774 00 4 00000	AXT	0,4		SET IR4.	TT153300
01664 -0340 00 1 00000	LAS	**,1		CHECK FOR REPEATS.	TT153310
01665 0020 00 0 01672	TRA	**5		NOT SAME, EXIT.	TT153320
01666 1 00001 4 01670	TXI	**+2,4,1		SAME, INDEX.	TT153330
01667 0020 00 0 01672	TRA	**3		NOT SAME, EXIT.	TT153340
01670 2 00001 1 01664	TIK	**-4,1,1		INDEX AND TRY NEXT WORD.	TT153350
01671 1 77777 4 01672	TXI	**+1,4,-1		LAST WORD, INDEX FOR LINE AT BOTTOM.	TT153360
01672 3 00022 4 01675	TXH	**+3,4,18		IF MORE THAN 18 REPEATS, COMMENT.	TT153370
01673 -0634 00 4 01674	SXD	**+1,4		LESS THAN SIX, RETURN TO NORMAL.	TT153380
01674 1 00000 1 01740	TXI	REG,1,**		..	TT153390
01675 0634 00 4 02025	SXA	NREP,4		MORE THAN SIX, CONVERT NUMBER.	TT153400
01676 0560 00 0 02025	LDQ	NREP		PLACE IN MQ.	TT153410
01677 0600 00 0 02026	STZ	DNREP		CLEAR DECIMAL NREP.	TT153420
01700 0774 00 4 00036	AXT	30,4		SET CONVERSION LOOP.	TT153430
01701 -0754 00 0 00000	PXD	0,0		CLEAR AC.	TT153440
01702 0221 00 0 03133	DVP	=10		MOD TEN.	TT153450
01703 0767 00 4 00036	ALS	30,4		SHIFT TO POSITION.	TT153460
01704 -0602 00 0 02026	ORS	DNREP		INSERT.	TT153470
01705 2 00006 4 01701	TIK	**-4,4,6		INDEX.	TT153480
01706 0560 00 0 02026	LDQ	DNREP		DELETE LEADING ZEROES.	TT153490
01707 -0154 06 0 01207	CRQ	TABBLK,0,6		..	TT153500
01710 -0600 00 0 02037	STQ	WREP+8		PLACE IN COMMENT.	TT153510
01711 -0500 00 0 02024	CAL	LWORD		CONVERT WORD.	TT153520
01712 0074 00 4 02047	TSX	(OPCD),4		..	TT153530
01713 0602 00 0 02043	SLW	WREP+12		..	TT153540
01714 0560 00 0 02024	LDQ	LWORD		..	TT153550
01715 0074 00 4 01260	TSX	OCT,4		..	TT153560
01716 0602 00 0 02044	SLW	WREP+13		..	TT153570
01717 -0600 00 0 02045	STQ	WREP+14		..	TT153580
01720 0560 00 0 03143	LDQ	=HC		ASSUME DOUBLE SPACE FOR COMMENT.	TT153590
01721 0500 00 0 02022	CLA	PMCNT		GET POST MORTEM LINE COUNT.	TT153600
01722 0402 00 0 03130	SUB	=3		REPEAT COMMENT TAKES THREE LINES.	TT153610
01723 0120 00 0 01726	TPL	**3		SKIP IF IT FITS.	TT153620
01724 0560 00 0 03146	LDQ	=H1		SET TO EJECT PAGE.	TT153630
01725 0500 00 0 03134	CLA	=58		RESET PM LINE COUNT.	TT153640
01726 0601 00 0 02022	STO	PMCNT		SAVE LINE COUNT.	TT153650
01727 -0600 00 0 02027	STQ	WREP		INSERT CARRIAGE CONTROL.	TT153660
01730 0074 00 4 02407	TSX	WOT,4		WOT REPEATS.	TT153670
01731 0 00020 0 02027	PZE	WREP,0,16		..	TT153680
01732 0074 00 4 02407	TSX	WOT,4		BLANK LINE.	TT153690
01733 0 00001 0 03160	PZE	=H ,0,1		..	TT153700
01734 -0500 00 0 02023	CAL	ILC		INCREMENT ILC BY NREP.	TT153710
01735 0361 00 0 02025	ACL	NREP		..	TT153720
01736 0621 00 0 02023	STA	ILC		..	TT153730
01737 0020 00 0 01653	TRA	ADR		RETURN TO CONTROL LOOP.	TT153740
01740 0074 00 4 02047	REG	TSX	(OPCD),4	NORMAL PATH, CONVERT WORD.	TT153750
01741 0602 00 2 02771	SLW	OUT+20,2		..	TT153770
01742 0560 00 1 00000	LDQ	**,1		CONVERT TO OCTAL.	TT153780
01743 0074 00 4 01260	TSX	OCT,4		..	TT153790
01744 0602 00 2 02772	SLW	OUT+21,2		INSERT.	TT153800
01745 -0600 00 2 02773	STQ	OUT+22,2		..	TT153810
					TT153820

TESTS FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
SECTION 5, SVCON, PMR, OCT, OCTADR, AND TABBLK.

01746 -2 00001 1 01776		TNX	FIN,1,1	COUNT WORDS CONVERTED.	TT153830
01747 2 00003 2 01660		TIX	LOOP1,2,3	COUNT WORDS THIS LINE.	TT153840
				ASSUME SINGLE SPACE FOR THIS LINE.	TT153850
01750 0560 00 0 03160	PPM	LDQ	=H	GET LINE COUNT.	TT153860
01751 0500 00 0 02022		CLA	PMCNT	COUNT 1 LINE.	TT153870
01752 0402 00 0 03126		SUB	=1	SKIP IF IT FITS.	TT153880
01753 0120 00 0 01756		TPL	*+3	SET TO EJECT.	TT153890
01754 0560 00 0 03146		LDQ	=H1	SET LINE COUNT.	TT153900
01755 0500 00 0 03135		CLA	=59	SAVE LINE COUNT.	TT153910
01756 0601 00 0 02022		STO	PMCNT	SET CARRIAGE CONTROL.	TT153920
01757 -0600 00 0 02745		STQ	OUT	PRINT THIS LINE.	TT153930
01760 0074 00 4 02407		TSX	WOT,4		TT153940
01761 0 00024 0 02745		PZE	OUT,0,20	..	TT153950
01762 -0500 00 0 02746		CAL	OUT+1	UPDATE WORD COUNT.	TT153960
01763 -0320 00 0 03150		ANA	=0070707070777	..	TT153970
01764 0361 00 0 03144		ACL	=0007070707C7600	..	TT153980
01765 -0320 00 0 03150		ANA	=0070707070777	..	TT153990
01766 -0130 00 0 00000		XCL		..	TT154000
01767 -0154 04 0 01207		CRQ	TABBLK,0,4	REMOVE LEADING ZEROES.	TT154010
01770 -0773 00 0 00014		RQL	12	BACK TO PROPER POSITION.	TT154020
01771 -0600 00 0 02746		STQ	OUT+1	INSERT.	TT154030
01772 -0500 00 0 02023		CAL	ILC	UPDATE ILC.	TT154040
01773 0361 00 0 03132		ACL	=6	..	TT154050
01774 0621 00 0 02023		STA	ILC	..	TT154060
01775 0020 00 0 01657		TRA	LOOP2	..	TT154070
01776 -2 00003 2 02004	FIN	TNX	*+6,2,3	IF LINE NOT FULL,	TT154080
01777 -0500 00 0 03160		CAL	=H	FILL IN LINE WITH BLANKS.	TT154090
02000 0602 00 2 02771		SLW	OUT+20,2	..	TT154100
02001 0602 00 2 02772		SLW	OUT+21,2	..	TT154110
02002 0602 00 2 02773		SLW	OUT+22,2	..	TT154120
02003 2 00003 2 02000		TIX	*-3,2,3	INDEX.	TT154130
02004 0560 00 0 03160		LDQ	=H	ASSUME SINGLE SPACE FOR LAST LINE.	TT154140
02005 0500 00 0 02022		CLA	PMCNT	GET LINE COUNT.	TT154150
02006 0402 00 0 03126		SUB	=1	COUNT 1 LINE.	TT154160
02007 0120 00 0 02012		TPL	*+3	SKIP IF IT FITS.	TT154170
02010 0560 00 0 03146		LDQ	=H1	SET TO EJECT.	TT154180
02011 0500 00 0 03135		CLA	=59	SET LINE COUNT.	TT154190
02012 0601 00 0 02022		STO	PMCNT	SAVE LINE COUNT.	TT154200
02013 -0600 00 0 02745		STQ	OUT	SET CARRIAGE CONTROL.	TT154210
02014 0074 00 4 02407		TSX	WOT,4	PRINT LAST LINE.	TT154220
02015 0 00024 0 02745		PZE	OUT,0,20	..	TT154230
02016 0774 00 4 00000	DX4	AXT	**+,4	RESTORE IRS.	TT154240
02017 0774 00 2 00000	DX2	AXT	**+,2	..	TT154250
02020 0774 00 1 00000	DX1	AXT	**+,1	..	TT154260
02021 0020 00 4 00002		TRA	2,4	RETURN.	TT154270
02022 0 00000 0 00055	PMCNT	PZE	45	STORAGE FOR LINE COUNT.	TT154280
02023 0 00000 0 00000	ILC	PZE		POST MORTEM STORAGE.	TT154290
02024 0 00000 0 00000	LWORD	PZE		..	TT154300
02025 0 00000 0 00000	NREP	PZE		..	TT154310
02026 0 00000 0 00000	CNREP	PZE		..	TT154320
02027 006060606060	WREP	BC1	9,0	.. FOLLOWING 00000	TT154330
02030 606060606060					TT154340
02031 606060606060					
02032 606060606060					

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
SECTION 5, SVCON, PMR, OCT, OCTADR, AND TABBLK.

02033	606060606060				
02034	606060606060				
02035	333360264643				
02036	434666314527				
02037	600000000000				
02040	602325434362	BCI	7, CELLS ALL CONTAIN 0000000000000000 ..		TT154350
02041	602143436023				
C2042	464563213145				
02043	600000000000				
02044	000000000000				
02045	000000000000				
02046	603333606060				

		SPACE	2 (OPCD), FIND MNEMONIC OPERATION CODE.		TT154360
					TT154370
					TT154380
02047	0634 00 2 02131	(OPCD)	SXA AR2,2	SAVE IR2.	TT154390
02050	0634 00 1 02132	SXA	AR1,1	SAVE IR1.	TT154400
02051	0774 00 1 00000	AXT	0,1	SET IR1.	TT154410
02052	-0320 00 0 03165	ANA	=0777700000000	MASK OPCD.	TT154420
02053	0100 00 0 02125	TZE	OPFND	HTR EXIT.	TT154430
02054	0602 00 0 02135	SLW	OPBIN	SAVE OPCD.	TT154440
02055	0630 00 0 02134	STP	PRE	SAVE PREFIX.	TT154450
02056	0520 00 0 02134	ZET	PRE	IF NON-ZERO, TYPE A.	TT154460
02057	0020 00 0 02117	TRA	TYPEA	..	TT154470
02060	0534 00 2 02406	LXA	SIZE,2	SET IR2.	TT154480
02061	0020 00 2 02116	TRA	LOWER,2	BEGIN SEARCH.	TT154490
02062	-3 77540 1 02066	SRCH1	TXL SRCH2,1,-NUM	CHECK RANGE.	TT154500
02063	-0500 00 1 02146	CAL	TABL,1	GET TABLE ENTRY.	TT154510
02064	-0320 00 0 03165	ANA	=0777700000000	MASK OPCD.	TT154520
02065	-0340 00 0 02135	LAS	OPBIN	COMPARE WITH OPBIN.	TT154530
02066	1 77776 2 02115	SRCH2	TXI RAISE,2,-2	BIGGER, GO TO RAISE INDEX.	TT154540
02067	0020 00 0 02125	TRA	OPFND	FOUND, EXIT WITH INDEX.	TT154550
02070	1 77776 2 02116	TXI	LOWER,2,-2	SMALLER, GO TO LOWER INDEX.	TT154560
02071	1 00400 1 02062	TXI	SRCH1,1,+256	TABLE, POWER OF TWO INCREMENTS.	TT154570
02072	1 77400 1 02062	TXI	SRCH1,1,-256	..	TT154580
02073	1 00200 1 02062	TXI	SRCH1,1,+128	..	TT154590
02074	1 77600 1 02062	TXI	SRCH1,1,-128	..	TT154600
02075	1 00100 1 02062	TXI	SRCH1,1,+64	..	TT154610
02076	1 77700 1 02062	TXI	SRCH1,1,-64	..	TT154620
02077	1 00040 1 02062	TXI	SRCH1,1,+32	..	TT154630
02100	1 77740 1 02062	TXI	SRCH1,1,-32	..	TT154640
02101	1 00020 1 02062	TXI	SRCH1,1,+16	..	TT154650
02102	1 77760 1 02062	TXI	SRCH1,1,-16	..	TT154660
02103	1 00010 1 02062	TXI	SRCH1,1,+8	..	TT154670
02104	1 77770 1 02062	TXI	SRCH1,1,-8	..	TT154680
02105	1 00004 1 02062	TXI	SRCH1,1,+4	..	TT154690
02106	1 77774 1 02062	TXI	SRCH1,1,-4	..	TT154700
02107	1 00002 1 02062	TXI	SRCH1,1,+2	..	TT154710
02110	1 77776 1 02062	TXI	SRCH1,1,-2	..	TT154720
02111	1 00001 1 02062	TXI	SRCH1,1,+1	..	TT154730
02112	1 77777 1 02062	TXI	SRCH1,1,-1	..	TT154740
02113	0020 00 0 02117	TRA	TYPEA	NOT FOUND, TYPE A.	TT154750
					TT154760

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
 SECTION 5, SVCON, PMR, OCT, OCTADR, AND TABBLK.

02114	0020 00 0	02117	TRA	TYPEA	..	TT154770
02115	0522 00 2	02115	RAISE XEC	*,2	RAISE INDEX.	TT154780
02116	0522 00 2	02116	LOWER XEC	*,2	LOWER INDEX.	TT154790
						TT154800
02117	0560 00 0	02135	TYPEA LDQ	OPBIN	TYPE A, PICKUP MNEMONIC.	TT154810
02120	-0754 00 0	00000	PXD	0,0	..	TT154820
02121	-0763 00 0	00003	LGL	3	..	TT154830
02122	0734 00 1	00000	PAX	0,1	..	TT154840
02123	-0500 00 1	02145	CAL	LSTA+7,1	PICKUP MNEMONIC.	TT154850
02124	0020 00 0	02131	TRA	AR2	GO TO EXIT.	TT154860
						TT154870
02125	-0500 00 1	02146	OPFND CAL	TABL,1	OPERATION FOUND, PICKUP WORD.	TT154880
02126	-0320 00 0	03140	ANA	=0000000777777	MASK OUT JUNK.	TT154890
02127	0767 00 0	00006	ALS	6	SHIFT LEFT ONE CHARACTER.	TT154900
02130	-0501 00 0	03156	ORA	=H 000	INSERT BLANKS.	TT154910
02131	0774 00 2	00000	AR2	AXT	RESTORE IRS.	TT154920
02132	0774 00 1	00000	ARI	AXT	..	TT154930
02133	0020 00 4	00001	TRA	1,4	RETURN TO CALLER.	TT154940
						TT154950
02134	0 00000 0	00000	PRE PZE		PREFIX STORAGE FOR TYPE A TEST.	TT154960
02135	0 00000 0	00000	OPBIN PZE		STORAGE FOR BINARY OPCD.	TT154970

		SPACE	2			TT154980
				TABLES FOR (OPCD).		TT154990
						TT155000
02136	606063674360	LSTA	BCI	1, TXL		TT155010
02137	606063456760		BCI	1, TNX		TT155020
02140	606C62635160		BCI	1, STR		TT155030
02141	606044712560		BCI	1, MZE		TT155040
02142	606063673060		BCI	1, TXH		TT155050
02143	606063316760		BCI	1, TIX		TT155060
02144	606063673160		BCI	1, TXI		TT155070
02145	606047712560		BCI	1, PZE		TT155080
						TT155090
02146	000000306351	TABL	VFD	012/0000,H24/0HTR	HTR	TT155100
02147	002000635121		VFD	012/0020,H24/0TRA	TRA	TT155110
02150	002100636351		VFD	012/0021,H24/0TTR	TTR	TT155120
02151	002200635123		VFD	012/0022,H24/0TRC	TRCA	TT155130
02152	002400635123		VFD	012/0024,H24/0TRC	TRCC	TT155140
02153	003000632526		VFD	012/0030,H24/0TEF	TEFA	TT155150
02154	003100632526		VFD	012/0031,H24/0TEF	TEFC	TT155160
02155	004000634350		VFD	012/0040,H24/0TLQ	TLQ	TT155170
02156	004100313121		VFD	012/0041,H24/0IIA	IIA	TT155180
02157	004200633146		VFD	012/0042,H24/0TIO	TIO	TT155190
02160	004300462131		VFD	012/0043,H24/0OAI	OAI	TT155200
02161	004400472131		VFD	012/0044,H24/0PAI	PAI	TT155210
02162	004600633126		VFD	012/0046,H24/0TIF	TIF	TT155220
02163	005100313151		VFD	012/0051,H24/0IIR	IIR	TT155230
02164	005400512663		VFD	012/0054,H24/0RFT	RFT	TT155240
02165	005500623151		VFD	012/0055,H24/0SIR	SIR	TT155250
02166	005600514563		VFD	012/0056,H24/0RNT	RNT	TT155260
02167	005700513151		VFD	012/0057,H24/0RIR	RIR	TT155270
02170	006000632346		VFD	012/0060,H24/0TCO	TCOA	TT155280
02171	006100632346		VFD	012/0061,H24/0TCO	TCOB	TT155290

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
SECTION 5, SVCON, PMR, OCT, OCTADR, AND TABBLK.

02172	006200632346	VFD	012/0062,H24/OTCO	TCOC	TT155300
02173	006300632346	VFD	012/0063,H24/OTCO	TCOD	TT155310
02174	007400636267	VFD	012/0074,H24/OTSX	TSX	TT155320
02175	010000637125	VFD	012/0100,H24/OTZE	TZE	TT155330
02176	011400236551	VFD	012/0114,H24/OCVR	CVR	TT155340
02177	012000634743	VFD	012/0120,H24/OTPL	TPL	TT155350
02200	013100672321	VFD	012/0131,H24/OXCA	XCA	TT155360
02201	014000634665	VFD	012/0140,H24/OTOV	TOV	TT155370
02202	016100635046	VFD	012/0161,H24/OTQO	TQO	TT155380
02203	016200635047	VFD	012/0162,H24/OTQP	TQP	TT155390
02204	020000444770	VFD	012/0200,H24/OMPY	MPY	TT155400
02205	020400654344	VFD	012/0204,H24/OVLM	VLM	TT155410
02206	022000246530	VFD	012/0220,H24/ODVH	DVH	TT155420
02207	022100246547	VFD	012/0221,H24/ODVP	DVP	TT155430
02210	022400652430	VFD	012/0224,H24/ODVH	DVH	TT155440
02211	022500652447	VFD	012/0225,H24/ODVP	DVP	TT155450
02212	024000262430	VFD	012/0240,H24/OFDH	FDH	TT155460
02213	024100262447	VFD	012/0241,H24/OFDP	FDP	TT155470
02214	026000264447	VFD	012/0260,H24/OFMP	FMP	TT155480
02215	030000262124	VFD	012/0300,H24/OFAD	FAD	TT155490
02216	030200266222	VFD	012/0302,H24/OFSB	FSB	TT155500
02217	030400262144	VFD	012/0304,H24/OFAM	FAM	TT155510
02220	030600266244	VFD	012/0306,H24/OFSM	FSM	TT155520
02221	032000214562	VFD	012/0320,H24/0ANS	ANS	TT155530
02222	032200255121	VFD	012/0322,H24/0ERA	ERA	TT155540
02223	034000232162	VFD	012/0340,H24/OCAS	CAS	TT155550
02224	036100212343	VFD	012/0361,H24/0ACL	ACL	TT155560
02225	040000212424	VFD	012/0400,H24/0ADD	ADD	TT155570
02226	040100212444	VFD	012/0401,H24/0ADM	ADM	TT155580
02227	040200626422	VFD	012/0402,H24/0SUB	SUB	TT155590
02230	042000304751	VFD	012/0420,H24/0HPR	HPR	TT155600
02231	044000313162	VFD	012/0440,H24/0IIS	IIS	TT155610
02232	044100432431	VFD	012/0441,H24/0LDI	LDI	TT155620
02233	044200466231	VFD	012/0442,H24/0OSI	OSI	TT155630
02234	044400462663	VFD	012/0444,H24/0OFT	OFT	TT155640
02235	044500513162	VFD	012/0445,H24/0RIS	RIS	TT155650
02236	044600464563	VFD	012/0446,H24/0ONT	ONT	TT155660
02237	046000432421	VFD	012/0460,H24/0LDA	LDA	TT155670
02240	050000234321	VFD	012/0500,H24/0CLA	CLA	TT155680
02241	050200234362	VFD	012/0502,H24/0CLS	CLS	TT155690
02242	052000712563	VFD	012/0520,H24/0ZET	ZET	TT155700
02243	052200672523	VFD	012/0522,H24/0XEC	XEC	TT155710
02244	053400436721	VFD	012/0534,H24/0LXA	LXA	TT155720
02245	053500432123	VFD	012/0535,H24/0LAC	LAC	TT155730
02246	054000512330	VFD	012/0540,H24/0RCH	RCHA	TT155740
02247	054100512330	VFD	012/0541,H24/0RCH	RCHC	TT155750
02250	054400432330	VFD	012/0544,H24/0LCH	LCHA	TT155760
02251	054500432330	VFD	012/0545,H24/0LCH	LCHC	TT155770
02252	056000432450	VFD	012/0560,H24/0LDQ	LDQ	TT155780
02253	056200435131	VFD	012/0562,H24/0LRI	LRI	TT155790
02254	056400254522	VFD	012/0564,H24/0ENB	ENB	TT155800
02255	060000626371	VFD	012/0600,H24/0STZ	STZ	TT155810
02256	060100626346	VFD	012/0601,H24/0STO	STO	TT155820
02257	060200624366	VFD	012/0602,H24/0SLW	SLW	TT155830
02260	060400626331	VFD	012/0604,H24/0STI	STI	TT155840

TESTS FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
SECTION 5, SVCON, PMR, OCT, OCTADR, AND TABBLK.

02261	062100626321	VFD	012/0621,H24/OSTA	STA	TT155850
02262	062200626324	VFD	012/0622,H24/OSTD	STD	TT155860
02263	062500626363	VFD	012/0625,H24/OSTT	STT	TT155870
02264	063000626347	VFD	012/0630,H24/OSTP	STP	TT155880
02265	063400626721	VFD	012/0634,H24/OSXA	SXA	TT155890
02266	064000622330	VFD	012/0640,H24/OSCH	SCHA	TT155900
02267	064100622330	VFD	012/0641,H24/OSCH	SCHA	TT155910
02270	070000234770	VFD	012/0700,H24/OCPY	CPY	TT155920
02271	073400472167	VFD	012/0734,H24/OPAX	PAX	TT155930
02272	073700472123	VFD	012/0737,H24/OPAC	PAC	TT155940
02273	075400476721	VFD	012/0754,H24/OPXA	PXA	TT155950
02274	076000476225	VFD	012/0760,H24/OPSE	PSE	TT155960
02275	076100454647	VFD	012/0761,H24/ONOP	NOP	TT155970
02276	076200512462	VFD	012/0762,H24/ORDS	RDS	TT155980
02277	076300434362	VFD	012/0763,H24/OLLS	LLS	TT155990
02300	076400226251	VFD	012/0764,H24/OBSR	BSR	TT156000
02301	076500435162	VFD	012/0765,H24/OLRS	LRS	TT156010
02302	076600665162	VFD	012/0766,H24/OWRS	WRS	TT156020
02303	076700214362	VFD	012/0767,H24/OALS	ALS	TT156030
02304	077000662526	VFD	012/0770,H24/OWEF	WEF	TT156040
02305	077100215162	VFD	012/0771,H24/OARS	ARS	TT156050
02306	077200512566	VFD	012/0772,H24/OREW	REW	TT156060
02307	077400216763	VFD	012/0774,H24/OAXT	AXT	TT156070
02310	077600622445	VFD	012/0776,H24/OSDN	SDN	TT156080
02311	402100254563	VFD	012/4021,H24/OENT	ESNT	TT156090
02312	402200635123	VFD	012/4022,H24/OTRC	TRCB	TT156100
02313	402400635123	VFD	012/4024,H24/OTRC	TRCD	TT156110
02314	403000632526	VFD	012/4030,H24/OTEF	TEFB	TT156120
02315	403100632526	VFD	012/4031,H24/OTEF	TEFD	TT156130
02316	404200513121	VFD	012/4042,H24/ORIA	RIA	TT156140
02317	404600473121	VFD	012/4046,H24/OPIA	PIA	TT156150
02320	405100313143	VFD	012/4051,H24/OIIL	IIL	TT156160
02321	405400432663	VFD	012/4054,H24/OLFT	LFT	TT156170
02322	405500623143	VFD	012/4055,H24/OSIL	SIL	TT156180
02323	405600434563	VFD	012/4056,H24/OLNT	LNT	TT156190
02324	405700513143	VFD	012/4057,H24/ORIL	RIL	TT156200
02325	406000632345	VFD	012/4060,H24/OTCN	TCNA	TT156210
02326	406100632345	VFD	012/4061,H24/OTCN	TCNB	TT156220
02327	406200632345	VFD	012/4062,H24/OTCN	TCNC	TT156230
02330	406300632345	VFD	012/4063,H24/OTCN	TCND	TT156240
02331	410000634571	VFD	012/4100,H24/OTNZ	TNZ	TT156250
02332	411400232150	VFD	012/4114,H24/OCAQ	CAQ	TT156260
02333	412000634431	VFD	012/4120,H24/OTMI	TMI	TT156270
02334	413000672343	VFD	012/4130,H24/OXCL	XCL	TT156280
02335	414000634546	VFD	012/4140,H24/OTNO	TNO	TT156290
02336	415400235150	VFD	012/4154,H24/OCRQ	CRQ	TT156300
02337	420000444751	VFD	012/4200,H24/OMPR	MPR	TT156310
02340	426000642644	VFD	012/4260,H24/OUFM	UFM	TT156320
02341	430000642621	VFD	012/4300,H24/OUFA	UFA	TT156330
02342	430200642662	VFD	012/4302,H24/OUFS	UFS	TT156340
02343	430400642144	VFD	012/4304,H24/OUAM	UAM	TT156350
02344	430600646244	VFD	012/4306,H24/OUSM	USM	TT156360
02345	432000214521	VFD	012/4320,H24/OANA	ANA	TT156370
02346	434000432162	VFD	012/4340,H24/OLAS	LAS	TT156380
02347	440000622244	VFD	012/4400,H24/OSBM	SBM	TT156390

TESTS FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
SECTION 5, SVCON, PMR, OCT, OCTADR, AND TABBLK.

02350	450000232143	VFD	012/4500,H24/OCAL	CAL	TT)56400
02351	450100465121	VFD	012/4501,H24/OORA	ORA	TT)56410
02352	452000457163	VFD	012/4520,H24/ONZT	NZT	TT)56420
02353	453400436724	VFD	012/4534,H24/OLXD	LXD	TT)56430
02354	453500432423	VFD	012/4535,H24/OLDC	LDC	TT)56440
02355	454000512330	VFD	012/4540,H24/ORCH	RCHB	TT)56450
02356	454100512330	VFD	012/4541,H24/ORCH	RCHD	TT)56460
02357	454400432330	VFD	012/4544,H24/OLCH	LCHB	TT)56470
02360	454500432330	VFD	012/4545,H24/OLCH	LCHD	TT)56480
02361	456400434731	VFD	012/4564,H24/OLPI	LPI	TT)56490
02362	460000626350	VFD	012/4600,H24/OSTQ	STQ	TT)56500
02363	460100625131	VFD	012/4601,H24/OSRI	SRI	TT)56510
02364	460200465162	VFD	012/4602,H24/0ORS	ORS	TT)56520
02365	460400624731	VFD	012/4604,H24/OSPI	SPI	TT)56530
02366	462000624350	VFD	012/4620,H24/OSLQ	SLQ	TT)56540
02367	462500626343	VFD	012/4625,H24/OSTL	STL	TT)56550
02370	463400626724	VFD	012/4634,H24/OSXD	SXD	TT)56560
02371	464000622330	VFD	012/4640,H24/OSCH	SCHB	TT)56570
02372	464100622330	VFD	012/4641,H24/OSCH	SCHD	TT)56580
02373	470000232124	VFD	012/4700,H24/OCAD	CAD	TT)56590
02374	473400472467	VFD	012/4734,H24/OPDX	PDX	TT)56600
02375	473700472423	VFD	012/4737,H24/OPDC	PDC	TT)56610
02376	475400476724	VFD	012/4754,H24/OPXD	PXD	TT)56620
02377	476000446225	VFD	012/4760,H24/OMSE	MSE	TT)56630
02400	476300432743	VFD	012/4763,H24/OLGL	LGL	TT)56640
02401	476400226226	VFD	012/4764,H24/OBSF	BSF	TT)56650
02402	476500432751	VFD	012/4765,H24/OLGR	LGR	TT)56660
02403	477200516445	VFD	012/4772,H24/0RUN	RUN	TT)56670
02404	477300515043	VFD	012/4773,H24/0RQL	RQL	TT)56680
02405	477400216723	VFD	012/4774,H24/0AXC	AXC	TT)56690
02406	ENTBL	BSS	0		TT)56700
02406	0 77540 0 00022	SIZE	PZE	18,,,-NUM	TT)56710
		NB		ADDRESS OF SIZE IS (2*E+2), WHERE E IS A NUMBER SUCH THAT (2**E).GE.(NUMBER OF ENTRIES IN TABLE).G.(2**((E-1))	TT)56730
				DECREMENT OF SIZE IS COMPLEMENT OF TABLE LENGTH.	TT)56740
					TT)56750
					TT)56760
00240	NUM	EQU	ENTBL-TABL	NUMBER IN OP TABLE.	TT)56770

TESTS FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
SECTION 6, INPUT/OUTPUT SUBROUTINES.

134

	TTL	SECTION 6, INPUT/OUTPUT SUBROUTINES. BUFFERED WOT, CALLING SEQUENCE,				TTI60000
		TSX \$WOT,4 PZE FIRST,T,LAST	OR	TSX \$WOT,4 PZE FIRST,T,N		TTI60010 TTI60020 TTI60030 TTI60040 TTI60050 TTI60060 TTI60070 TTI60080 TTI60090 TTI60100 TTI60110 TTI60120 TTI60130 TTI60140 TTI60150 TTI60160 TTI60170 TTI60180 TTI60190 TTI60200 TTI60210 TTI60220 TTI60230 TTI60240 TTI60250 TTI60260 TTI60270 TTI60280 TTI60290 TTI60300 TTI60310 TTI60320 TTI60330 TTI60340 TTI60350 TTI60360 TTI60370 TTI60380 TTI60390 TTI60400 TTI60410 TTI60420 TTI60430 TTI60440 TTI60450 TTI60460 TTI60470 TTI60480 TTI60490 TTI60500 TTI60510 TTI60520 TTI60530 TTI60540
		IF T IS NON-ZERO OR IF SW5 IS DOWN, PRINT ALSO. WRITES ONLY FIRST 22 WORDS ON TAPE.				
02407	0634 00 4 02442	WOT	SXA	WTX4,4	SAVE IR4.	
02410	0060 00 0 02410		TCUA	*	WAIT FOR DSC A.	
02411	-0760 00 0 01000		ETTA		CHECK FOR ECT CHN A.	
02412	0020 00 0 02452		TRA	ETA	EOT, EXIT.	
02413	-0500 00 4 00001		CAL	1,4	GET CONTROL WORD.	
02414	0625 00 0 02451		STT	WTTAG	SAVE TAG FOR DECISION TO PRINT.	
02415	0734 00 4 00000		PAX	0,4	FIRST TC IR4.	
02416	-0634 00 4 02432		SXD	WTTXI,4	SAVE FOR BUFFERING.	
02417	-0634 00 4 02422		SXD	WTTIX,4	SAVE FOR FINDING N.	
02420	-0734 00 4 00000		PDX	0,4	N OR LAST TO IR4.	
02421	1 00001 4 02422		TXI	*+1,4,1	PLUS 1.	
02422	2 00000 4 02424	WTTIX	TXI	*+2,4,**	IS IT N OR LAST.	
02423	1 77777 4 02424		TXI	*+1,4,-1	N IN IR4.	
02424	-3 00026 4 02426		TXL	*+2,4,22	N .LE. 22.	
02425	0774 00 4 00026		AXT	22,4	N = 22.	
02426	-0634 00 4 02450		SXD	WTCOM,4	SAVE FOR DSC COMMAND.	
02427	1 02715 4 02430		TXI	*+1,4,BUFF	FORM BUFF+N.	
02430	0634 00 4 02436		SXA	WTSLW,4	SAVE FOR BUFFERING.	
02431	-0534 00 4 02450		LXD	WTCOM,4	N IN IR4.	
02432	1 00000 4 02433	WTTXI	TXI	*+1,4,**	FORM FIRST+N.	
02433	0634 00 4 02435		SXA	WTCOM,4	SAVE FOR BUFFERING.	
02434	-0534 00 4 02450		LXD	WTCOM,4	N IN IR4.	
02435	-0500 00 4 00000	WTCAL	CAL	**,4	MOVE TO BUFFER.	
02436	0602 00 4 00000	WTSLW	SLW	**,4	..	
02437	2 00001 4 02435		TI	*-2,4,1	..	
02440	0766 00 0 01203		WTDA	3	SELECT OUTPUT TAPE.	
02441	0540 00 0 02450		RCHA	WTCOM	LOAD TO WRITE OUT BUFFER.	
02442	0774 00 4 00000	WTX4	AXT	**,4	RESTORE IR4.	
02443	0520 00 0 02451		ZET	WTTAG	WAS THE TAG ZERO.	
02444	0020 00 0 02520		TRA	PRINT	NO, THEN PRINT ALSO.	
02445	0760 00 0 00165		SWT	5	ZERO TAG, BUT CHECK SW5.	
02446	0020 00 4 00002		TRA	2,4	UP, DON'T PRINT.	
02447	0020 00 0 02520		TRA	PRINT	DOWN, PRINT ALSO.	
02450	0 00000 0 02715	WTCOM	I OCD	BUFF,0,**	OUTPUT COMMAND, N IN DECREMENT.	
02451	0 00000 0 00000		WTAG	PZE 0,0,0	STORAGE FOR TAG.	
02452	-0764 00 0 01202	ETA	BSFA	2	END OF TAPE A3, SET FOR RESTART.	
02453	-0764 00 0 02204		BSFB	4	REMOVE BINARY OUTPUT.	
02454	-0764 00 0 02204		BSFB	4	..	
02455	0774 00 1 00012		AXT	10,1	10 CLOSE COMMENTS.	
02456	0074 00 4 02407		TSX	WOT,4	CLOSE COMMENT.	
02457	0 00003 0 01077		PZE	ENDTP,0,3	..	
02460	0074 00 4 02407		TSX	WOT,4	CHANNEL 4 SKIP.	
02461	0 00001 0 03147		PZE	=H4 ,0,1	..	
02462	0770 00 0 01203		WEFA	3	END OF FILE MARK.	

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
SECTION 6, INPUT/OUTPUT SUBROUTINES.

02463	2 00001 1 02456	TIX	*-5,1,1	COUNT 10 TIMES.	TT160550
02464	-0772 00 0 01203	RUNA	3	THEN RUN A3.	TT160560
02465	0441 00 0 03125	LDI	*0	CLEAR INDICATORS.	TT160570
02466	0760 00 0 01000	BTAA		TURN OFF BOT LIGHT.	TT160580
02467	0761 00 0 00000	NOP		..	TT160590
02470	0074 00 4 02520	TSX	PRINT,4	COMMENT, AND STOP.	TT160600
02471	-0 00022 0 02476	MZE	WEOTA3,0,18	..	TT160610
02472	0760 00 0 01000	BTAA		CHECK FOR BEGINNING OF TAPE.	TT160620
02473	0020 00 0 00765	TRA	DOOR	BOT, GO RESTART.	TT160630
02474	-0764 00 0 01203	BSFA	3	NOT BOT, BACKSPACE TILL THERE.	TT160640
02475	0020 00 0 02472	TRA	*-3	THEN TRY AGAIN.	TT160650
02476	002545246046	WEOTA3 BCI		9,0END OF TAPE MARK ENCOUNTERED ON TAPE A3, TAPE CLOSED.	TT160660
02477	266063214725				TT160670
02500	604421514260				TT160680
02501	254523466445				
02502	632551252460				
02503	464560632147				
02504	256021037360				
02505	632147256023				
02506	434662252433				
02507	602330214527	BCI		9, CHANGE TAPE AND PRESS START TO RESTART THIS JOB.	TT160690
02510	256063214725				
02511	602145246047				
02512	512562626062				
02513	632151636063				
02514	466051256263				
02515	215163606330				
02516	316260414622				
02517	336060606060				

SPACE	2				TT160700
		BUFFERED PRINT, CALLING SEQUENCE,			TT160710
		TSX \$PRINT,4 OR	TSX \$PRINT,4		TT160720
		PRE FIRST,T,LAST	PRE FIRST,T,N		TT160730
					TT160740
					TT160750
		RECOGNIZES BLANK, 0, AND 1 AS CARRIAGE CONTROL (OTHER			TT160760
		CARRIAGE CONTROLS DON'T WORK TOO WELL), OTHERWISE,			TT160770
		SINGLE SPACE. PRINTS ONLY 20 WORDS, AND T IS IGNORED.			TT160780
		PRE=PZE, NORMAL RETURN (2,4), PRE=MZE, SPACE 0.1 PAGE,			TT160790
		LIGHT UP CONSOLE, AND STOP (HPR -1,7,63). RESTART			TT160800
		RETURNS (2,4).			TT160810
02520	0634 00 4 02642	PRINT SXA	PR4,4	SAVE IRS.	TT160820
02521	0634 00 2 02643	SXA	PR2,2	..	TT160830
02522	0634 00 1 02644	SXA	PR1,1	..	TT160840
02523	0600 00 0 00005	STZ	5	RESET INTERVAL TIMER.	TT160850
02524	-0061 00 0 02526	TCNT	*+2	IF TAPE TIMER IN USE,	TT160860
02525	-0540 00 0 00261	RCHT	QUIT	RESET TAPE TIMER.	TT160870
02526	-0500 00 4 00001	CAL	1,4	GET CONTROL WORD.	TT160880
02527	0734 00 4 00000	PAX	0,4	FIRST TO IR4.	TT160890
02530	-0634 00 4 02541	SXD	PTXI,4	SAVE FOR PICKUP.	TT160900
					TT160910

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
SECTION 6, INPUT/OUTPUT SUBROUTINES.

02531 -0634 00 4 02534	SXD	*+3,4	SAVE FOR FINDING N.	TTI60920	
02532 -0734 00 4 00000	PDX	0,4	N OR LAST TO IR4.	TTI60930	
02533 1 00001 4 02534	TXI	*+1,4,1	PLUS 1.	TTI60940	
02534 2 00000 4 02536	TXI	*+2,4,**	IS IT N OR LAST.	TTI60950	
02535 1 77777 4 02536	TXI	*+1,4,-1	N IN IR4.	TTI60960	
02536 -3 00024 4 02540	TXL	*+2,4,20	IS N .LE. 20.	TTI60970	
C2537 0774 00 4 00024	AXT	20,4	N = 20.	TTI60980	
02540 0634 00 4 02614	SXA	WDCNT,4	SAVE WDCNT.	TTI60990	
02541 1 00000 4 02542	PTXI TXI	*+1,4,**	COMPUTE LAST+1.	TTI61000	
02542 0634 00 4 02616	SXA	LDQ,4	INSERT IN PICKUP.	TTI61010	
02543 0534 00 4 02614	LXA	WDCNT,4	N IN IR4.	TTI61020	
02544 0522 00 0 02616	XEC	LDQ	PICKUP FIRST WORD.	TTI61030	
02545 -0754 00 0 00000	PXD	0,C	GET FIRST CHARACTER,	TTI61040	
02546 -0763 00 0 00006	LGL	6	FOR CARRIAGE CONTROL.	TTI61050	
02547 -0340 00 0 03126	LAS	=1	COMPARE WITH 1.	TTI61060	
02550 -0500 00 0 03127	CAL	=2	C.C. .G. 1, SINGLE SPACE.	TTI61070	
02551 0020 00 0 02552	TRA	*+1	C.C. .E. 1, NEW PAGE.	TTI61080	
02552 0737 00 2 00000	PAC	0,2	C.C. .E. 0, DOUBLE SPACE.	TTI61090	
02553 -0500 00 2 02660	CAL	SPRS,2	PICKUP SPR,	TTI61100	
02554 0602 00 0 02633	SLW	SPRA	AND INSERT AFTER SELECT.	TTI61110	
				TTI61120	
02555 0774 00 4 00005	AXT	5,4	SET FOR FIVE CHARACTERS, FIRST WORD.	TTI61130	
02556 -0500 00 0 03151	CAL	=02000000C0000	COLUMN MARK, SKIP 1ST COLUMN.	TTI61140	
				TTI61150	
02557 0774 00 1 00030	HRI	AXT	24,1	CLEAR CARD IMAGE.	TTI61160
02560 0600 00 1 02715	STZ	CARDIM+24,1	..	TTI61170	
02561 0600 00 1 02716	STZ	CARDIM+25,1	..	TTI61180	
02562 2 00002 1 02560	TXI	*-2,1,2	..	TTI61190	
02563 0774 00 2 00001	AXT	1,2	SET MARK FOR LEFT HALF.	TTI61200	
02564 0602 00 0 02657	PRLP	SPACE	2		TTI61210
02565 -0754 00 0 00000		SLW	PRCOL	SAVE COLUMN MARKER.	TTI61220
02566 -0763 00 0 00006		PXD	0,0	GET NEXT CHARACTER.	TTI61230
02567 0767 00 0 00001		LGL	6	..	TTI61240
02570 0774 00 1 00000		ALS	1	DOUBLE IT,	TTI61250
02571 -0500 00 0 02657		PAX	0,1	AND PLACE IN IR1.	TTI61260
		CAL	PRCOL	GET COLUMN MARKER.	TTI61270
				TTI61280	
02572 -3 00037 1 02606	ZONE	TXL	DIG,1,31	IF NO ZONE, SKIP.	TTI61290
02573 -3 00137 1 02575		TXL	*+2,1,95	IGNORE BLANK.	TTI61300
02574 -3 00140 1 02612		TXL	RLOOP,1,96	..	TTI61310
02575 3 00077 1 02600		TXH	*+3,1,63	CHECK FOR 12 ZONE.	TTI61320
02576 -0602 00 2 02714		ORS	CARDIM+23,2	YES, OR IT IN.	TTI61330
02577 1 77740 1 02605		TXI	TZEDG,1,-32	REMOVE ZONE, AND CHECK DIGIT.	TTI61340
02600 3 00137 1 02603		TXH	*+3,1,95	CHECK FOR 11 ZONE.	TTI61350
C2601 -0602 00 2 02712		ORS	CARDIM+21,2	YES, OR IT IN.	TTI61360
02602 1 77700 1 02605		TXI	TZEDG,1,-64	REMOVE ZONE AND CHECK DIGIT.	TTI61370
02603 -0602 00 2 02710		ORS	CARDIM+19,2	OR IN 0 ZONE.	TTI61380
02604 1 77640 1 02605		TXI	*+1,1,-96	REMOVE ZONE, AND CHECK DIGIT.	TTI61390
02605 -3 00000 1 02612	TZEDG	TXL	RLOOP,1,0	IGNORE 0 DIGIT WITH A ZONE.	TTI61400
				TTI61410	
02606 -3 00022 1 02611	CIG	TXL	*+3,1,18	CHECK FOR (8-N) CHARACTER.	TTI61420
02607 -0602 00 2 02670		ORS	CARDIM+3,2	YES, OR IN 8.	TTI61430
02610 1 77760 1 02611		TXI	*+1,1,-16	REMOVE 8.	TTI61440

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
SECTION 6, INPUT/OUTPUT SUBROUTINES.

02611	-0602 00 3 02710	ORS	CARDIM+19,3	OR IN DIGIT.	TT)61450
02612	0771 00 0 00001	RLOOP	ARS	1 SHIFT COLUMN MARKER.	TT)61460
02613	2 00001 4 02564		TIX	PRLP,4,1 COUNT CHARACTERS PER WORD.	TT)61470
02614	0774 00 4 00000	WDCNT	AXT	**,4 THIS WORD DONE, RESTORE WORD COUNT.	TT)61480
02615	-2 00001 4 02625		TNX	PNOW,4,1 INDEX, AND EXIT WHEN COUNT EXHAUSTED.	TT)61490
02616	0560 00 4 00000	LDQ	LDQ	**,4 PICKUP NEXT WORD.	TT)61500
02617	0634 00 4 02614		SXA	WDCNT,4 SAVE WORD COUNT.	TT)61510
02620	0774 00 4 00006		AXT	6,4 RESTORE CHARACTER COUNT.	TT)61520
02621	-0100 00 0 02564		TNZ	PRLP RETURN IF MORE TO THIS HALF.	TT)61530
02622	-3 00000 2 02625		TXL	PNOW,2,0 IF RIGHT HALF DONE, GO PRINT.	TT)61540
02623	-0500 00 0 03153		CAL	=04000000000000 SET COLUMN MARKER.	TT)61550
02624	1 77777 2 02564		TXI	PRLP,2,-1 SET IR2 FOR RIGHT HALF AND RETURN.	TT)61560
02625	0774 00 1 00030	PNOW	AXT	24,1 MOVE CARDIM TO BUFF,	TT)61570
02626	0060 00 0 02626		TCOA	* WHEN DSCA IS FREE.	TT)61580
02627	-0500 00 1 02715		CAL	CARDIM+24,1 ..	TT)61590
02630	0602 00 1 02745		SLW	BUFF+24,1 ..	TT)61600
02631	2 00001 1 02627		TIX	*-2,1,1 ..	TT)61610
02632	0766 00 0 01361		WPRA		TT)61620
02633	0000 60 0 02633	SPRA	HTR*	*	TT)61630
02634	0540 00 0 02664		RCHA	PRCOM SPACE CARRIAGE.	TT)61640
02635	-3 00001 4 02642		TXL	PR4,4,1 AND LOAD WITH THIS LINE.	TT)61650
02636	-0500 00 0 02663		CAL	C(IR4) .LE. 1 IFF WDCNT EXHAUSTED.	TT)61660
02637	0602 00 0 02633		NOSPC	MORE TO DO, SET SPR.	TT)61670
02640	-0500 00 0 03153		SLW	SPRA ..	TT)61680
02641	0020 00 0 02557		CAL	=04000000000000 GET COLUMN MARKER.	TT)61690
02642	0774 00 4 00000	PR4	AXT	1,4 GO BACK AND DO IT AGAIN.	TT)61700
02643	0774 00 2 00000	PR2	AXT	2,4 RESTORE IRS.	TT)61710
02644	0774 00 1 00000	PR1	AXT	*,2 ..	TT)61720
02645	0500 00 4 00001		CLA	1,4 GET CONTROL WORD AGAIN.	TT)61730
02646	0120 00 4 00002		TPL	2,4 IF PLUS, NORMAL EXIT.	TT)61740
02647	0766 00 0 01361	WPRA			TT)61750
02650	0760 00 0 01364	SPRA	4	STOP COMMAND, SPACE PRINTER.	TT)61760
02651	0760 00 0 01363	SPRA	3	..	TT)61770
02652	0502 00 0 03125	CLS	=0	SET S BIT TO ONE.	TT)61780
02653	0760 00 0 00006	COM		SET AC TO ALL ONES.	TT)61790
02654	0560 00 0 03166	LDQ	=07777777777777	LIGHT UP MQ.	TT)61800
02655	0420 00 7 77777	HPR	-1,7	STOP.....	TT)61810
02656	0020 00 4 00002	TRA	2,4	AND RETURN...	TT)61820
				STORAGE AND CONSTANTS FOR PRINT.	TT)61830
02657	0 00000 0 00000	PRCOL	PZE	COLUMN MARKER STCORAGE.	TT)61840
02660	0760 00 0 01364	SPRS	SPRA	4 CARRIAGE CONTROL, 0	TT)61850
02661	0760 00 0 01361		SPRA	1 MAINTAIN THIS 1	TT)61860
02662	0761 00 0 00000		NOP	ORDER. 2	TT)61870
02663	0760 00 0 01371	NOSPC	SPRA	9 RIGHT HALF SPRA.	TT)61880
02664	0 00030 0 02715	PRCOM	IOCD	BUFF,0,24 PRINT COMMAND.	TT)61890
02520	NPRINT SYN	PRINT		EXTERNAL NAME FOR PRINT.	TT)61900

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
 SECTION 6, INPUT/OUTPUT SUBROUTINES.

	SPACE	2		TT161990	
		STORAGE AREA.		TT162000	
				TT162010	
02665	CARDIM	BSS	24	CARD IMAGE BUFFER FOR PRINT.	TT162020
02715	BUFF	BSS	24	OUTPUT BUFFER FOR WOT.	TT162030
02745	OUT	BSS	22	OUTPUT BUFFER FOR POST MORTEM.	TT162040
				TT162050	
	00036	NSYM	EQU 30	30 NAMES ALLOWED IN MOVIE).	TT162060
02773		NAME	BSS NSYM	SUBROUTINE NAME TABLE.	TT162070
03031		ORIGIN	BSS NSYM	SUBROUTINE ORIGIN TABLE.	TT162080
03067		ENTRY	BSS NSYM	SUBROUTINE ENTRY POINT TABLE.	TT162090
			END	TT162100	
				TT162110	

## LITERALS

03125	000000000000
03126	000000000001
03127	000000000002
03130	000000000003
03131	000000000005
03132	000000000006
03133	000000000012
03134	000000000072
03135	000000000073
03136	000000000454
03137	000000602646
03140	000000777777
03141	000017000000
03142	004623632143
03143	006060606060
03144	007070707600
03145	014623632143
03146	016060606060
03147	046060606060
03150	070707070777
03151	200000000000
03152	377700000000
03153	400000000000
03154	462660000000
03155	600073C07300
03156	606000000060
03157	606060604000
03160	606060606060
03161	632562636260
03162	700000000000
03163	744421314534
03164	777400777777
03165	777700000000
03166	777777777777

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
POST PROCESSOR ASSEMBLY DATA

3167 IS THE FIRST LOCATION NOT USED BY THIS PROGRAM

REFERENCES TO DEFINED SYMBOLS

2223 T 136, 175, 204, 205, 704, 705, 710, 1147, 1150, 2524, 2525  
1170 AC 1157, 1535  
1171 MQ 1156, 1541  
1653 ADR 1737  
2132 AR1 2050  
2131 AR2 2047, 2124  
2 CAP 215  
2606 DIG 2572  
2020 DX1 1642  
2017 DX2 1641  
2016 DX4 1640  
2452 ETA 2412  
1776 FIN 1746  
2557 HRI 2641  
2023 ILC 1645, 1653, 1734, 1736, 1772, 1774  
1164 IR1 1154, 1551  
1165 IR2 1155, 1554  
1166 IR4 220, 263, 315, 426, 432, 525, 534, 630, 1145, 1557  
2616 LDQ 2542, 2544  
52 MAP  
240 NUM 2062, 2406, 2407  
1260 OCT 1301, 1536, 1542, 1546, 1715, 1743  
234 ORG 214, 1464  
2745 OUT 1656, 1741, 1744, 1745, 1757, 1761, 1762, 1771, 2000, 2001, 2002, 2013, 2015  
1503 PMH 1424, 1427, 1441, 1443, 1461  
1401 PMR 712, 713  
1750 PPM  
2644 PR1 2522  
2643 PR2 2521  
2642 PR4 2520, 2635  
2134 PRE 2055, 2056  
1740 REG 1652, 1661, 1674  
1 RIP 201  
533 SLR 173  
473 SSI 406, 416, 433  
1145 SX4  
235 TIT 202, 707  
425 TR8 405  
250 WEP 226, 230, 232  
2407 WOT 67, 71, 121, 131, 134, 175, 177, 231, 276, 344, 361, 440, 445, 451, 467, 565, 600  
645, 714, 745, 747, 753, 755, 1401, 1442, 1462, 1470, 1562, 1564, 1566, 1570, 1572, 1574, 1576  
1600, 1730, 1732, 1760, 2014, 2456, 2460  
702 BACK 233, 301, 347, 364, 472, 570, 603, 650  
2715 BUFF 2427, 2450, 2630, 2664  
1445 COD1 1414, 1417  
167 C(1) 27  
170 C(2) 31  
171 C(7) 33  
172 C(8) 35  
1523 DCON 1411  
765 DOOR 722, 743, 1001, 1023, 2473  
1026 EPMR 300, 346, 363, 471, 567, 602, 647, 711

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
POST PROCESSOR ASSEMBLY DATA

213 ESTM 206  
175 EVAL 137, 140  
131 EXCM 127  
236 EXEC 216, 222  
732 FILE 724  
431 FPER 411  
404 FPTR 172  
207 ITIM 203  
1024 LOAD 1006  
556 LOOP  
2136 LSTA 2123  
663 LSTM 706, 770, 1152  
1447 LSUB 133  
102 MORG 60, 62, 64, 75, 100  
2773 NAME 111, 123, 1420  
2025 NREP 1675, 1676, 1735  
36 NSYM 66, 103, 105, 111, 113, 116, 123, 1412, 1413, 1415, 1420, 2773, 3031, 3067, 3125  
1260 OCT1 1301  
4 PCT1 1410  
1510 PMBP 1463  
2625 PNCH 2615, 2622  
2564 PRRLP 2613, 2621, 2624  
2541 PTXI 2530  
261 QUIT 672, 705, 1150, 2525  
610 SADR 332, 531, 540, 541, 544, 546, 547, 556, 571  
361 SEQR 266, 320, 430, 530, 537  
1167 SIND 1162, 1545  
2406 SIZE 2060  
1412 SLPN 1447  
541 SLR1 333, 532  
453 SPER 442, 450  
2633 SPRA 2554, 2637  
2660 SPRS 2553  
73 SRCH 55, 56, 101, 130  
723 STCP  
314 STRR 170  
1172 SVPO 1161, 1524  
2146 TABL 2063, 2125, 2407  
241 TCAP 176  
237 TIME 205  
524 TIMR 171  
133 TMAP 126  
477 WACO 446  
503 WMQO 452  
2027 WREP 1710, 1713, 1716, 1717, 1727, 1731  
2442 WTX4 2407  
510 XFPT 460, 466, 470  
350 XSTR 341, 343, 345  
2572 ZONE  
742 CLOSE 733  
1256 COMRT 1233, 1241  
1250 COMSW 1234, 1235, 1253  
173 C(13) 37  
174 C(ST) 41  
1602 DCNX4 1523

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
POST PROCESSOR ASSEMBLY DATA

2026 DNREP 1677, 1704, 1706  
1002 DOOR1 776, 1020  
1517 ENDPM 1471  
1027 ENDRN 715  
1077 ENDTP 746, 2457  
2406 ENTBL 2407  
3067 ENTRY 105, 116  
714 FINIS 1473  
627 IOTMR 174  
1660 LOOP1 1650, 1651, 1747  
1657 LOOP2 1775  
2116 LOWER 2061, 2070  
2024 LWORD 1662, 1711, 1714  
2663 NOSPC 2636  
2135 OPBIN 2054, 2065, 2117  
2125 OPFND 2053, 2067  
2022 PMCNT 1431, 1440, 1451, 1460, 1721, 1726, 1751, 1756, 2005, 2012  
3 PPROG 1407  
2657 PRCOL 2564, 2571  
2664 PRCOM 2634  
2520 PRINT 725, 735, 763, 777, 1021, 2444, 2447, 2470, 2665  
1474 PROER 1402  
571 PSTOP 543, 554  
2115 RAISE 2066  
2612 RLDCP 2574, 2605  
673 RLSTM 701  
1113 SEXIT 1000  
677 SLSTM 663, 666, 673, 675  
2062 SRCH1 2071, 2072, 2073, 2074, 2075, 2076, 2077, 2100, 2101, 2102, 2103, 2104, 2105, 2106, 2107, 2110, 2111  
2112  
2066 SRCH2 2062  
1146 SVCN 221, 264, 316, 427, 434, 526, 535, 631  
701 TLSTM 667  
262 TRAPR 167  
2117 TYPEA 2057, 2113, 2114  
2605 TZECG 2577, 2602  
2614 WDCNT 2540, 2543, 2617  
474 WDVER 441  
2435 WTCAL 2433  
2450 WTCOM 2426, 2431, 2434, 2441  
2436 WTSIW 2430  
2451 WTTAG 2414, 2443  
2422 WTTIX 2417  
2432 WTTXI 2416  
1045 XFILE 736  
651 XIOBD 642, 644, 646  
611 XLOOP 562, 564, 566  
1126 XRCA1 1022  
365 XSEQR 362  
1031 XSTOP 726  
302 XTRAP 273, 275, 277  
1301 BCDTAB 1301, 1302, 1303, 1304, 1305, 1306, 1307, 1310, 1311, 1312, 1313, 1314, 1315, 1316, 1317, 1320, 1321  
1322, 1323, 1324, 1325, 1326, 1327, 1330, 1331, 1332, 1333, 1334, 1335, 1336, 1337, 1340, 1341, 1342  
1343, 1344, 1345, 1346, 1347, 1350, 1351, 1352, 1353, 1354, 1355, 1356, 1357, 1360, 1361, 1362, 1363  
1364, 1365, 1366, 1367, 1370, 1371, 1372, 1373, 1374, 1375, 1376, 1377, 1400

TESTS) FOR CAP, MONITOR FOR CLASS ASSEMBLY PROGRAM.  
POST PROCESSOR ASSEMBLY DATA

2665 CARDIM	2560, 2561, 2576, 2601, 2603, 2607, 2611, 2627
1233 COMADR	
1604 HEAD01	1563
1610 HEAD02	1534, 1565
1613 HEAD03	1537, 1540, 1567
1617 HEAD04	1543, 1544, 1571
1623 HEAD05	1547, 1550, 1573
1627 HEAD06	1553, 1575
1632 HEAD07	1556, 1577
1635 HEAD08	1561, 1601 0 MOVIE) 52, 54
2520 NPRINT	2665
1173 OCTADR	114, 117, 223, 270, 336, 464, 557, 572, 637, 1552, 1555, 1560, 1654
1640 OCTDMP	1444, 1466
3031 ORIGIN	103, 113, 1413, 1415
604 PSTOPS	552
1102 RENDTP	754
1207 TABBLK	1203, 1207, 1210, 1211, 1212, 1213, 1214, 1215, 1216, 1217, 1220, 1221, 1222, 1223, 1224, 1225, 1226 1227, 1230, 1231, 1232, 1707, 1767
7 TESTS)	
2476 WEOTA3	2471
1061 XCLOSE	764
141 XMAP01	70
147 XMAP02	72
153 XMAP03	112, 115, 120, 122
157 XMAP04	132
163 XMAP05	135
621 XPSTOP	575, 577, 601
2047 (OPCD)	1712, 1740

NO ERROR IN ABOVE ASSEMBLY.

\*TIME SPENT IN FAP.. 000054 IN HUNDREDTHS OF MINUTES.

BUFFERED INPUT/OUTPUT PROGRAMS FOR CAP.

PCC			RIP00010
COUNT	278		RIP00020
LBL	RIP	BINARY CARD LABEL.	RIP00030
00012	ENTRY RIP	SETUP READ OPERATIONS.	RIP00050
00071	ENTRY WCT1	WRITE-COLLATION-TAPE-1.	RIP00060
00147	ENTRY REWIND	REWIND COLLATION TAPE.	RIP00070
00157	ENTRY READ2	READ COLLATION TAPE.	RIP00080
00243	ENTRY PRINT	BUFFERRED PRINT PROGRAM.	RIP00090
00277	ENTRY PPROG	DUMP SYMBOLIC PROGRAM.	RIP00100
00347	ENTRY PCT1	DUMP COLLATION TAPE.	RIP00110
00027	ENTRY READ1	READ INPUT TAPE.	RIP00120
		RIP SETS UP READ1 AND PPROG.	RIP00130
			RIP00140
			RIP00150

TRANSFER VECTOR

00000	475146276060	PROG
00001	626704606060	SX4
00002	626523464560	SVCON
00003	664663606060	WOT
00004	254744516060	EPMR
00005	222123426060	BACK
00006	436263446060	LSTM
00007	222324632122	BCDTAB

LINKAGE DIRECTOR

00010	000000000000
00011	513147606060

00012	0634 00 4 00122	RIP	SXA	RX4,4	SAVE IR4.	RIP00160
00013	-0500 60 0 00000	CAL*	\$PROG		GET CONTROL WORD.	RIP00170
00014	-0734 00 4 00000	PDX	0,4		COUNT TC IR4.	RIP00180
00015	-3 04064 4 00017	TXL	**+2,4,LPROG		MAXIMUM NUMBER OF CARDS IN PROG.	RIP00190
00016	0774 00 4 04064	AXT	LPROG,4		..	RIP00200
00017	0754 00 4 00000	PXA	0,4		COUNT TO A(AC).	RIP00210
00020	0361 60 0 00000	ACL*	\$PROG		GET END ADDRESS.	RIP00220
00021	0621 00 0 00040	STA	PEND		SAVE IN READ1.	RIP00230
00022	0621 00 0 00312	STA	PPEND		SAVE IN PPROG.	RIP00240
00023	0634 00 4 00037	SXA	PLTH,4		SAVE IN READ1.	RIP00250
00024	0634 00 4 00310	SXA	PPLTH,4		SAVE IN PPROG.	RIP00260
00025	0534 00 4 00122	LXA	RX4,4		RESTORE IR4.	RIP00270
00026	0020 00 4 00001	TRA	1,4		RETURN.	RIP00280

SPACE	2		RIP00290
		READ1 TAKES NEXT 14 WORDS OF PROG AND STORES IN BUFF.	RIP00300
			RIP00310

00027	0520 00 0 00057	READ1	ZET	TECFI	CHECK FOR END OF PROGRAM.	RIP00320
00030	0020 00 0 00051	TRA	EOF1		END REACHED, COMMENT.	RIP00330
00031	0634 00 4 00122	SXA	RX4,4		SAVE IRS.	RIP00340
00032	0634 00 2 00123	SXA	RX2,2		..	RIP00350
00033	-0500 00 4 00001	CAL	1,4		GET CONTROL WORD.	RIP00360
00034	0361 00 0 10611	ACL	=14		COMPUTE BUFFER+14.	RIP00370
00035	0621 00 0 00041	STA	SLW1		INSERT.	RIP00380
00036	0774 00 4 00016	AXT	14,4		SET WORD COUNT.	RIP00390
00037	0774 00 2 00000	PLTH	AXT	**,2	SET PROGRAM INDEX.	RIP00400

## BUFFERED INPUT/OUTPUT PROGRAMS FOR CAP.

00040	-0500 00 2 00000	PEND	CAL	**,2	COPY CARD INTO BUFFER.	RIP00410
00041	0602 00 4 00000	SLW1	SLW	**,4	..	RIP00420
00042	2 00001 2 00044	TIX	TECFI	*+2,2,1	IF END OF PROG, SET TEOF1.	RIP00430
00043	-0625 00 0 00057	STL	TECFI	..	..	RIP00440
00044	2 00001 4 00040	TIX	PEND,4,1	COUNT WORDS.	..	RIP00450
00045	0634 00 2 00037	SXA	PLTH,2	SAVE PROGRAM INDEX.	..	RIP00460
00046	0534 00 4 00122	LXA	RX4,4	RESTORE IRS.	..	RIP00470
00047	0534 00 2 00123	LXA	RX2,2	..	..	RIP00480
00048	0020 00 4 00002	TRA	2,4	RETURN.	..	RIP00490
00049	0522 60 0 00001	EOF1	XEC*	\$SX4	SAVE IR4.	RIP00500
00050	0074 00 4 00002	TSX	\$SVCON,4	SAVE CONSOLE.	..	RIP00510
00051	0074 00 4 00003	TSX	\$WOT,4	COMMENT, EOF ON INPUT.	..	RIP00520
00052	0 00011 0 00060	PZE	WEOLFI,0,9	..	..	RIP00530
00053	-0625 60 0 00004	STL*	\$EPMR	SET ERROR INDICATOR.	..	RIP00540
00054	0020 60 0 00005	TRA*	\$BACK	EXIT TO POST MORTEM.	..	RIP00550
00055	0 00000 0 00000	TEOF1	PZE	END OF FILE MARK ON INPUT TAPE.	..	RIP00560
00056	002545246046	WEOLFI	BCI	9,0END OF FILE REACHED WHILE READING CAP INPUT TAPE.	..	RIP00570
00057	266026314325					RIP00580
00058	605125212330					RIP00590
00059	252460663031					
00060	432560512521					
00061	243145276023					
00062	214760314547					
00063	646360632147					
00064	253360606060					

SPACE	2	WCT1 TAKES 14 WORDS AND WRITES THEM ON COLLATION TAPE BUFFER. IF TAG OF CONTROL WORD IS NON-ZERO, THEN N (IN DECREMENT OF CONTROL WORD) WORDS OF BUFFER AND 14-N BLANK WORDS GO TO COLLATION TAPE BUFFER.	RIP00600			
00071	0520 00 0 00135	WCT1	ZET	TECTC	CHECK FOR EOT ON CT1.	RIP00610
00072	0020 00 0 00126		TRA	EOTC	EOT REACHED, COMMENT.	RIP00620
00073	0634 00 4 00122		SXA	RX4,4	SAVE IRS.	RIP00630
00074	0634 00 2 00123		SXA	RX2,2	..	RIP00640
00075	0634 00 1 00124		SXA	RX1,1	..	RIP00650
00076	-0500 00 4 00001		CAL	1,4	GET CONTROL WORD.	RIP00660
00077	0625 00 0 00134		STT	TAG	SAVE TAG.	RIP00670
00100	0771 00 0 00022		ARS	18	D(AC) TO A(AC).	RIP00680
00101	-0520 00 0 00134		NZT	TAG	IF TAG=0, A(AC)=14.	RIP00690
00102	-0500 00 0 10611		CAL	=14	COUNT IS 14.	RIP00700
00103	0734 00 2 00000		PAX	0,2	COUNT TO IR2.	RIP00710
00104	1 00001 2 00105		TXI	*+1,2,1	RAISE COUNT FOR TEST.	RIP00720
00105	0754 00 2 00000		PXA	0,2	PLACE IN A(AC).	RIP00730
00106	0361 00 4 00001		ACL	1,4	COMPUTE, BUFFER+COUNT+1.	RIP00740
00107	0621 00 0 00112		STA	WCAL	INSERT.	RIP00750
00110	0774 00 4 00016		AXT	14,4	SET RECORD COUNT.	RIP00760
00111	0774 00 1 10150	WLCT	AXT	LCT1,1	MAXIMUM NUMBER OF RECORDS ON CT1.	RIP00770
00112	-0500 00 2 00000	WCAL	CAL	**,2	MOVE BUFFER TO CT1.	RIP00780
00113	2 00001 2 00115		TIX	*+2,2,1	COUNT BUFFER.	RIP00790
00114	-0500 00 0 10614		CAL	=H	BLANKS IF BUFFER DONE.	RIP00800

BUFFERED INPUT/OUTPUT PROGRAMS FOR CAP.

00115	0602 00 1 10571		SLW	CT1,1	WCT.	RIP00870
00116	2 00001 1 00120		TIX	*+2,1,1	COUNT WORDS CT1.	RIP00880
00117	-0625 00 0 00135		STL	TEOTC	END OF CT1, SET TEOTC.	RIP00890
00120	2 00001 4 00112		TIX	WCAL,4,1	COUNT WORDS IN RECORD.	RIP00900
00121	0634 00 1 00111		SXA	WLCT,1	SAVE CT1 INDEX.	RIP00910
00122	0774 00 4 00000	RX4	AXT	**,*4	RESTORE IRS.	RIP00920
00123	0774 00 2 00000	RX2	AXT	**,*2	..	RIP00930
00124	0774 00 1 00000	RX1	AXT	**,*1	..	RIP00940
00125	0020 00 4 00002		TRA	2,4	RETURN.	RIP00950
00126	0522 60 0 00001	EOTC	XEC*	\$SX4	SAVE IR4.	RIP00970
00127	0074 00 4 00002		TSX	\$SVCON,4	SAVE CONSOLE.	RIP00980
00130	0074 00 4 00003		TSX	\$WOT,4	COMMENT, EOT CT1.	RIP00990
00131	0 00011 0 00136		PZE	WEOTC,0,9	..	RIP01000
00132	-0625 60 0 00004		STL*	\$EPMR	SET ERROR INDICATOR.	RIP01010
00133	0020 60 0 00005		TRA*	\$BACK	EXIT TO POST MORTEM.	RIP01020
00134	0 00000 0 00000	TAG	PZE		CONTROL WORD FOR WCT1.	RIP01040
00135	0 00000 0 00000	TEOTC	PZE		END OF TAPE MARK ON COLLATION TAPE.	RIP01050
00136	002545246046	WEOTC	BCI		9,0END OF TAPE REACHED WHILE WRITING CAP COLLATION TAPE.	RIP01060
00137	266063214725					
00140	605125212330					
00141	252460663031					
00142	432560665131					
00143	633145276023					
00144	214760234643					
00145	432163314645					
00146	606321472533					

		SPACE	2			
				REWIND SETS UP READ2 AND PCT1. READ2 AND PCT1 CHECK THAT REWIND HAS BEEN CALLED.		RIP01070
00147	-0625 00 0 00156	REWIND	STL	TREW	CT1 REWOUND.	RIP01110
00150	-0500 00 0 00111		CAL	WLCT	GET CT1 INDEX IN A(AC).	RIP01120
00151	0767 00 0 00022		ALS	18	PLACE IN D(AC).	RIP01130
00152	0622 00 0 00175		STD	TLCT	SAVE IN READ2.	RIP01140
00153	0622 00 0 00403		STD	PTLCT	SAVE IN PCT1.	RIP01150
00154	0140 00 0 00155		TOV	*+1	TURN OFF AC0VL.	RIP01160
00155	0020 00 4 00001		TRA	1,4	RETURN.	RIP01170
00156	0 00000 0 00000	TREW	PZE		BEGINNING OF TAPE MARK ON COLLATION TAPE.	RIP01180
						RIP01190

		SPACE	2			
				READ2 READS ONE RECORD OF THE COLLATION TAPE BUFFER INTO BUFFER OF CONTROL WORD.		RIP01200
00157	0634 00 4 00122	READ2	SXA	RX4,4	SAVE IRS.	RIP01240
00160	0634 00 2 00123		SXA	RX2,2	..	RIP01250
00161	-0520 00 0 00156		NZT	TREW	TEST FOR REWIND.	RIP01260
00162	0020 00 0 00204		TRA	NREW	NOT REWCUND, COMMENT.	RIP01270
00163	0520 00 0 00231		ZET	TEOFC	CHECK FOR EOF ON CT1.	RIP01280
00164	0020 00 0 00223		TRA	EOF	EOF REACHED, COMMENT.	RIP01290
00165	0774 00 2 10150	RLCT	AXT	LCT1,2	MAXIMUM NUMBER OF CARDS ON CT1.	RIP01300

## BUFFERED INPUT/OUTPUT PROGRAMS FOR CAP.

00166	-C500 00 4 00001	CAL	1,4	GET CONTROL WORD.	RIP01310	
00167	0361 00 0 10611	ACL	=14	COMPUTE BUFFER+14.	RIP01320	
00170	0621 00 0 00173	STA	*+3	INSERT.	RIP01330	
00171	0774 00 4 00016	AXT	14,4	SET WORD COUNT.	RIP01340	
00172	-0500 00 2 10571	CAL	CT1,2	MOVE TO BUFFER.	RIP01350	
00173	0602 00 4 00000	SLW	**+,4	..	RIP01360	
00174	1 77777 2 00175	TXI	*+1,2,-1	COUNT CT1.	RIP01370	
00175	3 00000 2 00177	TLCT	TXH	*+2,2,**	CHECK FOR FILE MARK.	RIP01380
00176	-0625 00 0 00231	STL	TECFC	FILE MARK.	RIP01390	
00177	2 00001 4 00172	TIK	*-5,4,1	COUNT WORDS.	RIP01400	
00200	0634 00 2 00165	SXA	RLCT,2	SAVE CTL INDEX.	RIP01410	
00201	0534 00 4 00122	LXA	RX4,4	RESTORE IRS.	RIP01420	
00202	0534 00 2 00123	LXA	RX2,2	..	RIP01430	
00203	0020 00 4 00002	TRA	2,4	RETURN.	RIP01440	
00204	0074 00 4 00006	NREW	TSX	\$LSTM,4	CT1 NOT REWOUND, RESET TRAP.	RIP01450
00205	0074 00 4 00003		TSX	\$WOT,4	COMMENT.	RIP01460
00206	0 00011 0 00212	PZE	WNREW,0,9	..	RIP01470	
00207	-0760 00 0 00005	ESTM		RE-ENTER TRAP.	RIP01480	
00210	0074 00 4 00147	TSX	REWIND,4	REWIND CT1.	RIP01490	
00211	0020 00 0 00165	TRA	RLCT	RETURN.	RIP01500	
00212	005125212402	WNREW	BCI	9,CREAD2 CALLED BEFORE REWIND, COLLATION TAPE REWOUND.	RIP01510	
00213	602321434325				RIP01520	
00214	246022252646				RIP01530	
00215	512560512566					
00216	314524736C23					
00217	464343216331					
00220	464560632147					
00221	256C51256646					
00222	644524336060					
00223	0522 60 0 00001	EOFC	XEC*	\$SX4	SAVE IR4.	RIP01540
00224	0074 00 4 00002		TSX	\$SVCON,4	SAVE CONSOLE.	RIP01550
00225	0074 00 4 00003		TSX	\$WOT,4	COMMENT, EOF ON CT1.	RIP01560
00226	0 00011 0 00232	PZE	WEOF,0,9	..	RIP01570	
00227	-0625 60 0 00004	STL*	\$EPMR	SET ERROR INDICATOR.	RIP01580	
00230	0020 60 0 00005	TRA*	\$BACK	EXIT TO POST MORTEM.	RIP01590	
00231	0 00000 0 00000	TEOFC	PZE		END OF FILE MARK ON COLLATION TAPE.	RIP01600
00232	002545246046		WEOF, BCI		9,0END OF FILE REACHED WHILE READING COLLATION TAPE.	RIP01610
00233	26026314325					RIP01620
00234	605125212330					RIP01630
00235	252460663031					
00236	432560512521					
00237	243145276023					
00240	464343216331					
00241	464560632147					
00242	253360606060					
		SPACE	2	PRINT COUNTS LINES AND CALLS \$WOT.	RIP01640	
00243	0634 00 4 00122	PRINT	SXA	RX4,4	SAVE IR4.	RIP01650
00244	0500 00 0 00267		CLA	LNCNT	COUNT LINES.	RIP01660
						RIP01670
						RIP01680

BUFFERED INPUT/OUTPUT PROGRAMS FOR CAP.

00245	0402 00 0 10610	SUB	=1		RIP01690
00246	0601 00 0 00267	STO	LNCNT	..	RIP01700
00247	-0120 00 0 00261	TMI	LNEX	CHECK FOR LNCNT EXCEEDED.	RIP01710
00250	-0500 00 4 00001	CAL	1,4	SET CONTROL WORD FOR WOT.	RIP01720
00251	0621 00 0 00255	STA	CWOT	..	RIP01730
00252	0622 00 0 00255	STD	CWOT	..	RIP01740
00253	0074 00 4 00006	TSX	\$LSTM,4	RESET TRAP.	RIP01750
00254	0074 00 4 00003	TSX	\$WOT,4	OK, GO TO WOT.	RIP01760
00255	0 00000 0 00000	CWOT	PZE	..	RIP01770
00256	-0760 00 0 00005	ESTM		RESET TRAP.	RIP01780
00257	0534 00 4 00122	LXA	RX4,4	RESTORE IR4.	RIP01790
00260	0020 00 4 00002	TRA	2,4	RETURN.	RIP01800
00261	0522 60 0 00001	LNEX	XEC*	\$SX4	RIP01810
00262	0074 00 4 00002	TSX	\$SVCON,4	LNCNT EXCEEDED, SAVE IR4.	RIP01820
00263	0074 00 4 00003	TSX	\$WOT,4	SAVE CONSOLE.	RIP01830
00264	0 00007 1 00270	PZE	WLNX,1,7	COMMENT.	RIP01840
00265	-0625 60 0 00004	STL*	\$EPMR	..	RIP01850
00266	0020 60 0 00005	TRA*	\$BACK	SET ERROR INDICATOR.	RIP01860
				EXIT TO POST MORTEM SECTION.	RIP01870
00267	0 00000 0 00454	LNCNT	PZE	300	RIP01880
00270	004751462751	WLNX	BCI	MAXIMUM LINES OUTPUT.	RIP01890
00271	21444255160			7,0PROGRAMMER OUTPUT EXCEEDS 300 RECORDS.	RIP01900
00272	466463476463				
00273	602567232525				
00274	246260030000				
00275	605125234651				
00276	246233606060				

		SPACE	2	PPROG PRINTS UP TO 15C CARDS OF \$PROG.	RIP01910	
					RIP01920	
00277	0634 00 4 00122	PPROG	SXA	RX4,4	SAVE IRS.	RIP01930
00300	0634 00 2 00123		SXA	RX2,2	..	RIP01940
00301	0634 00 1 00124		SXA	RX1,1	..	RIP01950
00302	0074 00 4 00003		TSX	\$WOT,4	INITIAL COMMENT.	RIP01960
00303	0 00010 0 00337		PZE	PHEAD,0,8	..	RIP01970
00304	0074 00 4 00003		TSX	\$WOT,4	BLANK LINE.	RIP01980
00305	0 00001 0 10614		PZE	=H ,0,1	..	RIP01990
00306	-0500 00 0 00007		CAL	\$BCDTAB	GET ADDRESS OF TABLE.	RIP02000
00307	0621 00 0 00313		STA	CRQ1	..	RIP02010
00310	0774 00 1 00000	PPLTH	AXT	*,1	PROGRAM WORD COUNT.	RIP02020
00311	0774 00 2 00016		AXT	14,2	BUFFER WORD COUNT.	RIP02030
00312	0560 00 1 00000	PPEND	LDQ	*,1	GET CURRENT WORD.	RIP02040
00313	-0154 06 0 00000	CRQ1	CRQ	*,0,6	DELETE ILLEGAL CHARACTERS.	RIP02050
00314	-0600 00 2 10610		STQ	PBUFF+15,2	PLACE IN BUFFER.	RIP02060
00315	-2 00001 2 00317		TNX	*+2,2,1	COUNT WORDS IN BUFFER.	RIP02070
00316	1 77777 1 00312		TXI	*-4,1,-1	COUNT WORDS IN PROG.	RIP02080
00317	0560 00 0 10614		LDQ	=H	PICKUP STANDARD CARRIAGE CONTROL.	RIP02090
00320	0500 00 0 00336		CLA	PPCNT	DECREMENT LINE COUNT.	RIP02100
00321	0402 00 0 10610		SUB	=1	..	RIP02110
00322	0120 00 0 00325		TPL	*+3	CHECK FOR OVERFLOW.	RIP02120
00323	0500 00 0 10612		CLA	=59	OVERFLOW, RESTORE LINE COUNT-1.	RIP02130
00324	0560 00 0 10613		LDQ	=H1	SET TO EJECT.	RIP02140
00325	0601 00 0 00336		STO	PPCNT	SAVE REMAINING LINE COUNT.	RIP02150
					RIP02160	

## BUFFERED INPUT/OUTPUT PROGRAMS FOR CAP.

00326	-0600 00 0 10571	STQ	PBUFF	INSERT CARRIAGE CONTROL.	RIP02170
00327	0074 00 4 00003	TSX	\$WOT,4	PRINT THIS CARD.	RIP02180
00330	0 00017 0 10571	PZE	PBUFF,0,15	..	RIP02190
00331	2 00001 1 00311	TIX	PPLTH+1,1,1	COUNT RECORDS.	RIP02200
00332	0534 00 4 00122	LXA	RX4,4	RESTORE IRS.	RIP02210
00333	0534 00 2 00123	LXA	RX2,2	..	RIP02220
00334	0534 00 1 00124	LXA	RX1,1	..	RIP02230
00335	0020 00 4 00001	TRA	1,4	RETURN.	RIP02240
00336	0 00000 0 00072	PPCNT PZE	58	60 LINES PER PAGE - 2 FOR HEADING.	RIP02250
00337	016C60606060	PHEAD BCI	2,1		RIP02260
00340	606C60606060				RIP02270
00341	604746626360	BCI		6, POST MCRTEM OF SYMBOLIC PROGRAM.	RIP02280
00342	444651632544				
00343	604626606270				
00344	442246433123				
00345	604751462751				
00346	214433606060				
		SPACE	2		RIP02290
				PCT1 PRINTS UP TO 300 RECORDS OF CT1.	RIP02300
					RIP02310
00347	0634 00 4 00122	PCT1	SXA	RX4,4	RIP02320
00350	0634 00 2 00123		SXA	RX2,2	RIP02330
00351	0634 00 1 00124		SXA	RX1,1	RIP02340
00352	0074 00 4 00003		TSX	\$WOT,4	RIP02350
00353	0 00010 0 00411		PZE	CHEAD,0,8	RIP02360
00354	0074 00 4 00003		TSX	\$WOT,4	RIP02370
00355	0 00001 0 10614		PZE	=H ,C,1	RIP02380
00356	-0500 00 0 00007		CAL	\$BCDTAB	RIP02390
00357	0621 00 0 00365		STA	CRQ2	RIP02400
00360	-0520 00 0 00156			REW	RIP02410
00361	0074 00 4 00147		TSX	REWIND,4	RIP02420
00362	0774 00 1 10150		AXT	LCT1,1	RIP02430
00363	0774 00 2 00016	PCTL	AXT	14,2	RIP02440
00364	0560 00 1 10571		LDQ	CT1,1	RIP02450
00365	-0154 06 0 00000		CRQ2	**,0,6	RIP02460
00366	-0600 00 2 10610		STQ	PBUFF+15,2	RIP02470
00367	1 77777 1 00370		TXI	*+1,1,-1	RIP02480
00370	2 00001 2 00364		TIX	*-4,2,1	RIP02490
00371	0560 00 0 10614		LDQ	=H	RIP02500
00372	0500 00 0 00410		CLA	PCCNT	RIP02510
00373	0402 00 0 10610		SUB	=1	RIP02520
00374	0120 00 0 00377		TPL	*+3	RIP02530
00375	050C 00 0 10612		CLA	=59	RIP02540
00376	0560 00 0 10613		LDQ	=H1	RIP02550
00377	0601 00 0 00410		STO	PCCNT	RIP02560
00400	-0600 00 0 10571		STQ	PBUFF	RIP02570
00401	0074 00 4 00003		TSX	\$WOT,4	RIP02580
00402	0 00017 0 10571		PZE	PBUFF,0,15	RIP02590
00403	3 00000 1 00363	PTLCT	TXH	PCTL,1,**	RIP02600
00404	0534 00 4 00122		LXA	RX4,4	RIP02610
00405	0534 00 2 00123		LXA	RX2,2	RIP02620
00406	0534 00 1 00124		LXA	RX1,1	RIP02630
00407	0020 00 4 00001		TRA	1,4	RIP02640

BUFFERED INPUT/OUTPUT PROGRAMS FOR CAP.

00410	0 00000 0 00072	PCCNT PZE	58	60 LINES PER PAGE - 2 FOR HEADING.	RIP02650
00411	016060606060	CHEAD BCI	2,1		RIP02660
00412	606060606060				RIP02670
00413	604746626360	BCI	6,	POST MORTEM OF COLLATION TAPE.	RIP02680
00414	444651632544				
00415	604626602346				
00416	434321633146				
00417	456063214725				
00420	336060606060				
		04064 LPROG EQU	14*150	150 CARDS ON INPUT TAPE.	RIP02690
		10150 LCT1 EQU	14*300	300 RECORDS MAX CN COLLATION TAPE.	RIP02700
					RIP02710
00421	512523465124	BCI	9,	RECORD NO. 1, COLLATION TAPE, NOTHING HAS BEEN WRITTEN	RIP02720
00422	604546336001				RIP02730
00423	736023464343				
00424	216331464560				
00425	632147257360				
00426	454663303145				
00427	276030216260				
00430	222525456066				
00431	513163632545				
00432	604645602363	BCI	5,	ON CT1.	RIP02740
00433	013360606060				
00434	606060606060				
00435	606060606060				
00436	606060606060				
10571		CT1 BES	LCT1-14	COLLATION TAPE BUFFER.	RIP02750
10571		PBUFF BSS	15	PRINT BUFFER.	RIP02760
					RIP02770
		END			RIP02780

LITERALS

10610	000000000001
10611	000000000016
10612	000000000073
10613	016060606060
10614	606060606060

BUFFERED INPUT/OUTPUT PROGRAMS FOR CAP.  
POST PROCESSOR ASSEMBLY DATA

150

10615 IS THE FIRST LOCATION NOT USED BY THIS PROGRAM

REFERENCES	TO	DEFINED SYMBOLS
10571	CT1	115, 172, 364
12	RIP	
124	RX1	75, 301, 334, 351, 406
123	RX2	32, 47, 74, 160, 202, 300, 333, 350, 405
122	RX4	12, 25, 31, 46, 73, 157, 201, 243, 257, 277, 332, 347, 404
1	SX4	51, 126, 223, 261
134	TAG	77, 101
3	WOT	53, 130, 205, 225, 254, 263, 302, 304, 327, 352, 354, 401
5	BACK	56, 133, 230, 266
313	CRQ1	307
365	CRQ2	357
255	CWCT	251, 252
223	EOF C	164
51	EOF I	30
126	EOT C	72
4	EPMR	55, 132, 227, 265
10150	LCT1	111, 165, 362, 421, 10571
261	LNE X	247
6	LSTM	204, 253
204	NREW	162
347	PCT1	
363	PCTL	403
40	PEND	21, 44
37	PLTH	23, 45
0	PRCG	13, 20
165	RLCT	200, 211
41	SLW1	35
175	TLCT	152
156	TREW	147, 161, 360
112	WCAL	107, 120
71	WCT1	
111	WLCT	121, 150
411	CHEAD	353
267	LNCNT	244, 246
4064	LPRCG	15, 16, 421
10571	PBUFF	314, 326, 330, 366, 400, 402
410	PC CNT	372, 377
337	PHEAD	303
336	PPC NT	320, 325
312	PPEND	22
310	PPLTH	24, 331
277	PPROG	
243	PRINT	
403	PTLCT	153
27	READ1	
157	READ2	
2	SVCCN	52, 127, 224, 262
231	TEOFC	163, 176
57	TEOF I	27, 43
135	TEOT C	71, 117
232	WE OFC	226
60	WE OFI	54

BUFFERED INPUT/OUTPUT PROGRAMS FOR CAP.  
POST PRCESSOR ASSEMBLY DATA

136	WEOTC	131
270	WLNX	264
212	WNREW	206
7	BCDTAB	306, 356
147	REWIND	210, 361

NO ERROR IN ABOVE ASSEMBLY.

\*TIME SPENT IN FAP.. 000012 IN HUNDREDTHS OF MINUTES.

## SYMBOLIC PROGRAM TO TEST CAP.

	PCC COUNT LBL ENTRY	150 PROG PRCG	BINARY CARD LABEL.	PROG0010 PROG0020 PROG0030 PROG0050	
00002					
LINKAGE DIRECTOR					
C0000	000000000000				
00001	475146276060				
00002	0 01724 0 00003	PROG PZE	*+1,0,LTH	CONTROL WORD. START,,LENGTH. DELETE GENERATED OCTAL FROM LISTING.	PROG0060 PROG0070
00003	232147606060	BCI	9,CAP	REM THE FOLLOWING ARE ALL LEGAL CAP INSTRUCTIO	PROG0080 PROG0090
00014	456233606060	BCI	5,NS.	TSTCAP00	PROG0100 PROG0110
00021	606060606060	BCI	9,	REM PROGRAM TO COUNT BITS IN AC.	PROG0120 PROG0130
00032	606060606060	BCI	5,	TSTCAP01	PROG0140 PROG0150
00037	234664456360	BCI	9,COUNT	LDQ ZERO ZERO TEST CELLS	PROG0160 PROG0170
00050	606060606060	BCI	5,	TSTCAP02	PROG0180 PROG0190
00055	606060606060	BCI	9,	STQ BITS ..	PROG0200 PROG0210
00066	606060606060	BCI	5,	TSTCAP03 COUNT 36 BITS.	PROG0220 PROG0230
00073	606060606060	BCI	9,	LXA THSX TSTCAP04	PROG0240 PROG0250
00104	606060606060	BCI	5,	PROGRAM TO COUNT BITS IN AC.	PROG0260 PROG0270
00111	434646476060	BCI	9,LOOP	LBT BIT OR NO.	PROG0280 PROG0290
00122	606060606060	BCI	5,	TSTCAP05 NO BIT.	PROG0300 PROG0310
00127	606060606060	BCI	9,	TRA NO TSTCAP06	PROG0320 PROG0330
00140	606060606060	BCI	5,	WORD BIT, SAVE AC,	PROG0340 PROG0350
00145	702562606060	BCI	9,YES	SLW TSTCAP07	PROG0360 PROG0370
00156	606060606060	BCI	5,	AND INCREMENT COUNT.	PROG0380 PROG0390
00163	606060606060	BCI	9,	CAL BITS TSTCAP08	PROG0400 PROG0410
00174	606060606060	BCI	5,	ACL ONE TSTCAP09 ..	PROG0420 PROG0430
00201	606060606060	BCI	9,	TSTCAP10 ..	PROG0440 PROG0450
00212	606060606060	BCI	5,	SLW BITS RESTORE AC.	PROG0460 PROG0470
00217	606060606060	BCI	9,	TSTCAP11 NEXT BIT.	PROG0480 PROG0490
00230	606060606060	BCI	5,	TSTCAP12 INDEX.	PROG0500 PROG0510
00235	606060606060	BCI	9,	CAL WORD TSTCAP13 GET COUNT.	PROG0520
00246	606060606060	BCI	5,	TSTCAP14 STOP WITH TRANSFER TO 70000	
00253	606060606060	BCI	9,DONE	OCTL 002100070000	
00264	606060606060	BCI	5, OCTAL.	TSTCAP15	
00271	454660606060	BCI	9,NO	TIX LOOP TSTCAP16 TRUE ZERO.	
00302	606060606060	BCI	5,	CAL BITS TSTCAP17 INCREMENT OF ONE.	
00307	606060606060	BCI	9,	TSTCAP18 ADDRESS IS 36.	
00320	606060606060	BCI	5,	OCTL 000000000000 TSTCAP19	
00325	244645256060	BCI	9,ZERO	002100070000	
00336	604623632143	BCI	5,	STOP WITH TRANSFER TO 70000	
00343	606060606060	BCI	9,	REM STORAGE. TSTCAP20 STORAGE FOR BIT COUNT.	
00354	606060606060	BCI	5,	TSTCAP21 TEMPORARY STORAGE FOR AC.	
00361	712551466060	BCI	9,ZERO	OCTL 000000000000	
00372	606060606060	BCI	5,		
00377	464525606060	BCI	9,ONE	INT 1 TSTCAP20	
00410	606060606060	BCI	5,	TSTCAP21	
00415	633062676060	BCI	9,THSX	LAS 36 TSTCAP19	
00426	606060606060	BCI	5,		
00433	606060606060	BCI	9,	REM DATA. TSTCAP20	
00444	606060606060	BCI	5,		
00451	223163626060	BCI	9,BITS	INT 0 TSTCAP20	
00462	606060606060	BCI	5,		
00467	664651246060	BCI	9,WORD	INT 0 TSTCAP21	

SYMBOLIC PROGRAM TO TEST CAP.

00500	606060606060	BCI	5,	TSTCAP22	PROG0530
00505	606060606060	BCI	9,	REM TEST OF CAP PSEUDO-OPS, AND FLAGS.	PROG0540
00516	606060606060	BCI	5,	TSTCAP23	PROG0550
00523	606060606060	BCI	9,	ILCD 8 ILLEGAL OPCODE.	PROG0560
00534	606060606060	BCI	5,	TSTCAP24	PROG0570
00541	606060606060	BCI	9,	TRA UNDEF UNDEFINED SYMBOL.	PROG0580
00552	606060606060	BCI	5,	TSTCAP25	PROG0590
00557	606060606060	BCI	9,	INT 1,2,-7,13A3,9 ERROR IN INTOP.	PROG0600
00570	606060606060	BCI	5,	TSTCAP26	PROG0610
00575	606060606060	BCI	9,	WMW AEN ILLEGAL OPCODE AND UNDEFINE	PROG0620
00606	246062704422	BCI	5,C SYMBOL.	TSTCAP27	PROG0630
00613	606060606060	BCI	9,	COMP NO = YES + LOOP	PROG0640
00624	606060606060	BCI	5,	TSTCAP28	PROG0650
00631	234644476060	BCI	9,COMP COMP	Z = A * B * C / D / E / FLAG	PROG0660
00642	606060606060	BCI	5,	TSTCAP29	PROG0670
00647	606060606060	BCI	9,	TRA COMP USE OF SYMBOL DEFINED BY CO	PROG0680
00660	4464733606060	BCI	5,MP.	TSTCAP30	PROG0690
00665	606060606060	BCI	9,	COMP COUNT,1 = LOOP01,2 - START,4	PROG0700
00676	606060606060	BCI	5,	TSTCAP31	PROG0710
00703	606060606060	BCI	9,	COMP DZ = (E+Z*(D+Z*(C+Z*(B+Z*A)))) + FOO	PROG0720
00714	606060606060	BCI	5,	TSTCAP32	PROG0730
00721	606060606060	BCI	9,	TIX COUNT+3*((NO-YES)*Z+1)*(LOOP-COUNT)+8*(ZE	PROG0740
00732	514640244645	BCI	5,RO-DONE)+8)	TSTCAP33	PROG0750
00737	606060606060	BCI	9,	REM TEST OF PROPOSED MODIFICATIONS TO CAP.	PROG0760
00750	606060606060	BCI	5,	TSTCAP34	PROG0770
00755	446443606060	BCI	9,MUL	INT 0 MULTIPLY DEFINED SYMBOL.	PROG0780
00766	606060606060	BCI	5,	TSTCAP35	PROG0790
00773	446443606060	BCI	9,MUL	INT 0 MULTIPLY DEFINED SYMBOL.	PROG0800
01004	606060606060	BCI	5,	TSTCAP36	PROG0810
01011	236060606060	BCI	9,C	PZE -32+BITS PZE CODE.	PROG0820
01022	606060606060	BCI	5,	TSTCAP37	PROG0830
01027	246060606060	BCI	9,D	MZE NO+65 MZE CODE.	PROG0840
01040	606060606060	BCI	5,	TSTCAP38	PROG0850
01045	606060606060	BCI	9,	SLW \$+1 \$ FOR THIS LOCATION	PROG0860
01056	606060606060	BCI	5,	TSTCAP39	PROG0870
01063	606060606060	BCI	9,	CLA 2*\$-1 \$ TEST.	PROG0880
01074	606060606060	BCI	5,	TSTCAP40	PROG0890
01101	606060606060	BCI	9,	MTH C/3 DIVISION IN ADDRESS	PROG0900
01112	606060606060	BCI	5,	TSTCAP41	PROG0910
01117	716060606060	BCI	9,Z	PON (YES-COUNT)/3+F PON WITH DIVISION IN ADDR	PROG0920
01130	256262602151	BCI	5,ESS ARITHMETIC.	TSTCAP42	PROG0930
01135	606060606060	BCI	9,	STO (C-FLAG)/2 DIVISION WITH NEGATIVE ANSW	PROG0940
01146	255133606060	BCI	5,ER.	TSTCAP43	PROG0950
01153	606060606060	BCI	9,	SLW -8*BITS+\$*1+7*Z USE OF \$ AS A SYMBOL.	PROG0960
01164	606060606060	BCI	5,	TSTCAP44	PROG0970
01171	606060606060	BCI	9,	ARF (\$-C)/5+Q \$,/, AND ILLEGAL OPCODE	PROG0980
01202	606060606060	BCI	5,	TSTCAP45	PROG0990
01207	546051254421	BCI	9,* REMARK CARD WITH * IN COLUMN 1.		PROG1000
01220	606060606060	BCI	5,	TSTCAP46	PROG1010
01225	224345426060	BCI	9,BLNK	BLNK BLANK OPCODE.	PROG1020
01236	606060606060	BCI	5,	TSTCAP47	PROG1030
01243	745313546160	BCI	9,(\$=*) NOP UNDEF S, O, AND U FLAGS.		PROG1040
C1254	606060606060	BCI	5,	TSTCAP48	PROG1050
C1261	506060606060	BCI	9,Q	HOL 5THIS IS HOLLERITH INFO.	PROG1060
01272	606060606060	BCI	5,	TSTCAP49	PROG1070
01277	606060606060	BCI	9,	CLA* FLAG USE OF FLAGGED INSTRUCTION.	PROG1080

## SYMBOLIC PROGRAM TO TEST CAP.

01310	606060606060	BCI	5,	TSTCAP50	PROG1090
01315	264321276060	BCI	9, FLAG	STO =1139 LITERAL.	PROG1100
01326	606060606060	BCI	5,	TSTCAP51	PROG1110
01333	606060606060	BCI	9,	CLA =1139 SAME LITERAL.	PROG1120
01344	606060606060	BCI	5,	TSTCAP52	PROG1130
01351	605460606060	BCI	9, *	LAC* =5597.0 E, S, AND F FLAGS.	PROG1140
01362	606060606060	BCI	5,	TSTCAP53	PROG1150
01367	606060606060	BCI	9,	TNX Z,3,5 TAG AND DECREMENT FIELD.	PROG1160
01400	606060606060	BCI	5,	TSTCAP54	PROG1170
01405	606060606060	BCI	9,	FAD (YES-COUNT)*(NO-LOOP)+START,2+3*(NO-LOOP)	PROG1180
01416	606060606060	BCI	5,	TSTCAP55	PROG1190
01423	247160606060	BCI	9,DZ	OCT 17,13,-44,Q,13,,1 OCT PSEUDO-OP.	PROG1200
01434	606060606060	BCI	5,	TSTCAP56	PROG1210
01441	606060606060	BCI	9,	FDP FLAG A DIVIDE INSTRUCTION.	PROG1220
01452	606060606060	BCI	5,	TSTCAP57	PROG1230
01457	606060606060	BCI	9,	STO MUL+UNDEF FOLLOWED BY A STORE.	PROG1240
01470	606060606060	BCI	5,	TSTCAP58	PROG1250
01475	626321516360	BCI	9, START	EQU COUNT+3*(NO-LOOP) PROPER USE OF EQU.	PROG1260
01506	606060606060	BCI	5,	TSTCAP59	PROG1270
01513	216060606060	BCI	9,A	TRA START USE OF SYMBOL DEFINED BY EQ	PROG1280
01524	643360606060	BCI	5,U.	TSTCAP60	PROG1290
01531	473160606060	BCI	9,PI	EQU END-COMP PHASE ERROR.	PROG1300
01542	606060606060	BCI	5,	TSTCAP61	PROG1310
01547	226060606060	BCI	9,B	TRA PI USE OF SYMBOL WITH PHASE ER	PROG1320
01560	514651336060	BCI	5,ROR.	TSTCAP62	PROG1330
01565	256060606060	BCI	9,E	BSS 5 PROPER BSS.	PROG1340
01576	606060606060	BCI	5,	TSTCAP63	PROG1350
01603	266060606060	BCI	9,F	BSS LOOP-COUNT PROPER SYMBOLIC DEFINITION	PROG1360
01614	462660226262	BCI	5,OF BSS.	TSTCAP64	PROG1370
01621	434646470001	BCI	9,LOOP01	BSS CALL-F IMPROPER BSS, PHASE ERROR.	PROG1380
01632	606060606060	BCI	5,	TSTCAP65	PROG1390
01637	232143436060	BCI	9,CALL	CALL COUNT,NO,C,YES LEGAL CALL MACRO.	PROG1400
01650	606060606060	BCI	5,	TSTCAP66	PROG1410
01655	232143430260	BCI	9,CALL2	CALL ABLE,BAKER+2,CHRLY-5*(NO-LOOP)	PROG1420
01666	606060606060	BCI	5,	TSTCAP67	PROG1430
01673	602646466060	BCI	9, FOO	CLA \$ CHECK ILC AFTER BSS AND CAL	PROG1440
01704	433360606060	BCI	5,L.	TSTCAP68	PROG1450
01711	602545246060	BCI	9, END	END COUNT+1*UNDEF FINALLY THE END.	PROG1460
C1722	606060606060	BCI	5,	TSTCAP69	PROG1470
		DETAIL		RETURN TO NORMAL MODE.	PROG1480
		END		LENGTH OF PROG.	PROG1490
01724	LTH	EQU	*-1-PROG		PROG1500

## POST PROCESSOR ASSEMBLY DATA

1727 IS THE FIRST LOCATION NOT USED BY THIS PROGRAM

REFERENCES TO DEFINED SYMBOLS  
 1724 LTH 2, 1727  
 2 PROG 1727

NO ERROR IN ABOVE ASSEMBLY.  
 \*TIME SPENT IN FAP.. 000007 IN HUNDREDS OF MINUTES.

1.17 MINUTES ELAPSED SINCE START OF JOB  
SUBPROGRAM STORAGE MAP FOLLOWS.

NAME ORIGIN ENTRY

CAP 144 151

PASS1 201 213

PASS2 317 327

VAREVL 637 644

OPTBL 1117 1121

INTOP 1226 1230

SCAN 1351 1353

SYMSTO 2462 2465

ENDOP 3036 3042

COMPPOP 3207 3217

EXPR 3752 3760

TERM 4155 4163

(MAIN) 4320 4321

TESTS 4325 4331

END OF STORAGE MAP.

## TEST OF CAP, BEGIN ASSEMBLY.

		CAP	REM	THE FOLLOWING ARE ALL LEGAL CAP INSTRUCTIONS.	
		COUNT	REM	PROGRAM TO COUNT BITS IN AC.	TSTCAP00
			LDQ	ZERO ZERO TEST CELLS	TSTCAP01
	50000	056000050016	STQ	BITS ..	TSTCAP02
	50001	460000050021	LXA	THSX COUNT 36 BITS.	TSTCAP03
	50002	053400450020	LOOP	LBT BIT OR NO.	TSTCAP04
	50003	076000000001	TRA	NO NO BIT.	TSTCAP05
	50004	002000050013	YES	SLW WORD BIT, SAVE AC,	TSTCAP06
	50005	060200050022	CAL	BITS AND INCREMENT COUNT.	TSTCAP07
	50006	450000050021	ACL	ONE ..	TSTCAP08
	50007	036100050017	SLW	BITS ..	TSTCAP09
	50010	060200050021	CAL	WORD RESTORE AC.	TSTCAP10
	50011	450000050022	LGR	1 NEXT BIT.	TSTCAP11
	50012	476500000001	TIX	LOOP INDEX.	TSTCAP12
	50013	2C0001450003	NO	CAL BITS GET COUNT.	TSTCAP13
	50014	450000050021	DONE	OCTL 002100070000 STOP WITH TRANSFER TO 70000 OCTAL.	TSTCAP14
	50015,	002100070000		REM STORAGE.	TSTCAP15
	50016	000000000000	ZERO	OCTL 000000000000 TRUE ZERO.	TSTCAP16
	50017	000001000000	ONE	INT 1 INCREMENT OF ONE.	TSTCAP17
	50020	434000000044	THSX	LAS 36 ADDRESS IS 36.	TSTCAP18
				REM DATA.	TSTCAP19
	50021	000000000000	BITS	INT 0 STORAGE FOR BIT COUNT.	TSTCAP20
	50022	000000000000	WORD	INT 0 TEMPORARY STORAGE FOR AC.	TSTCAP21
				REM TEST OF CAP PSEUDO-OPS, AND FLAGS.	TSTCAP22
O	50023	000000000010		ILCD 8 ILLEGAL OPCODE.	TSTCAP23
U	50024	002000000000		TRA UNDEF UNDEFINED SYMBOL.	TSTCAP24
E	50025	000001000000		INT 1,2,-7,13A3,9 ERROR IN INTOP.	TSTCAP25
CU	50032	000000000000		WMW AEN ILLEGAL OPCODE AND UNDEFINED SYMBOL.	TSTCAP26
	50033	050000050005		COMP NO = YES + LOOP	TSTCAP27
	50034	030000050003		CLA YES	TSTCAP28
	50035	060100050013	COMP	FAD LOOP	
				STO NO	
				COMP Z = A * B * C / D / E / FLAG	TSTCAP29
	50036	056000050143		LDQ A	
	50037	026000050145		FMP B	
	50040	013100000000		XCA	
	50041	026000050114		FMP C	
	50042	024100050115		FDP D	
	50043	013100000000		XCA	
	50044	024100050146		FDP E	
	50045	013100000000		XCA	
	50046	024100050132		FDP FLAG	
	50047	460000050154		STQ TEM	
	50050	050000050154		CLA TEM	
	50051	060100050121		STO Z	
	50052	002000050036		TRA COMP USE OF SYMBOL DEFINED BY COMP.	TSTCAP30
				COMP COUNT,1 = LOOP01,2 - START,4	TSTCAP31
	50053	050000050150		CLA LOOP01,2	
	50054	030200050142		FSB START,4	
	50055	060100050000		STO COUNT,1	
				COMP DZ = (E+Z*(D+Z*(C+Z*(B+Z*A)))) + FOO	TSTCAP32
	50056	056000050121		LDQ Z	
	50057	026000050143		FMP A	
	50060	060100050154		STO TEM	
	50061	050000050145		CLA B	
	50062	030000050154		FAD TEM	
	50063	060100050155		STO TEM+1	
	50064	056000050121		LDQ Z	
	50065	026000050155		FMP TEM+1	

	50066	060100050156	STO	TEM+2		
	50067	050000050114	CLA	C		
	50070	030000050156	FAD	TEM+2		
	50071	060100050157	STO	TEM+3		
	50072	056000050121	LDQ	Z		
	50073	0260000C50157	FMP	TEM+3		
	50074	060100050160	STO	TEM+4		
	50075	050000050115	CLA	C		
	50076	030000050160	FAD	TEM+4		
	50077	060100050161	STO	TEM+5		
	50100	056000050121	LDQ	Z		
	50101	026000050161	FMP	TEM+5		
	50102	060100050162	STO	TEM+6		
	50103	050000050146	CLA	E		
	50104	030000050162	FAD	TEM+6		
	50105	060100050163	STO	TEM+7		
	50106	050000050163	CLA	TEM+7		
	50107	030000050153	FAD	FOO		
	50110	060100050137	STO	DZ		
	50111	200001440517	TIX	COUNT+3*((NO-YES)*Z+1)*(LOOP-COUNT)+8*(ZERO-DONE)+8)	TSTCAP33	
			REM	TEST OF PROPCSED MODIFICATIONS TO CAP.	TSTCAP34	
O	50112	000000000000	MUL	INT 0 MULTIPLY DEFINED SYMBOL.	TSTCAP35	
O	50113	000000000000	MUL	INT 0 MULTIPLY DEFINED SYMBOL.	TSTCAP36	
O	50114	000000047761	C	PZE -32+BITS PZE CODE.	TSTCAP37	
O	50115	000000050114	D	MZE NO+65 MZE CODE.	TSTCAP38	
U	50116	0602000C0001	SLW	\$+1 \$ FOR THIS LOCATION	TSTCAP39	
U	50117	050000077777	CLA	2*\$-1 \$ TEST.	TSTCAP40	
OU	50120	000000000000	MTH	C/3 DIVISION IN ADDRESS	TSTCAP41	
O	50121	0000000050154	Z	PON (YES-COUNT)/3+F PON WITH DIVISION IN ADDRESS ARITHMETIC.	TSTCAP42	
O	50122	060100077762	STO	(C-FLAG)/2 DIVISION WITH NEGATIVE ANSWER.	TSTCAP43	
U	50123	060200030657	SLW	-8*BITS+\$#1+7*Z USE OF \$ AS A SYMBOL.	TSTCAP44	
OU	50124	000000000014	ARF	(\$-C)/5+Q \$,/, AND ILLEGAL OPCODE	TSTCAP45	
O	50125	000000050115	*	REMARK CARD WITH * IN COLUMN 1.	TSTCAP46	
O	50126	000000050126	BLNK	BLNK BLANK OPCODE.	TSTCAP47	
OU	50127	000000000000	(\$=*)	NOP UNDEF S, O, AND U FLAGS.	TSTCAP48	
OU	50130	000000000000	Q	HOL 5THIS IS HOLLERITH INFO.	TSTCAP49	
O	50131	000000050132	CLA#	FLAG USE OF FLAGGED INSTRUCTION.	TSTCAP50	
O	50132	060100031043	FLAG	STO =1139 LITERAL.	TSTCAP51	
O	50133	050000031043	CLA	=1139 SAME LITERAL.	TSTCAP52	
OU	50134	000000000000	*	LAC# =5597.0 E, S, AND F FLAGS.	TSTCAP53	
O	50135	000000050121	TNX	Z,3,5 TAG AND DECREMENT FIELD.	TSTCAP54	
O	50136	030000050212	FAD	(YES-COUNT)*(NO-LOOP)+START,2+3*(NO-LOOP)	TSTCAP55	
O	50137	000000000021	DZ	OCT 17,13,-44,Q,13,,1 OCT PSEUDO-OP.	TSTCAP56	
O	50140	024100050132	FDP	FLAG A DIVIDE INSTRUCTION.	TSTCAP57	
U	50141	060100050113	STO	MUL+UNDEF FOLLOWED BY A STORE.	TSTCAP58	
O	50142	000000050030	START	EQU COUNT+3*(NO-LOOP) PROPER USE OF EQU.	TSTCAP59	
O	50143	002000050142	A	TRA START USE OF SYMBOL DEFINED BY EQU.	TSTCAP60	
O	50144	000000000126	PI	EQU END-CCMP PHASE ERROR.	TSTCAP61	
O	50145	002000050144	B	TRA PI USE OF SYMBOL WITH PHASE ERROR.	TSTCAP62	
O	50146	0C00000C0005	E	BSS 5 PROPER BSS.	TSTCAP63	
O	50147	000000000003	F	BSS LOOP-COUNT PROPER SYMBOLIC DEFINITION OF BSS.	TSTCAP64	
O	50150	000000000002	LCOP01	BSS CALL-F IMPROPER BSS, PHASE ERROR.	TSTCAP65	
O	50151	000000050000	CALL	CALL COUNT,NO,C,YES LEGAL CALL MACRO.	TSTCAP66	
OU	50152	0000000C0000	CALL2	CALL ABLE,BAKER+2,CHRLY-5*(NO-LOOP)	TSTCAP67	
U	50153	050000000000	FOO	CLA \$ CHECK ILC AFTER BSS AND CALL.	TSTCAP68	
U		50000	END	END REM TEMPORARY STORAGE AREA BEGINS HERE.	TSTCAP69	
U				END COUNT+1*UNDEF FINALLY THE END.		

RETURN FROM CAP, ENTRY POINT IS 50000.

POST MORTEM OF SYMBOLIC PROGRAM.		
CAP	REM THE FOLLOWING ARE ALL LEGAL CAP INSTRUCTIONS.	TSTCAP00
	REM PROGRAM TO COUNT BITS IN AC.	TSTCAP01
COUNT	LDQ ZERO ZERO TEST CELLS	TSTCAP02
	STQ BITS ..	TSTCAP03
	LXA THSX COUNT 36 BITS.	TSTCAP04
LOOP	LBT BIT OR NO.	TSTCAP05
	TRA NO NO BIT.	TSTCAP06
YES	SLW WORD BIT, SAVE AC,	TSTCAP07
	CAL BITS AND INCREMENT COUNT.	TSTCAP08
	ACL ONE ..	TSTCAP09
	SLW BITS ..	TSTCAP10
	CAL WORD RESTORE AC.	TSTCAP11
	LGR 1 NEXT BIT.	TSTCAP12
NO	TIX LCOP INDEX.	TSTCAP13
	CAL BITS GET COUNT.	TSTCAP14
DONE	CCTL 002100070000 STOP WITH TRANSFER TO 70000 OCTAL.	TSTCAP15
	REM STORAGE.	TSTCAP16
ZERO	OCTL 00000C00000000 TRUE ZERO.	TSTCAP17
ONE	INT 1 INCREMENT OF ONE.	TSTCAP18
THSX	LAS 36 ADDRESS IS 36.	TSTCAP19
	REM DATA.	TSTCAP20
BITS	INT 0 STORAGE FOR BIT COUNT.	TSTCAP21
WORD	INT 0 TEMPORARY STORAGE FOR AC.	TSTCAP22
	REM TEST OF CAP PSEUDO-OPS, AND FLAGS.	TSTCAP23
	ILCD 8 ILLEGAL OPCODE.	TSTCAP24
	TRA UNDEF UNDEFINED SYMBCL.	TSTCAP25
	INT 1,2,-7,13A3,9 ERROR IN INTOP.	TSTCAP26
	WMW AEN ILLEGAL OPCODE AND UNDEFINED SYMBCL.	TSTCAP27
	COMP NO = YES + LOOP	TSTCAP28
COMP	COMP Z = A * B * C / D / E / FLAG	TSTCAP29
	TRA COMP USE OF SYMBOL DEFINED BY COMP.	TSTCAP30
	COMP COUNT,1 = LCPO01,2 - START,4	TSTCAP31
	COMP DZ = (E+Z*(D+Z*(C+Z*(B+Z*A)))) + FOO	TSTCAP32
	TIX COUNT+3*((NO-YES)*Z+1)*(LOOP-COUNT)+8*(ZERO-DONE)+8	TSTCAP33
	REM TEST OF PROPOSED MODIFICATIONS TO CAP.	TSTCAP34
MUL	INT 0 MULTIPLY DEFINED SYMBOL.	TSTCAP35
MUL	INT 0 MULTIPLY DEFINED SYMBOL.	TSTCAP36
C	PZE -32BITS PZE CODE.	TSTCAP37
D	MZE NO+65 MZE CODE.	TSTCAP38
	SLW \$+1 \$ FOR THIS LOCATION	TSTCAP39
	CLA 2*\$-1 \$ TEST.	TSTCAP40
	MTH C/3 DIVISION IN ADDRESS	TSTCAP41
Z	PON (YES-COUNT)/3+F PON WITH DIVISION IN ADDRESS ARITHMETIC.	TSTCAP42
	STO (C-FLAG)/2 DIVISION WITH NEGATIVE ANSWER.	TSTCAP43
	SLW -8*BITS+\$*1+7*Z USE OF \$ AS A SYMBOL.	TSTCAP44
	ARF (\$-C)/5+Q \$,, AND ILLEGAL CPCODE	TSTCAP45
*	REMARK CARD WITH * IN COLUMN 1.	TSTCAP46
BLNK	BLNK BLANK OPCODE.	TSTCAP47
(\$=*)	NOP UNDEF S, O, AND U FLAGS.	TSTCAP48
Q	HOL 5THIS IS HOLLERITH INFO.	TSTCAP49
	CLA# FLAG USE OF FLAGGED INSTRUCTION.	TSTCAP50
FLAG	STO =1139 LITERAL.	TSTCAP51
	CLA =1139 SAME LITERAL.	TSTCAP52
*	LAC# =5597.0 E, S, AND F FLAGS.	TSTCAP53
	TNX Z,3,5 TAG AND DECREMENT FIELD.	TSTCAP54
	FAD (YES-COUNT)*(NO-LLOOP)+START,2+3*(NO-LOOP)	TSTCAP55
DZ	OCT 17,13,-44,Q,13,,1 OCT PSEUDO-OP.	TSTCAP56
	FDP FLAG A DIVIDE INSTRUCTION.	TSTCAP57

START	STO MUL+UNDEF	FOLLOWED BY A STORE.	TSTCAP58
A	EQU COUNT+3*(NO-LOOP)	PROPER USE OF EQU.	TSTCAP59
PI	TRA START	USE OF SYMBOL DEFINED BY EQU.	TSTCAP60
B	EQU END-COMP	PHASE ERROR.	TSTCAP61
E	TRA PI	USE OF SYMBOL WITH PHASE ERROR.	TSTCAP62
F	BSS 5	PROPER BSS.	TSTCAP63
LCOP01	BSS LOOP-COUNT	PROPER SYMBOLIC DEFINITION OF BSS.	TSTCAP64
	BSS CALL-F	IMPROPER BSS, PHASE ERROR.	TSTCAP65
CALL	CALL COUNT,NO,C,YES	LEGAL CALL MACRO.	TSTCAP66
CALL2	CALL ABLE,BAKER+2,CHRLY-5*(NO-LOOP)		TSTCAP67
FOO	CLA \$	CHECK ILC AFTER BSS AND CALL.	TSTCAP68
END	END COUNT+1*UNDEF	FINALLY THE END.	TSTCAP69

POST MORTEM OF COLLATION TAPE.

CAP	REM THE FOLLOWING ARE ALL LEGAL CAP INSTRUCTIONS.	TSTCAP00
	REM PROGRAM TO COUNT BITS IN AC.	TSTCAP01
COUNT	LDQ ZERO ZERO TEST CELLS	TSTCAP02
	STQ BITS ..	TSTCAP03
LLOOP	LXA THSX COUNT 36 BITS.	TSTCAP04
	LBT BIT OR NO.	TSTCAP05
YES	TRA NO NO BIT.	TSTCAP06
	SLW WORD BIT, SAVE AC,	TSTCAP07
	CAL BITS AND INCREMENT COUNT.	TSTCAP08
	ACL ONE ..	TSTCAP09
	SLW BITS ..	TSTCAP10
	CAL WORD RESTORE AC.	TSTCAP11
	LGR 1 NEXT BIT.	TSTCAP12
NO	TIIX LOOP INDEX.	TSTCAP13
	CAL BITS GET COUNT.	TSTCAP14
DCONE	OCTL 0021C0070000 STOP WITH TRANSFER TO 70000 OCTAL.	TSTCAP15
	REM STORAGE.	TSTCAP16
ZERO	CCTL 000000000000 TRUE ZERO.	TSTCAP17
ONE	INT 1 INCREMENT OF ONE.	TSTCAP18
THSX	LAS 36 ADDRESS IS 36.	TSTCAP19
	REM DATA.	TSTCAP20
BITS	INT 0 STORAGE FOR BIT COUNT.	TSTCAP21
WORD	INT 0 TEMPORARY STORAGE FOR AC.	TSTCAP22
	REM TEST OF CAP PSEUDO-OPS, AND FLAGS.	TSTCAP23
	ILCD 8 ILLEGAL OPCODE.	TSTCAP24
	TRA UNDEF UNDEFINED SYMBOL.	TSTCAP25
	INT 1,2,-7,13A3,9 ERROR IN INTOP.	TSTCAP26
	WMW AEN ILLEGAL OPCODE AND UNDEFINED SYMBCL.	TSTCAP27
	COMP NO = YES + LOOP	TSTCAP28
	CLA YES	
	FAD LOOP	
	STO NO	
COMP	COMP Z = A * B * C / D / E / FLAG	TSTCAP29
	LDQ A	
	FMP B	
	XCA	
	FMP C	
	FDP D	
	XCA	
	FDP E	
	XCA	
	FDP FLAG	
	STQ TEM	
	CLA TEM	
	STO Z	
	TRA COMP USE OF SYMBOL DEFINED BY COMP.	TSTCAP30
COMP	COUNT,1 = LOOPC1,2 - START,4	TSTCAP31
	CLA LOOPC1,2	
	FSB START,4	
	STO COUNT,1	
	COMP DZ = (E+Z*(D+Z*(C+Z*(B+Z*A)))) + FCO	TSTCAP32
	LDQ Z	
	FMP A	
	STO TEM	
	CLA B	
	FAD TEM	
	STO TEM+1	
	LDQ Z	

FMP	TEM+1	
STO	TEM+2	
CLA	C	
FAD	TEM+2	
STO	TEM+3	
LDQ	Z	
FMP	TEM+3	
STO	TEM+4	
CLA	D	
FAD	TEM+4	
STO	TEM+5	
LDQ	Z	
FMP	TEM+5	
STO	TEM+6	
CLA	E	
FAD	TEM+6	
STO	TEM+7	
CLA	TEM+7	
FAD	FOO	
STO	DZ	
TIX	COUNT+3*(((NO-YES)*Z+1)*(LOOP-COUNT)+8*(ZERO-DONE)+8)	TSTCAP33
REM	TEST OF PROPOSED MODIFICATIONS TO CAP.	TSTCAP34
MUL	INT 0 MULTIPLY DEFINED SYMBOL.	TSTCAP35
MUL	INT 0 MULTIPLY DEFINED SYMBOL.	TSTCAP36
C	PZE -32+BITS PZE CODE.	TSTCAP37
C	MZE NC+65 MZE CODE.	TSTCAP38
SLW	\$+1 \$ FOR THIS LOCATION	TSTCAP39
CLA	2*\$-1 \$ TEST.	TSTCAP40
MTH	C/3 DIVISION IN ADDRESS	TSTCAP41
Z	PON (YES-COUNT)/3+F PON WITH DIVISION IN ADDRESS ARITHMETIC.	TSTCAP42
STO	(C-FLAG)/2 DIVISION WITH NEGATIVE ANSWER.	TSTCAP43
SLW	-8*BITS+\$+1+7*Z USE OF \$ AS A SYMBOL.	TSTCAP44
ARF	(\$-C)/5+Q \$,/, AND ILLEGAL OPCODE	TSTCAP45
* REMARK CARD WITH * IN COLUMN 1.		
BLNK	BLNK BLANK OPCODE.	TSTCAP46
(\$==/	NOP UNDEF S, O, AND U FLAGS.	TSTCAP47
Q	HOL 5THIS IS HOLLERITH INFO.	TSTCAP48
FLAG	CLA* FLAG USE OF FLAGGED INSTRUCTION.	TSTCAP49
FLAG	STO =1139 LITERAL.	TSTCAP50
	CLA =1139 SAME LITERAL.	TSTCAP51
*	LAC* =5597.0 E, S, AND F FLAGS.	TSTCAP52
	TNX Z,3,5 TAG AND DECREMENT FIELD.	TSTCAP53
	FAD (YES-COUNT)*(NO-LOOP)+START,2+3*(NO-LOOP)	TSTCAP54
DZ	OCT 17,13,-44,Q,13,,1 OCT PSEUDO-OP.	TSTCAP55
	FDP FLAG A DIVIDE INSTRUCTION.	TSTCAP56
	STO MUL+UNDEF FOLLOWED BY A STORE.	TSTCAP57
START	EQU COUNT+3*(NC-LOOP) PROPER USE OF EQU.	TSTCAP58
A	TRA START USE OF SYMBOL DEFINED BY EQU.	TSTCAP59
PI	EQU END-COMP PHASE ERROR.	TSTCAP60
B	TRA PI USE OF SYMBOL WITH PHASE ERROR.	TSTCAP61
E	BSS 5 PROPER BSS.	TSTCAP62
F	BSS LOOP-COUNT PROPER SYMBOLIC DEFINITION OF BSS.	TSTCAP63
LOOP01	BSS CALL-F IMPROPER BSS, PHASE ERROR.	TSTCAP64
CALL	CALL CCUNT,NO,C,YES LEGAL CALL MACRO.	TSTCAP65
CALL2	CALL ABLE,BAKER+2,CHRLY-5*(NO-LOOP)	TSTCAP66
FOO	CLA \$ CHECK ILC AFTER BSS AND CALL.	TSTCAP67
TEM	REM TEMPORARY STORAGE AREA BEGINS HERE.	TSTCAP68
END	END COUNT+1*UNDEF FINALLY THE END.	TSTCAP69

POST MORTEM OF CONSOLE.

S,Q,P= 0,0,0

AC = 000000050000

MQ = 606060600500

SI = 0000C0000007

IR1= 27624

IR2= 1

IR4= 73226

OCTAL DUMP OF CAP FOLLOWS.

144	TTR 002100000213	TTR 002100000327	TTR 002100007767	HTR 000000000000	TIX 232147606060	SXA 063400400164
152	STO 060100000171	LDI 044100000200	TSX 007400400144	LFT 405400000001	TRA 002000000166	STI 060400000172
160	LDI 044100000200	CLA 050000000171	TSX 007400400145	OSI 044200000172	AXT 077400473226	TRA 002000400001
166	TSX 007400400146	HTR 000005000173	TRA 002000000157	HTR 000000050000	HTR 000000000000	TCO 006270442246
174	MZE 436063212243	TIX 256062317125	TXN 602567232525	TIX 242524336060	HTR 0C0000000000	

OCTAL DUMP OF PASS1 FOLLOWS.

201	TTR 002100007615	TTR 002100007553	TTR 002100001353	TTR 002100002465	TTR 002100001375	TTR 002100003217
207	TTR 002100003042	TTR 002100007673	HTR 000000000000	MZE 472162620160	SXA 063400400277	PAC 073700100000
215	TRA 002000000220	TSX 007400400201	HTR 000000000301	TSX 007400400202	HTR 000000000301	CAL 450000000302
223	TSX 007400400203	AXT 077400400012	LAS 43400040C246	TRA 002000000230	TRA 002060400247	TIX 200002400225
231	CAL 450000000301	TSX 007400400204	TXI 177777100216	HTR 00000512544	TRA 002000000246	HTR 000000314563
237	TRA 002000000247	HTR 000046236343	TRA 002000000263	HTR 000023464447	TRA 002000000254	HTR 000000254524
245	TRA 002000000266	TRA 002000000216	CAL 450000000301	TSX 007400400204	TSX 007400400205	HTR 000000000301
253	TRA 002000000216	CAL 450000000301	TSX 007400400204	TSX 007400400201	HTR 000000000301	TSX 007400400206
261	HTR 000000000301	TRA 002000000220	CAL 450000000301	TSX 007400400204	TXI 177777100216	TSX 007400400207
267	TSX 007400400201	HTR 000000000301	CAL 450000000301	TSX 007400400204	TSX 007400400210	PXA 075400100000
275	PAC 073700400000	PXA 075400400000	AXT 077400477624	TRA 002000400001	TXN 602545246060	TXN 602545246060
303	TIX 234664456320	PZE 015464452425	TIX 266060263145	TIX 214343706063	TXH 302560254524	TXH 336060606060
311	TXN 606060606060	TNX 606060606060	TNX 606060606060	TNX 606060606060	TNX 636263232147	PZE 061160606060

OCTAL DUMP OF PASS2 FOLLOWS.

317	TTR 002100001121	TTR 002100007703	TTR 002100001353	TTR 00210000644	TTR 002100001230	TTR 002100007767
325	HTR 000000000000	MZE 472162620260	SXA 063400400455	PAC 073700100000	CAL 450060000317	ARS 077100000022
333	STA 062100000356	ACL 036160000317	STA 062100000357	STA 062100000366	LDI 044100000631	STZ 060000000602
341	OSI 044200000602	STI 060400000602	LDI 044100000631	SXA 063400100576	TSX 007400400320	HTR 000000000613
347	CAL 450000000614	TSX 007400400321	AXT 077400400012	LAS 4340004040407	TRA 002000000355	TRA 002060400410
355	TIX 200002400352	AXT 077400400104	LAS 434000401226	TRA 002000000362	TXI 177777400366	TIX 200002400357
363	SIR 005500000002	PXD 475400000000	TRA 002000000367	CAL 450000401226	SLW 060200100000	TSX 007400400322
371	HTR 000000000613	ORS 460200100000	TSX 007400400461	TXI 177777100341	HTR 0000000512544	TRA 002000000407
377	HTR 000000314563	TRA 002000000411	HTR 00046236343	TRA 002000000415	HTR 000023464447	TRA 002000000430
405	HTR 000000254524	TRA 002000000432	TSX 007400400512	TRA 002000000341	TSX 007400400323	HTR 000000000613
413	TSX 007400400461	TRA 002000000341	PXD 475400000000	AXT 077400200002	AXT 077400400006	LDQ 056000200617
421	RQL 477300000003	LGL 476300000003	TSX 200001400421	TIX 200001200417	SLW 060200100000	TSX 007400400461
427	TXI 177777100341	TSX 007400400512	TRA 002000000341	TSX 007400400322	HTR 000000000613	STD 060100000577
435	TSX 007400400523	SLW 060200000606	CLA 050000000577	TSX 007400400544	LDQ 056000000631	LGR 476500000022
443	ORA 450100000635	SLW 060200000611	XCL 413000000000	ORA 450100000634	SLW 060200000612	CAL 450000000636
451	SLW 060200000607	SLW 060200000610	TSX 007400400324	HTR 000023000606	AXT 077400477616	CLA 050000000577
457	OSI 044200000602	TRA 002000400001	SXA 063400400510	TSX 007400400523	SLW 060200000606	LAC 053500400576
465	PXA 075400400000	TSX 007400400544	SLW 060200000607	LXA 053400400576	CAL 450000400000	TSX 007400400555
473	STQ 460000000601	LGR 476500000022	ORA 450100000635	SLW 060200000610	STQ 460000000611	CAL 450000000601
501	LDQ 056000000631	LGR 476500000022	XCL 413000000000	ORA 450100000634	SLW 060200000612	TSX 007400400324
507	HTR 000023000606	AXT 077400477405	TRA 002000400001	SXA 063400400521	AXT 077400400005	CAL 450000000636

515	SLW 060200400613	TIX 200001400515	TSX 007400400324	HTR 000023000606	AXT 077400477371	TRA 002000400001
523	SXA 063400400542	TOV 014000000525	PIA 404600000000	LGR 476500000003	CAL 450000000633	AXT 077400400003
531	TQP 016200000534	ALS 076700000006	ACL 036100400606	RQL 477300000001	TIX 200001400531	LDQ 056000000636
537	TOV 014000000542	LGL 476300000006	TNO 414000000540	AXT 077400477343	TRA 002000400001	SXA 063400400553
545	LGR 476500000017	CAL 450000000632	AXT 077400400005	ALS 076700000003	LGL 476300000003	TIX 200001400550
553	AXT 077400477340	TRA 002000400001	SXA 063400400574	XCL 413000000000	PXD 475400000000	AXT 077400400006
561	ALS 076700000003	LGL 476300000003	TIK 200001400561	SLW 060200000600	PXD 475400000000	AXT 077400400006
567	ALS 076700000003	LGL 476300000003	TIK 200001400567	XCL 413000000000	CAL 450000000600	AXT 077400477306
575	TRA 002000400001	HTR 000000027624	HTR 000000050000	PZE 000500000000	HTR 000000000000	HTR 000000000007
603	HTR 000000000025	HTR 000000000046	HTR 000000000064	TNX 606460606060	TNX 606060606060	TNX 606060606060
611	TNX 60606060500	HTR 000000606060	TNX 602545246060	TNX 602545246060	TIX 234664456320	PZE 015464452425
617	TIX 266060263145	TIX 214343706063	TXH 302560254524	TXH 336060606060	TNX 606060606060	TNX 606060606060
625	TNX 606060606060	TNX 606060606060	TNX 636263232147	PZE 061160606060	HTR 000000000000	HTR 000000000000
633	HTR 000000000160	HTR 000000606060	TNX 606060000000	TNX 606060606060	HTR 000000000000	HTR 000000000000

OCTAL DUMP OF VAREVL FOLLOWS.

637	TTR 002100002510	TTR 002100001423	TTR 002100001445	HTR 000000000000	STR 516551256543	SXA 063400400667
645	SXA 063400200670	SXA 063400100671	CAL 450000400001	ACL 036100001113	STA 062100000722	STZ 060000001104
653	STZ 060000001105	MSE 476000000141	NOP 076100000000	AXT 077400200012	AXT 077400100007	LDQ 056060000722
661	STQ 460000001111	TSX 007400400711	PAX 073400400000	TPL 012000000666	PAC 073700400000	PXA 075400400000
667	AXT 077400477346	AXT 077400200001	AXT 077400127624	TRA 002000400002	PXD 475400000000	NZT 452000001105
675	TRA 002000400001	STZ 060000001104	STZ 060000001105	MSE 476000000141	NOP 076100000000	TXI 100001400703
703	SXA 063400400667	SXA 063400200670	SXA 063400100671	AXT 077400100002	AXT 077400200012	TRA 002000000662
711	SXA 063400401102	STZ 060000001100	STZ 060000001101	STZ 060000001110	STZ 060000001107	AXT 077400400025
717	SXA 063400401103	TRA 002000000737	AXT 077400100006	LDQ 056000200627	PXD 475400000000	LGL 476300000006
725	STQ 460000001111	AXT 077400400025	LAS 434000400775	TRA 002000000732	TRA 002000000775	TIX 200003400727
733	LGR 476500000006	CAL 450000001107	LGL 476300000006	SLW 060200001107	ZET 052000001104	TRA 002000000745
741	LDO 056000001111	TIX 200001100723	TIX 200001200721	STL 462500001104	AXT 077400400003	CAL 450000001114
747	TRA 0C2000000775	HTR 000000000020	TRA 002000001031	TRA 002000001047	HTR 000000000040	TRA 002000001034
755	TRA 002000001047	HTR 000000000054	TRA 002000001037	TRA 002000001054	HTR 000000000060	HTR 000060000762
763	TRA 002000001076	HTR 000000000073	HTR 000060000765	TRA 002000001070	HTR 000000000074	HTR 000060000770
771	TRA 002000001055	HTR 000000000034	HTR 000060000773	TRA 002000001064	SXA 063400401106	LAS 434000001115
777	TRA 002000001001	TRA 002000001055	ZET 052000001110	TRA 002000001026	CAL 450000001107	ANA 432000001116
1005	TZE 010000001012	CAL 450000001107	TSX 007400400637	STO 060100001110	TRA 002000001026	LDQ 056000001107
1013	AXT 077400400006	PXD 475400000000	LGL 476300000006	STO 060100001112	CLA 050000001110	ALS 076700000002
1021	ADD 040000001110	ALS 076700000001	ADD 040000001112	STO 060100001110	TIX 200001401014	STZ 060000001107
1027	LXA 0534C0401103	TRA 002000400776	CLA 050000001110	STO 060100001101	TRA 002000001043	CLS 050200001110
1035	STC 060100001101	TRA 002000001043	LDQ 056000001110	MPY 020000001101	STQ 460000001101	TRA 002000001043
1043	LXA 053400401106	SXA 063400401103	STZ 060000001110	TRA 002000400777	CLA 050000001100	ADD 040000001101
1051	STO 060100001100	STZ 060000001101	TRA 002000000737	TRA 002000000737	TSX 007400400640	HTR 000004001100
1057	TSX 007400400711	STO 060100001110	TSX 007400400641	HTR 0000C04001100	TRA 002000000737	CLA 050000001100
1065	ADD 040CC00001101	LXA 053400401102	TRA 002000400001	STL 462500001105	STL 462500001104	PSE 07600000141
1073	SXA 0634C0100706	SXA 063400200707	TRA 002000001064	STL 462500001104	TRA 002000001064	HTR 000000050000
1101	HTR 000000000000	HTR 000000077116	HTR 000000000014	HTR 0000000001077	HTR 000000000000	HTR 000000000014
1107	HTR 0000C0000000	HTR 000000000000	TXN 602631450000	HTR 000000000001	HTR 000000000014	HTR 000000000034

OCTAL DUMP OF OPTBL FOLLOWS.

1117	HTR 000000000000	MZE 464763224360	PZE 000104001122	HTR 000000212343	ACL 036100000000	HTR 000000214521
1125	ANA 432000000000	HTR 000000232143	CAL 450000000000	HTR 000000233062	PSE 076000000002	HTR 000000234321
1133	CLA 050000000000	HTR 000000234362	CLS 050200000000	HTR 000000234644	PSE 076000000006	HTR 000000262124
1141	FAD 030000000000	HTR 000000262447	FDP 024100000000	HTR 000000264447	FMP 026000000000	HTR 000000266222
1147	FSB 030200000000	HTR 000000432123	LAC 053500400000	HTR 000000432162	LAS 434000000000	HTR 000000432263
1155	PSE 076000000001	HTR 000000432450	LDQ 056000000000	HTR 000000432743	LGL 476300000000	HTR 000000432751
1163	LGR 476500000000	HTR 000000436721	LXA 053400400000	HTR 000000465121	DRA 450100000000	HTR 000000472263
1171	MSE 476000000001	HTR 000000515043	RQL 477300000000	HTR 000000624366	SLW 060200000000	HTR 000000626346
1177	STO 060100000000	HTR 000000626350	STQ 460000000000	HTR 000000626721	SXA 063400400000	HTR 000000633167
1205	TIX 200001400000	HTR 000000634431	TMI 412000000000	HTR 000000634743	TPL 012000000000	HTR 000000635047
1213	TQP 016200000000	HTR 000000635121	TRA 002000000000	HTR 000000636267	TSX 007400400000	HTR 000000637125
1221	TZE 010000000000	HTR 000000672321	XCA 013100000000	HTR 000000672343	XCL 413000000000	

OCTAL DUMP OF INTOP FOLLOWS.

1226	HTR 000000000000	TXH 314563464760	SXA 063400401340	SXA 063400201341	SXA 063400101314	CAL 450000400001
1234	ACL 036100001350	STA 062100001242	STZ 060000001343	STZ 060000001345	STZ 060000001346	AXT 077400200012
1242	LDQ 056000200627	AXT 077400400006	PXD 475400000000	LGL 476300000006	LAS 434000001347	TRA 002000001264
1250	TRA 002000001302	STL 462500001346	STO 060100001344	CLA 050000001343	ALS 076700000002	ADD 040000001343
1256	ALS 0767C0000001	ACL 036100001344	STO 060100001343	TIX 200001401244	TIX 200001201242	TRA 002000001330
1264	AXT 077400100010	LAS 434000101302	TRA 002000001270	TRA 0020060101303	TIX 200002101265	TRA 002000001302
1272	HTR 000000000020	TRA 002000001305	HTR 000000000040	TRA 002000001310	HTR 000000000073	TRA 002000001314
1300	HTR 000000000060	TRA 002000001330	SIR 005500000004	STL 462500001345	TRA 002000001261	ZET 052000001346
1306	TRA 002000001302	TRA 002000001261	ZET 052000001346	TRA 002000001302	CLS 050200001343	TRA 002000001260
1314	AXT 077400127665	CLA 050000001343	ALS 076700000022	ZET 052000001345	PXD 475400000000	STZ 060000001345
1322	STZ 060100100000	STZ 060000001343	STZ 060000001346	TIX 17777101326	SXA 063400101314	TRA 002000001261
1330	LXA 053400101314	CLA 050000001343	ALS 076700000022	ZET 052000001345	PXD 475400000000	STZ 060000001345
1336	STO 0601C0100000	TIX 17777101340	AXT 077400477367	AXT 07740C200001	TRA 002000400002	HTR 00C0000000000
1344	HTR 000000000000	HTR 000000000000	HTR 000000001252	HTR 000000000012	HTR 000000000014	

OCTAL DUMP OF SCAN FOLLCWS.

1351	HTR 000000000000	TIX 234644442160	SXA 063400401372	XCL 413000000000	AXT 077400400006	STZ 060000001374
1357	PXD 475400000000	LGL 476300000006	LAS 434000002460	TRA 002000001364	TRA 002000001370	LGR 476500000006
1365	CAL 450000001374	LGL 476300000006	SLW 060200001374	TIX 200001401357	CAL 450000001374	AXT 07740477430
1373	TRA 002004000001	HTR 000000254524	SXA 063400401420	SXA 063400201421	CAL 450000400001	ACL 036100002457
1401	STA 062100001404	AXT 077400400012	AXT 077400200006	LDQ 056000400315	PXD 475400000000	LGL 476300000006
1407	LAS 434000002461	TRA 002000001415	TXI 17777101415	LAS 434000002460	TRA 002000001415	TRA 002000001417
1415	TIX 200001201405	TIX 200001401403	TXI 17777101420	AXT 077400477527	AXT 077400200116	TRA 002000400002
1423	SXA 063400401442	SXA 063400201443	CAL 450000400001	PDX 473400200000	PXA 075400200000	ACL 036100400001
1431	STA 062100001433	AXT 077400400764	CAL 450000201104	SLW 060200402457	TIX 200001401440	SIL 405500000002
1437	TRA 002000001442	TIX 200001201433	SXA 063400401432	AXT 077400476723	AXT 077400200011	TRA 002000400002
1445	SXA 063400401470	SXA 063400201471	CAL 450000400001	STD 062200001466	ARS 077100000022	ACL 036100400001
1453	STA 062100001464	AXT 077400200001	LXA 053400401432	TXI 100001401457	TXL 700764401462	SIL 405500000004
1461	TRA 002000001470	CAL 450000402457	STZ 060000402457	SLW 060200201104	TXI 100001201466	TXL 70004201456
1467	SXA 063400401432	AXT 077400476717	AXT 077400200010	TRA 002000400002	HTR 000000000000	HTR 000000000000

.. FOLLOWING 498 CELLS ALL CONTAIN HTR 000000000000 ..

2457 HTR 000000000014 HTR 000000000060 HTR 000000000073

OCTAL DUMP OF SYMSTO FOLLOWS.

2462	TTR 0021C0001353	HTR 000000000000	TNX 627044272563	LAS 434000003035	TRA 002000002470	TRA 002000400001
2470	SXA 063400402506	TSX 007400402462	XCL 413000000000	PXA 075400100000	PAC 073700400000	PXA 075400400000
2476	LXD 453400402524	TXI 100002402500	TXL 700310402503	SIL 405500000001	TRA 002000002506	STQ 460000403035
2504	SLW 060200403036	SXD 463400402524	AXT 077400477506	TRA 002000400001	SXA 063400402522	LXD 453400402524
2512	LAS 434000403035	TRA 002000002515	TRA 002000002521	TIX 200002402512	PXD 475400000000	SIR 005500000001
2520	TRA 002000002522	CAL 450000403036	AXT 077400476771	TRA 002000400001	PZE 000106003035	HTR 000000000000

.. FOLLOWING 129 CELLS ALL CONTAIN HTR 000000000000 ..

2727	HTR 000000254524	HTR 000000050164	HTR 000000632544	HTR 00000050154	HTR 000000264646	HTR 000000050153
2735	PZE 002321434302	HTR 000000050152	HTR 000000050153	HTR 000000050151	MZE 434646470001	HTR 000000050150
2743	HTR 000000000026	HTR 000000050147	HTR 000000000025	HTR 000000050146	HTR 000000000022	HTR 000000050145
2751	HTR 0000000004731	HTR 000000050144	HTR 000000000021	HTR 000000050143	TCO 006263215163	HTR 000000050142
2757	HTR 0000000002471	HTR 000000050137	HTR 000000000054	HTR 000000050134	HTR 000026432127	HTR 000000050132
2765	HTR 000000000050	HTR 000000050130	TSX 007453135461	HTR 000000050127	HTR 000022434542	HTR 000000050126
2773	RFT 005451254421	HTR 000000050125	HTR 000000000071	HTR 000000050121	HTR 000000000024	HTR 000000050115
3001	HTR 000000000023	HTR 000000050114	HTR 0000000446443	HTR 000000050113	HTR 0000000446443	HTR 000000050112
3007	HTR 000023464447	HTR 000000050036	HTR 000066465124	HTR 000000050022	HTR 000022316362	HTR 000000050021
3015	HTR 000063306267	HTR 000000050020	HTR 0000000464525	HTR 000000050017	HTR 000071255146	HTR 000000050016
3023	HTR 000024464525	HTR 000000050015	HTR 000000004546	HTR 000000050013	HTR 0000000702562	HTR 000000050005
3031	HTR 000043464647	HTR 000000050003	PZE C02346644563	HTR 000000050000	TNX 606060606060	

OCTAL DUMP CF ENDOP FOLLOWS.

3036	TTR 002100002465	TTR 002100007615	HTR 000000000000	MZE 473165215160	NZT 452000003161	TRA 002000400001
3044	SXA 063400403054	CAL 450000003206	TSX 007400403036	TSX 007400403037	HTR 000000003056	LAC 053500403161
3052	SXD 463400403053	TXI 177770103054	AXT 077400477512	TRA 002000400001	TNX 606325446060	TNX 605125446060
3060	TNX 632544474651	TIK 215170606263	MZE 465121272560	TIK 215125216022	TIK 252731456260	TXH 302551253360
3066	TNX 606060606060	TXN 606060606060				
3074	SXA 063400403101	AXT 077400400013	TXN 600001403101	SLW 060200403177	SXA 063400403075	AXT 077400474365
3102	TRA 002000400001	SXA 063400403114	CAL 450000040001	SLW 060200003164	TSX 007400403037	HTR 000000003163
3110	TSX 007400403116	AXT 077400427667	TXI 177777403113	SXA 063400403111	AXT 077400474363	TRA 002000400002
3116	SXA 063400403125	AXT 077400400013	SXA 063400403075	AXT 077400400016	CAL 450000003203	SLW 060200403201
3124	TIK 200001403123	AXT 077400474670	TRA 002000400001	CLA 050000003160	LDQ 056000003160	ADD 040000003201
3132	STC 060100003160	CAS 034000003161	STO 060100003161	NOP 076100000000	XCA 013100000000	TNZ 410000003142
3140	CAL 450000003206	TRA 002000400001	CAS 034000003202	TRA 002000003150	TRA 002000003150	ALS 076700000006
3146	ORA 450100003205	TRA 002000400001	XCA 013100000000	PXD 475400000000	DVP 022100003202	RQL 477300000006
3154	STQ 460000003162	ORA 450100003162	ORA 450100003204	TRA 002000400001	HTR 000000000010	HTR 000000000010
3162	HTR 000000000000	TNX 606060606060				
3170	TNX 606060606060					
3176	TNX 606C60606060	TNX 606060606060				
3204	TNX 632544200000	TNX 632544200060	TNX 632544606060	HTR 000000000001	HTR 000000000012	TNX 606060606060

OCTAL DUMP OF COMPOP FOLLOWS.

3207	TTR 002100003111	TTR 002100003160	TTR 002100003116	TTR 002100003760	TTR 002100003074	TTR 002100003103
3215	HTR 000000000000	TIK 234644474647	SXA 063400403417	SXA 063400203420	PXA 075400100000	STA 062160003207
3223	CAL 450000400001	ACL 036100003745	STA 062100003241	STZ 060600003210	STZ 060000003425	CAL 450000003743
3231	SLW 060200003424	TSX 007400403211	AXT 077400400310	SXA 063400403333	TOV 014000003236	TRA 002000003237
3237	AXT 077400200012	AXT 077400100006	CAL 4500000200315	LAS 434000003751	TRA 002000003245	TRA 002000003272
3245	XCL 413000000000	PXD 475400000000	LGL 476300000006	STQ 460000003426	LAS 434000003747	TRA 002000003254
3253	TRA 002000003270	AXT 077400400007	LAS 434000403304	TRA 002000003260	TRA 002000003304	TIX 200001403255
3261	LGR 476500000006	CAL 450000003424	LGL 476300000006	TNO 414000003267	TSX 007400403332	CAL 450000003743
3267	SLW 060200003424	LDQ 056000003426	TIK 200001103246	TIX 200001203240	STL 462500003425	TRA 002000003304
3275	HTR 000000000020	HTR 000000000040	HTR 000000000054	HTR 000000000061	HTR 000000000074	HTR 000000000034
3303	HTR 000000000013	SLW 060200003427	CAL 450000003424	LAS 434000003743	TRA 002000003311	TRA 002000003317
3311	LDQ 056000003751	LGL 476300000006	TND 414000003312	TSX 007400403332	CAL 450000003743	SLW 060200003424
3317	ZET 052000003425	TRA 002000003343	CAL 450000003427	TSX 007400403332	CAL 450000003427	ERA 032200003744
3325	TNZ 410000003270	CAL 450000003333	ACL 036100003743	STA 062100003430	TRA 002000003270	SXA 063400403337
3333	AXT 077400400253	SLW 060200403743	TNX 600001403341	SXA 063400403333	AXT 077400474464	TRA 002000400001
3341	SIL 405500000010	TRA 002000003417	CAL 450000003333	STA 062100003431	TRA 002000003346	LXA 053400103431
3347	SXD 463400103364	LXA 053400103430	SXA 063400103432	TXI 177777103353	CAL 450000103743	TZE 010000003363
3355	LAS 434000003750	TRA 002000003360	TRA 002000003366	LAS 434000003746	TRA 002000003363	TRA 002000003370
3363	TXI 177777103364	TXH 300253103353	TRA 002000003401	SXA 063400103432	TRA 002000003363	SXD 463400103376
3371	STZ 060000103743	LXA 053400103432	STZ 060000103743	SXA 063400103376	TSX 007400403212	PZE 000256000306
3377	HTR 000000003743	TRA 002000003350	SXD 463400103406	LXA 053400103432	STZ 060000103743	SXA 063400103406
3405	TSX 007400403212	PZE 000253700307	HTR 000000003743	AXT 077400100310	CAL 450000103743	TZE 010000003415
3413	TSX 007400403213	TXI 177777103411	TSX 007400403214	TSX 606263466060	AXT 077400477520	AXT 077400200116
3421	CAL 450060003207	PAX 073400100000	TRA 002000040002	HTR 000000000001	HTR 0000000003274	HTR 000000000000
3427	TNX 606060606060	HTR 000000000307	HTR 000000000253	HTR 000000000307	TIX 247160606060	HTR 000000000000

.. FOLLOWING 198 CELLS ALL CONTAIN HTR 000000000000 ..

3743	HTR 000000000001	HTR 000000000013	HTR 000000000014	HTR 000000000034	HTR 000000000060	HTR 000000000074
3751	TNX 606060606060					

OCTAL DUMP OF EXPR FOLLOWS.

3752	TTR 002100004163	TTR 002100003074	TTR 002100003103	TTR 002100003127	HTR 000000000000	TIX 256747516060
3760	SXA 063400404136	SXA 063400204137	SXA 063400104140	CAL 450000400001	STD 062200004026	STD 062200004070
3766	STT 062500004143	STA 062100004037	PAX 073400100000	TXI 177777103772	SXA 063400104052	CAL 450000400002
3774	STA 062100004007	STA 062100004054	STA 062100004040	STA 062100004056	SUB 040200004150	STA 062100004132
4002	STZ 060000004144	STZ 060000004142	STZ 060000004145	STZ 060000004146	TRA 002000004007	CAL 450000103743
4010	TZE 010000004025	LAS 434000004154	TRA 002000004014	TRA 002000004031	LAS 434000004153	TRA 002000004017
4016	TRA 002000004031	LAS 434000004152	TRA 002000004022	TRA 002000004033	LAS 434000004151	TRA 002000004025

4024	TRA 002000004033	TXI 177777104026	TXH 300253104007	STL 462500004144	TRA 002000004033	STL 462500004146
4032	TRA 002000004025	NZT 452000004146	TRA C02000004042	SXD 463400104037	TSX 007400403752	PZE 00C256000253
4040	HTR 000000003743	STZ 060000004146	SXA 063400104037	NZT 452000004144	TRA 002000004025	TRA 002000004046
4046	STZ 060000004145	CAL 450000004151	SLW 060200004142	STL 462500004147	AXT 07740010306	STZ 060000004144
4054	CAL 450000103743	TZE 010000004067	STZ 060000103743	LAS 434000004152	TRA 002000004062	TRA 002000004073
4062	LAS 434000004151	TRA 002000004065	TRA 002000004073	TSX 007400403753	STL 462500004145	TXI 177777104070
4070	TXH 300253104054	STL 462500004144	TRA 002000004073	XCL 413000000000	CLA 050000004142	STQ 460000004142
4076	ZET 052000004147	TRA 002000004111	ERA 032200004151	TZE 010000004103	TRA 002000004106	TSX 007400403754
4104	TNX 602621246060	TRA 002000004125	TSX 007400403754	TXN 602662226060	TRA 002000004125	NZT 452000004145
4112	TRA 002000004125	STZ 060000004147	ERA 032200004151	TZE 010000004117	TRA 002000004122	TSX 007400403754
4120	TNX 602343216060	TRA 002000004125	TSX 007400403754	TXN 602343626060	TRA 002000004125	NZT 452000004144
4126	TRA 002000004067	ZET 052000004143	TRA 002000004136	TSX 007400403755	SLW 060200103742	TSX 007400403753
4134	TSX 007400403754	TNX 606263466060	AXT 077400474373	AXT 077400200001	AXT 077400100307	TRA 002000400003
4142	TIX 264646606060	HTR 0000000700000	HTR 000000004072	HTR 000000004067	HTR 000000000000	HTR 000000000000
4150	HTR 000000000001	HTR 000000000020	HTR 000000000040	HTR 000000000054	HTR 000000000061	
<b>OCTAL DUMP OF TERM FOLLOWS.</b>						
4155	TTR 002100003074	TTR 002100003103	TTR C02100003116	HTR 000000000000	TNX 632551446060	
4163	SXA 063400404310	SXA 063400204311	SXA 063400104312	STD 062200004214	PAX 073400100000	
4171	TXI 177777104172	CAL 450000400002	STA C62100004201	STA 062100004203	SUB 040200004315	STA 062100004274
4177	STA 062100004304	STZ 060000004314	CAL 450000103743	TZE 010000004213	STZ 060000103743	LAS 434000004317
4205	TRA 002000004207	TRA 002000004240	LAS 434000004316	TRA 002000004212	TRA 0020C0004216	TSX 007400404155
4213	TXI 177777104214	TXH 300256104201	TRA 002000004262	XCL 413000000000	CAL 450000004314	STQ 460000004314
4221	TZE 010000004225	ERA 032200004316	TZE 010000004230	TRA 002000004235	TSX 007400404156	TXN 604324506060
4227	TRA 002000004213	TSX 007400404156	TXN 60264476060	TSX 007400404156	TXN 606723216060	TRA 002000004213
4235	TSX 007400404156	TNX 602624476060	TRA 002000004213	XCL 413000000000	CAL 450000004314	STQ 460000004314
4243	TZE 010000004247	ERA 032200004316	TZE 010000004252	TRA 002000004255	TSX 007400404156	TXN 602343216060
4251	TRA 002000004213	TSX 007400404156	TNX 60264476060	TRA 002000004213	TSX 007400404156	TXN 602624476060
4257	TSX 007400404156	TNX 606723216060	TRA 002000004213	CAL 450000004314	TZE 010000004267	ERA 032200004316
4265	TZE 010000004271	TRA 002000004301	TSX 007400404157	TRA 002000004310	TSX 007400404156	TXN 60264476060
4273	TSX 007400404160	SLW 060200103742	TSX 007400404155	TSX 007400404156	TSX 007400404156	TRA 002000004310
4301	TSX 007400404160	TNX 602624476060	TSX 007400404160	SLW 060200103742	TSX 007400404155	TSX 007400404156
4307	TNX 606263506060	AXT 077400473742	AXT 077400200001	AXT 077400100256	TRA 002000400003	HTR 000000000054
4315	HTR 000000000001	HTR 000000000054	HTR C00000000061			
<b>OCTAL DUMP OF (MAIN) FOLLOWS.</b>						
4320	TTR 002100004331	TSX 007400404320	TXL 777777777777	TXL 777777777777	TXL 777777777777	
<b>OCTAL DUMP OF ASSEMBLED PROGRAM FOLLOWS.</b>						
50000	LDQ 056000050016	STQ 460000050021	LXA 053400450020	PSE 076000000001	TRA 002000050013	SLW 060200050022
50006	CAL 450000050021	ACL 036100050017	SLW 060200050021	CAL 450000050022	LGR 476500000001	TIX 200001450003
50014	CAL 450000050021	TTR 002100070000	HTR 000000000000	HTR 000001000000	LAS 434000000044	HTR 000000000000
50022	HTR 000000000000	HTR 000000000010	TRA 002000000000	HTR 000001000000	HTR 000002000000	MZE 400007000000
50030	HTR 000000000000	HTR 000001100000	HTR 000000000000	CLA 050000050005	FAD 030000050003	STD 060100050013
50036	LDQ 056000050143	FMP 026000050145	XCA 013100000000	FMP 026000050114	FDP 024100050115	XCA 013100000000
50044	FDP 024100050146	XCA 013100000000	FDP 024100050132	STQ 460000050154	CLA 050000050154	STD 060100050121
50052	TRA 002000050036	CLA 050000050150	FSB 030200050142	STO 060100050000	LDQ 056000050121	FMP 026000050143
50060	STD 060100050154	CLA 050000050145	FAD 030000050154	STO 060100050155	LDQ 056000050121	FMP 026000050155
50066	STD 060100050156	CLA 050000050114	FAD 030000050156	STD 060100050157	LDQ 056000050121	FMP 026000050157
50074	STD 060100050160	CLA 050000050115	FAD 030000050160	STD 060100050161	LDQ 056000050121	FMP 026000050161
50102	STD 060100050162	CLA 050000050146	FAD 030000050162	STD 060100050163	CLA 050000050163	FAD 030000050153
50110	STD 060100050137	TIX 200001440517	HTR 000000000000	HTR 000000000000	HTR 000000047761	HTR 000000050114
50116	SLW 060200000001	CLA 050000050177	HTR 000000000000	HTR 000000050154	STD 060100077762	SLW 060200030657
50124	HTR 000000000014	HTR 000000050115	HTR 000000050126	HTR 000000000000	HTR 000000000000	HTR 000000050132
50132	STD 060100031043	CLA 050000031043	HTR 000000000000	HTR 000000050121	FAD 030000050212	HTR 000000000021
50140	FDP 024100050132	STD 060100050113	HTR 000000050030	TRA 002000050142	HTR 000000000126	TRA 002000050144
50146	HTR 000000000005	HTR 000000000003	HTR 000000000002	HTR 000000050000	HTR 000000000000	CLA 050000000000

.. FOLLOWING 147 CELLS ALL CONTAIN HTR 000000000000 ..

50377 HTR 000000000000

END OF POST MORTEM.

END OF RUN.

## Appendix C

### SUGGESTED ADDITIONS TO CAP

This appendix contains a list of suggested modifications to CAP which a student may attempt to make when using CAP as a laboratory exercise. With each modification is given a "point" value which is an indication of the relative difficulty of modification.

The descriptions of many of these additions make reference to similar facilities in FAP (FORTRAN Assembly Program). Detailed information on the operation of the FAP facilities can be obtained from the FAP reference manual.\*

#### C.1 Symbols

- |  |           |
|--|-----------|
| 1. Add a test for multiply defined symbols and have CAP indicate with an M every operation involving a multiply defined symbol.      | 40 points |
| 2. Sort the symbol table after PASS1. Beware, this is a difficult modification. If it fails, nothing else in CAP will work properly. | 40 points |
| a. Interchange sort.   | 75 points |
| b. Radix sort or any sort which takes a time comparable to $N \log N$ .  | 75 points |
| 3. Use an exponential table lookup of the sorted symbol table for SYMGET.  | 50 points |
| 4. Add the pseudo-op EQU which is to operate as in FAP. Check for phase errors, and indicate with a P.                               | 35 points |
| 5. Add a test to flag the eleven illegal characters in the location field. Indicate with an S.                                       | 35 points |

#### C.2 Operation Field

- |   |           |
|---|-----------|
| 1. Add the three-letter prefix codes to CAP as in FAP (that is, PZE, MZE, PØN, etc., and blank field).  | 25 points |
| 2. Add the pseudo-op ØCT which accepts octal input in the same format as INT. Errors should be indicated with an E.                                   | 50 points |
| 3. Add the pseudo-op BSS as in FAP. Check for phase errors and indicate with a P.   | 40 points |
| 4. Add the pseudo-op HØL which accepts a card in the format of that in Figure C.1. n is a digit from 1 to 9, or if blank or 0 it is assumed to be 10. | 50 points |

\* Reference Manual, FORTRAN Assembly Program (FAP), IBM Publication C28-6235 (September, 1962).

$H\emptyset L$  should then use  $n$  words of storage for BCI words as the FAP pseudo-op BCI does.




Figure C.1. Format for  $H\emptyset L$  pseudo-operations.

- |  |           |
|--|-----------|
| 5. Add the pseudo-op CALL as in FAP except that:<br>a. No transfer vector is formed.<br>b. No error words are generated. | 50 points |
| 6. Allow for indirect addressing of operators with an asterisk.  | 25 points |
| 7. Use an exponential table lookup for the op-table. (Only 25 points if you did this for the symbol table also.)         | 75 points |
| 8. Improve the REM pseudo-op so that blanks replace the letters REM in the assembly listing.                             | 25 points |

#### C.3 Variable Field

- |  |           |
|--|-----------|
| 1. Modify VAREVL to accept a "/" as a break character for division. Be careful of signs.                           | 25 points |
| 2. Modify CAP to consider "\$" as a symbol (in the variable field) meaning "this location" as does the "*" in FAP. | 40 points |
| 3. Add decimal integer literals.   | 75 points |
| 4. Modify CAP to accept a tag field and remove the present tags in ØPTBL.  | 25 points |
| 5. Extend 4 so that CAP will also accept a decrement field and remove the present decrement in ØPTBL.              | 15 points |

#### C.4 Assembly Listing

- |   |           |
|---|-----------|
| 1. After the assembly listing, print a listing of symbols defined and their values.   | 40 points |
| 2. Bonus for literals: After the symbol table, print a listing of literals.   | 40 points |
| 3. Bonus for multiply defined symbols: Before the assembly listing, print a list of multiply defined symbols and their multiple values. | 40 points |
| 4. Bonus for symbol table: Form a table of undefined symbols and print after the assembly listing.                                      | 25 points |

- |  |                                     |
|--|-------------------------------------|
| 5. Print $\emptyset$ CT, INT, and CALL in detail mode.<br>6. Consider a * in column 1 to indicate a remark as in FAP.<br>7. Improve the assembly listing by separating the fields of the octal words, that is, CLA 64 should print as follows: | 25 points<br>25 points<br>65 points |
|--|-------------------------------------|

0500 00 0 00100

While TXL 1,1,1 should print

-3 00001 1 00001.

and INT -32 should print

-000040 000000

while H $\emptyset$ L 1 AB should print (if you have added H $\emptyset$ L)

602122606060

8. Print the nonerror indications A, T, and D where applicable. For example, the letter A means either "an instruction normally written with an address does not have one" or "an instruction normally written without an address has one." Similarly for T (tag) and D (decrement).

9. Add the nonerror indications F and Q. F means "a nonindirectly addressable instruction has an indirect address." Q means "the instruction ST $\emptyset$  (instead of the probable STQ) follows a divide instruction."

N.B.: In connection with these last three suggestions (and others) you may note that all operation codes are completely specified by the first four and the last four octal digits. Thus the middle four may be used in  $\emptyset$ PTBL for A, T, D, and F information and for controlling printing of instructions. These middle four digits may be masked out of the opcode before inserting in the assembled program.

### C.5 Compiler

1. Add diagnostics to C $\emptyset$ MP including  
 a. Nonzero reduction level.  
 b. Illegal grammar, that is,

multiple "=" signs

A = C(B)

A = C) + (B

A = C + (\*C)

2. Let column 7 be used for continuation cards in the same way that column 6 is in F $\emptyset$ RTRAN, or column 11 is in MAD.

3. Add the operator \*\* to C $\emptyset$ MP in such a way that A\*\*B would be compiled as

CLA A

LDQ B

TSX EXP3, 4

75 points

50 points

75 points

and the result from EXP3 is left in the AC. The operator \*\* should be given proper precedence.

4. Modify the compiler to accept integer and floating point constants and form these into a table , say,' LIT+00 to LIT+99 at the end of the program after TEM. To convert an integer of magnitude less than  $2^{27}$  to floating point, the following sequence of 7090 instructions will work: | 90 points

CLA INT	C(AC) = address integer
$\phi RA = \phi 233000000000$	Put in exponent
FAD = $\phi 233000000000$	Normalize
ST $\phi$ FLT	CFLT) = floating point equivalent of the integer INT

5. Improve the efficiency of the compiler by reducing the number of combinations | 50 - 100 points

ST $\phi$	TEM+n
CLA	TEM+n

and replacing the combinations

STQ	TEM+n
CLA	TEM+n

and

ST $\phi$	TEM+n
LDQ	TEM+n

with

XCA