# **MRX/OS System Generation**

Checklist

2260.003-01



Computer System
Products

#### May 1973 Edition

This edition is a major revision and obsoletes all previous editions. It documents the operating procedures at their level in MRX/OS Release 2.

Technical changes are marked with a bar in the outer margin. Changes due to subsequent releases will be documented in future publications bulletins or revisions.

Requests for copies of Memorex publications should be made to your Memorex representative or to the Memorex branch office serving your locality.

A reader's comment form is provided at the back of this publication. If the form has been removed, comments may be addressed to the Memorex Corporation, Publications Dept., 8941 — 10th Ave. No. (Golden Valley) Minneapolis, Minnesota 55427.

©1972, 1973 MEMOREX CORPORATION

### **PREFACE**

This document is a question-and-answer checklist that should be used to select system generation options. The answers to the questions comprise your input data to the system generation programs. Coding forms are printed after each question so that you can code your system generation options directly into this document and thereby create a permanent record of your particular system. Appendix C shows samples of completed Checklists. After each sample is an explanation of the coded statements as well as the defaults that have been selected. Appendix A lists the Control Language statements required to execute the system generation programs.

This Checklist should be used in conjunction with the MRX/OS System Generation Reference manual. Before you attempt to complete the Checklist, read this reference manual. Section 5 of the manual lists and explains possible answers to all of the Checklist questions. Material is presented in this section that is not discussed in the Checklist itself.

# TABLE OF CONTENTS

Section		Page
1	INTRODUCTION	1-1
	Preparing the System Generation Input Deck	1-1
	How to Use the Checklist	1-1
	Example 1	1-2
	Example 2	1-3
	Example 3	1-3
2	SYSTEM GENERATION CHECKLIST	2-1
	SYSGEN Control	2-1
	System Control	2-2
	Output Spooler	2-4
	I/O Devices	2-6
	Telecommunications	2-10
	Control Language Services	2-12
	Assembler Language	2-15
	COBOL Language	2-16
APPEND	IX A – CONTROL LANGUAGE STATEMENTS FOR SYSTEM	
	GENERATION	A-1
APPEND	IX B — DEVICE DESCRIPTIONS	B-1
APPEND	IX C – SYSTEM GENERATION EXAMPLES	C-1
APPEND	IX D – BYTE REQUIREMENTS FOR OPTIONAL FEATURES	D-1

## 1. INTRODUCTION

#### PREPARING THE SYSTEM GENERATION INPUT DECK

This Checklist has been designed to allow you to prepare your system generation input deck in three steps.

STEP 1. Read the Checklist questions and answer those that describe your hardware configuration and software system. Put your

answers on the coding lines provided with each question. When you finish answering the questions you will have coded

your input data for JOBONE.

STEP 2. Code the Control Language statements listed in Appendix A of this Checklist. Additional statements for SYSGEN-related

jobs appear in Appendix B of the MRX/OS System

Generation Reference manual.

STEP 3. Keypunch your answers to the Checklist questions and the Control Language statements. After you have keypunched

this information, arrange your input deck. Insert the Checklist data (answers to Checklist questions) after the

//DATA statement for JOBONE.

If you have previously initialized the disc pack that will contain your new resident operating system, you are now ready to execute the system generation programs. If you have not initialized your disc pack, do so before you execute the system generation programs. Use the Disc Initialize utility that is described in the MRX/OS Utility Programs Reference manual to perform the initialization procedure.

If at the completion of this procedure the console contains messages that list the tracks on your disc that are bad, make sure that your PCAT, CCAT, \$MSGLIB, and \$NUCLIB files are not assigned to cylinders containing the bad tracks.

#### HOW TO USE THE CHECKLIST

All of the questions (and possible answers) that appear in this Checklist are explained in Section 5 of the MRX/OS System Generation Reference manual. If you have any questions about a particular item in the Checklist, refer to Section 5. When you have finished keypunching your input data and you have initialized the disc pack that will contain your new resident operating system, refer to Section 4 of the System Generation Reference manual for the operating procedures that you should follow to perform your system generation.

When answering the Checklist questions, remember the following rules:

- 1. The choices to the questions are in boldface type. If the question applies to your system, select one of the choices; or you may choose not to answer and select the default value.
- 2. Default values in this Checklist are italicized. If a question has a default value, it is shown immediately after the coding choices. When you decide to accept the default value for a particular question, you need not code an answer for that question. If you define answers in addition to the default answers, you must also code the default answer.

If you do not have a telecommunications network in your system, you can ignore all the questions in the Telecommunications section. If you have no COBOL compiler, you can ignore all the questions in the COBOL Language section.

- 3. Begin your answer to each question in card column 6.
- 4. Always leave card column 5 blank.
- 5. Remember to keypunch the information that has been precoded in card columns 1 through 4 for every question that you answer. These numbers are used to identify the questions to the SYSGEN programs.
- 6. If you do not answer a question because it does not pertain to your system or because you have decided to accept the system generation default, do not keypunch the first four digits of that particular card.
- 7. If you want to add comments to your answers to the Checklist questions, leave one or more blank spaces after the last character of your answer and then code your comments.

The following examples show the types of questions and answers that appear on the Checklist. Questions that do not show default values have no defaults.

#### **EXAMPLE 1**

What is the main memory size of your computer? Specify one:

16KB, 24KB, 32KB, 48KB, 64KB

1 2 3 4 5	6 7 8 9 10 11 12 13 14 15 16 17 18 19 20 21 22 23 24 25 26 27 28 29 30 31 32 33 34 35 36 37 38 39 40	
2001	24KB MAIN MEMORY	6 77 78 79 80
•		

This answer shows a computer system that has 24KB of central storage. (MAIN MEMORY is a comment entry.)

#### **EXAMPLE 2**

Specify, on separate data cards, the device type and device address of each magnetic tape drive in your configuration. Appendix B lists the device type entry for supported devices. The device address is a three-digit hexadecimal number that begins with a 1 or 2. Use a comma to separate the device type from the device address.

Refer to Appendix D for the byte requirement of each tape drive and each controller. A maximum of four drives can be connected to one controller. The 800 bpi drives can be connected to 1600 bpi controllers, but 1600 bpi drives cannot be connected to 800 bpi controllers.

1, 2, 3, 4, 5	6 7 8 9 10 11 12 13	14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24, 25, 26, 27, 28, 29, 30, 31, 32, 33, 34, 35, 36, 37	38,39,40
3401	68.221	16.00 TAPE I	76 77 78 79 80
3402	68.222	16.00 TAPE 2	76 77 78 79 80

This answer shows two 1600 bpi tape drives located at device addresses 221 and 222.

#### **EXAMPLE 3**

How many cards are there in your average Assembler Language program? Specify a number from 1 through 65,535. Do not include a comma in your answer.

Default is 1000.

1, 2, 3, 4, 5	5 6 7 8 9 10 11 12 13 14 15 16 17 18 19 20 21 22 23 24 25 26 27 28 29 30 31 32 33 34 35 36 37 38 39 40	
5201	76 77	78 79 80

Because no answer is coded here, the SYSGEN programs will automatically supply the default value 1000. Remember, do *not* keypunch the card unless you code an answer to the question. Because you have accepted the default for this question, you would not submit a card numbered 5201.

## 2. SYSTEM GENERATION CHECKLIST

#### SYSGEN CONTROL

- 1. What type of SYSGEN are you performing? Specify one:
  - 1 Type 1 is a complete system generation.
  - 2 Type 2 is a modification of the resident operating system.
  - 3 Type 3 is a modification of the programming services.

#### Default is 1.

If you are performing a Type 1 SYSGEN, you must read all of the sections in this Checklist and answer the questions that describe your configuration and your system. If you are performing a Type 2 SYSGEN, you must answer the questions that pertain to features you wish to modify in the following Checklist sections: SYSGEN Control, System Control, Input Spooler, I/O Devices, and Telecommunications. If you are performing a Type 3 SYSGEN, you must answer the questions that pertain to features you wish to modify in the following Checklist sections: SYSGEN Control, Control Language Services, Assembly Language, and COBOL Language.

Refer to Section 3 in the MRX/OS System Generation Reference manual for a description of the file (library) of object modules used for each type of SYSGEN. This file is used as input to the Linkage Editor in SYSGEN job 2.

1.	2 3	4	5	6	7	8 ,	9	10	1	1	12	13	14	. 1	5	16	17	18	1	9 2	20.	21	22	23	24	25	2	6 2	7 2	8 :	29	30	31	32	33	34	1 3	5	36	37	38	39	40					
10	10	1																																										76	77	78	79	80
																					_																	Ī										

2. Which resident operating system do you have? Specify one:

MINIMUM (8KB)

**RESIDENT EXTENSION (10KB)** 

Default is RESIDENT EXTENSION.

The final size of your resident operating system depends upon the hardware-related options and software features that you decide to add to either the Minimum system or the Resident Extension system. Table D-1 in Appendix D lists the features and their byte requirements that can be added to both systems. Table D-2 lists the byte requirements of the telecommunications lines.

1, 2, 3, 4,	5, 6, 7, 8, 9	10 11	12 13 14	15 16	17 18	19 20	21, 2	2 23 2	25	26 27	28	29,30	31	33 34	35	36,37	38 39 40	
1002																		76 77 78 79 80
				•													L _ 1 _ 1	

3. What is the name of your library that contains the file of SYSGEN object modules that you want updated by the SYSGEN programs? The library name must be a 1 to 8 character alphanumeric name, and it must match the name you supply on the //CALL statement in GENPROC3.

Default is \$SGOBJ.

Refer to Section 3 in the MRX/OS System Generation Reference manual for a description of the library (\$SGOBJ) that contains the file of object modules that you want updated.

Refer to Appendix A in this manual for the //CALL statement of GENPROC3.

1, 2, 3, 4, 5	6.7.8.	9, 10, 11,	12 13 14 15 16	17, 18, 19, 20, 21, 22, 23, 24	25 26 27 28 29 30 31	32 33 34 35 36 37 38 39 40	
1003	****						76 77 78 79 80
	1				<del></del>		
	1						

#### SYSTEM CONTROL

1. What is the main memory size of your computer? Specify one:

16KB, 24KB, 32KB, 48KB, 64KB

<b>2001</b>	1, 2, 3, 4, 5, 6, 7, 8, 9, 10, 11	1 12 13 14 15 16 17 18 19 20 21 22 23 24	24, 25, 26, 27, 28, 29, 30, 31, 32, 33, 34, 35, 36, 37, 38, 39, 40	
	2001		76 77 78 79	80

2. Does your system have the hardware Error Correction (ECC) feature? Specify one:

YES

NO

Default is NO.

This feature is not available on the MRX 7200 Processing Unit. Table D-1 in Appendix D lists the software byte requirements.

1, 2, 3, 4, 5	6,7,8,	9, 10,	11, 1	2 13	14, 15,	16	17, 1	8 19	20	21	22	23 2	4 2	5,26	27	28	29	30 3	1 3	2 33	34	35	36 3	37	38 39	40		
2002							,																				76 77 7	8 79 80

3. If you have a two-partition system, specify in bytes the size of partition 1. Otherwise, omit this question, and the SYSGEN programs will automatically assign the memory that is not occupied by the resident operating system to your single user partition. No partition can be smaller than 8,192 bytes.

Use the following steps to determine the size of partition 1.

- 1. Add to the basic size of your resident (8KB or 10KB) the byte requirements of the various hardware-related options and software features that you have selected for your system. Tables D-1, D-2 and D-3 in Appendix D list these byte requirements.
- 2. Round this total byte count to a value that is divisible by 256.
- 3. Next, subtract this value from the total main memory size of your computer (your answer to question 1 in this section of the Checklist).
- 4. The remainder of your subtraction is the total amount of memory you have available for your user partitions.
- 5. Decide how large you want your first partition. Check to make sure that the size you have selected is divisible by 256; if not, round the number so that it is divisible by 256. This is the number that you code in answer to the question.

To find the size of the second partition, perform the following operation: subtract the rounded byte count for partition 1 from the total byte count available for use by the user partitions. The remainder is the size of your second partition. Do not code this number in answer to this question.

1, 2, 3, 4, 5	6 7 8 9 10 11 12 13 14	15 16 17 18 19 20 21 22 23 24 25 26 27 28 29	30, 31, 32, 33, 34, 35, 36, 37, 38, 39, 40
2003			76 77 78 79 80

4. If you have the Resident Extension operating system, specify whether or not you have selected Performance Option 1. Specify one:

YES

NO

Default is NO.

See Table D-1 in Appendix D for the byte requirement of this feature.

1, 2, 3, 4, 5	6 7 8	9 10	11	12	13 14	15	16	17	18, 1	19 2	20 2	21	22,2	23 2	25	26	27	28	29 3	0 31	32	33	34 3	5	36,37	38	39	40			
2004																													76 77	78	79 80
																_	<b></b>														

5. If you have the Resident Extension operating system, specify whether or not you have selected Performance Option 2. Specify one: YES NO Default is NO. See Table D-1 in Appendix D for the byte requirement of this feature. 2005 76 77 78 79 80 **OUTPUT SPOOLER** Answer the questions in this section if you have the Resident Extension system. If you specify NO in answer to question 1, skip the remaining questions in this section. If you have the Minimum system omit this section entirely. 1. Does your system have the Output Spooler feature? Specify one: YES NO Default is NO. See Table D-1 in Appendix D for the byte requirement of this feature. 1, 2, 3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24, 25, 26, 27, 28, 29, 30, 31, 32, 33, 34, 35, 36, 37, 38, 39, 40 2501 76 77 78 79 80 2. If your system has the Output Spooler, what is the maximum number of printers that you want dedicated to the Spooler at any one time? Specify a number in the following range: 1-14

Default is 1.

The number of device addresses coded in answer to question 4 in this section must not exceed the number of devices specified in answer to this question. The buffer space required for printers is determined from the answer to this question and the answer to question 5 in this section. Refer to Table D-2 in Appendix D for specific details.

Ļ	_2	_3	4	5	6	7	8	9	10	1	1 1	2 1	3 1	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31	32	33	34	35	36	37	38	39	40	l			
2	<u>5</u>	Ø	2	_																																					76 7	7 7	8 79	80
				-										_	_							-																						

3.	If you have a reader/punch, do you want it dedicated to output spooling? Specify one:
	YES
	NO
	Default is NO.
1, 2, <b>25</b> ,0	3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24, 25, 26, 27, 28, 29, 30, 31, 32, 33, 34, 35, 36, 37, 38, 39, 40  76, 77, 78, 79, 80
4.	If your system has the Output Spooler specify a list of the device addresses for the printers that you want assigned to the Spooler. Separate the device addresses one from another with a comma.
	Default is 21E.  All device addresses specified in answer to this question must also be specified in answer to question 4 in the I/O Devices section of this Checklist. Note also that the device type must also be specified when answering question 4 in the I/O Devices section. The number of printers that can be assigned depends on the printer blocking factor that you select. See Table D-2 in Appendix D for details.
1, 2, 3 <b>2.5</b> Ø	3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24, 25, 26, 27, 28, 29, 30, 31, 32, 33, 34, 35, 36, 37, 38, 39, 40  76, 77, 78, 79, 80
5.	If your system has the Output Spooler, specify the printer blocking factor. Refer to Table D-2 in Appendix D for the ranges allowed.  Default is 1.
1 2 3 <b>25</b>	3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24, 25, 26, 27, 28, 29, 30, 31, 32, 33, 34, 35, 36, 37, 38, 39, 40  76, 77, 78, 79, 80
6.	If your system has the Output Spooler, specify the punch blocking factor. Refer to Table D-1 in Appendix D for the byte requirement of the Spooler punch. Specify a number in the following range:  1-2
	Default is 1.
1, 2, 3 2.5 Ø	3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24, 25, 26, 27, 28, 29, 30, 31, 32, 33, 34, 35, 36, 37, 38, 39, 40  76, 77, 78, 79, 80

7.	If your system has the Output Spooler, what is the maximum number of files that you want to allow queued on the Spooler queue? Specify a number in the following range:
	45-255
	Default is 45.
1, 2, 3 <b>25</b>	3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24, 25, 26, 27, 28, 29, 30, 31, 32, 33, 34, 35, 36, 37, 38, 39, 40  76, 77, 78, 79, 80
8.	If your system has the Output Spooler, do you want the Job Accounting feature? Specify one:
	YES
	NO
	Default is NO.
	See Table D-1 in Appendix D for the byte requirement of this feature.
1 2 25	3 4 5 6 7 8 9 10 11 12 13 14 15 16 17 18 19 20 21 22 23 24 25 26 27 28 29 30 31 32 33 34 35 36 37 38 39 40 76 77 78 79 80
1/0 E	EVICES
1.	Does your system have the Second Channel feature? Specify one:
	YES
	NO
	Default is NO.
	See Table D-1 in Appendix D for the byte requirement of this feature.
3.Ø	3 4 5 6 7 8 9 10 11 12 13 14 15 16 17 18 19 20 21 22 23 24 25 26 27 28 29 30 31 32 33 34 35 36 37 38 39 40  76 77 78 79 80

2. Do you have a card reader attached to your integrated card reader attachment feature? Specify one:

YES

NO

If you specify YES, the SYSGEN programs assign your card reader to device address 204. The device type will be 23 to denote a buffered reader with the early return feature. If this device is your standard input device, refer to question 2 in the Control Language Services section of this Checklist.

1 2 3 4	5 6 7	8 , 9	9, 10	11	12, 1	3 14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31	32	33	34	35	36	37	38	39	40				_
3100																																	76 77	78	79	80
																												_								

3. Do you have a card reader/punch attached to your integrated card reader/punch attachment feature? Specify one:

YES

NO

If you specify YES, the SYSGEN programs will automatically assign your card reader/punch to device address 20C. The device type will be 11 to denote a buffered card reader/punch. If this device is your standard input device, refer to question 2 in the Control Language Services section of this Checklist.

1 2 3 4 5	6,7,8,	9 10	11, 13	2 13 14	4 15	16	17 1	8 19	20	21	22	23 24	25	26	27 2	8 29	30	31	32 3	3 34	35	36 3	7 3	8 39	40		
3200																										76 77	8 79 80

4. Specify, on separate data cards, the device type and device address of each line printer in your configuration. Appendix B lists supported device types. Use a comma to separate the device type from the device address. The device address is a three-digit hexadecimal number that must begin with 1 or 2 (in order to begin your device address with a 1, you must have answered YES to question 1 in this section).


Two speeds of line printers are available. They are: 600 lpm and 1200 lpm.

Default is 51,21E.

1 2 3 4	5 6 7	8	9	10	11	12	13	14	15	16	17	18	19	20	2	1 2	2, 23	24	25	26	27	28	29	30	31	32	33	34	35	36	3,37	38	3 39	40				
3300						_																													76	77	78	79
																											_											
3301																_		-			·							<u>'                                    </u>		_					76	77	78	79
	1				_													-										_		Ь			4	لــــا				
1, 2, 3, 4,	5 6 7	. 8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	2 23	24	25	26	27	28	29	30	31	32	33	34	35	36	37	38	3 39	40	М			
3302			سلبسما		-										•	'	-	•	•	•	_			-	_			<u> </u>	_				_		76	77	78	79

One printer is supported under both resident operating systems. Cards numbered 3303 through 3314 are available for additional line printers attached via the Selector Channel under both systems. Refer to Table D-1 in Appendix D for the byte requirements for additional line printers.

5. Specify, on separate data cards, the device type and device address of each magnetic tape drive in your configuration. Appendix B lists supported device types. Use a comma to separate the device type from the device address. The device address is a three-digit hexadecimal number that must begin with 1 or 2 (in order to begin your device address with a 1, you must have answered YES to question 1 in this section).




Additional cards numbered 3406 through 3459 are available for additional tapes under both resident operating systems. Refer to Table D-1 in Appendix D for the byte requirements for tape drives and tape controllers. A maximum of 4 drives can be attached to one controller. Do not attempt to attach 1600 bpi drives to the MRX 3237 Model 12 Magnetic Tape Drive controller (800 bpi controller).

6. Specify, on separate data cards, the device type and device address of each disc drive in your configuration. Appendix B lists supported device types. Use a comma to separate the device type from the device address. The device address is a three-digit hexadecimal number that must begin with a 3.

Defaults are: 70,300

70,301

1 2 3 4 5 6 7 8 9 10 11 12 13 14 15 16 17 18 19 20 21 22 23 24 25 26 27 28 29 30 31 32 33 34 35 36 37 38 39 40




Both systems support two disc drives. A maximum of 8 drives can be added under either resident operating system. It is also possible to configure a system containing only one drive. Refer to Table D-1 in Appendix D for the byte requirement for additional disc drives. Address 300 is assumed to be assigned to the system disc.

7. Do you want the disc Seek-on-Position software feature in your system? Specify one:

YES

NO

Default is NO.



See Table D-1 in Appendix D for the byte requirements of this feature.


8.	If you want automatically shared discs at IPL (initial program load) time, enter the
	addresses of the discs you want shared. Separate the addresses one from another
	using a comma. If you do not want this feature, omit this question.

1		2.	3	4	5	. 6	; ;	7 .	8	9	10	1	1	12	13	14	15	16	17	7, 1	8	19	20	21	22	2 23	24	2	5, 2	26	27	28	29	30	31	32	33	34	35	3	6 3	7	38 39	40	0					
3	7	1 9	8	Ø																							4.											4							T	76 7	7	78	79	80
						T						,																		_							·			_									استسا	

9. What UCS (universal character set) images do you want associated with each of your printers? Enter the printer address and the associated image for each UCS printer. Separate the printer address from the character image with a comma. Separate each pair one from another with a comma.

Example:

21E, PN, 21A, XX



#### **TELECOMMUNICATIONS**

If you have a telecommunications network in your configuration, you must answer the following series of questions. Otherwise omit them.


1. How many telecommunications lines do you have in your configuration? For MRX/40 Resident Extension users, specify a decimal number from 1 through 7. For MRX/50 Resident Extension users, specify a decimal number from 1 through 15. For each line you declare in answer to this question, you must code a data card that answers question 2. For example, if you specify 6 in answer to this question, you must code six data cards to answer question 2.

1 2 3 4	5	6.	7 8	, 9	10	11	12	13	14	15, 1	16 1	7 18	19	20	21	22	23	24	25	26	27	28 2	29	30	31	32	33	34	35	36 3	7	38 39	40				
4001																																		76	77 7	8 7	9 80

2. Specify, on separate data cards, the device type and device address of each telecommunications line in your configuration. Separate the device type from the device address with a comma. Appendix B lists supported device types. Appendix D, Table D-3, lists the byte requirements for each type. The device addresses available are 001 through 00F.

Remember, the device address must correspond to the line number. For example, the device address for line 1 would be 001, and for line A (decimal 10) it would be 00A.

1



Cards numbered 4108 through 4115 are available for additional line descriptions.

3. Do you want a logical communications capability in addition to the physical communications system that you have just configured? Specify one:

YES

NO

Default is NO.

1 2 3 4 5 6	6 7 8 9 10 11	12 13 14 15 16 17 18 19 20	21 22 23 24 25 26 27 28 29	30 31 32 33 34 35 36 37 38 39 4	0
4201					76 77 78 79 80

The byte requirements for this feature are listed in Table D-1 in Appendix D.

CONT	ROL LANGUAGE SERVICES
1.	What is the maximum number of entries that you will allow in your job queue?  Specify a number in the following range:  1-62
	Default is 1, which gives you first-in, first-out, job flow.
	Detault is 1, which gives you first-in, first-out, job flow.
1, 2 <b>5</b> , 1	3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24, 25, 26, 27, 28, 29, 30, 31, 32, 33, 34, 35, 36, 37, 38, 39, 40  76, 77, 78, 79, 80
2.	What device are you using as your standard input device for job control purposes? Specify one:
	READER
	READER/PUNCH
	Default is READER.
5 /	3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24, 25, 26, 27, 28, 29, 30, 31, 32, 33, 34, 35, 36, 37, 38, 39, 40  76, 77, 78, 79, 80
3.	What value do you want Control Language Services to supply for the keyword PRIORITY when the keyword is omitted from //JOB statements? Specify a number in the following range:  1-9
	Default is 1.
	Delaure is 1.
	3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24, 25, 26, 27, 28, 29, 30, 31, 32, 33, 34, 35, 36, 37, 38, 39, 40
5/	Ø.3. 76 77 78 79 80
	\( \begin{aligned} \] \tag{\text{\tinch{\text{\tin\tin\text{\text{\text{\text{\text{\text{\text{\tin\tint{\text{\ti}\tint{\text{\text{\text{\text{\text{\text{\text{\text{\text{\text{\text{\text{\text{\text{\text{\text{\texitin}\tint{\text{\texitin{\texit{\texitit{\text{\text{\texitin}\text{\texitint{\text{\tin\tint{\tint{\tintet{\texit{\texi{\texi{\texi{\texi{\tet

4.	What value do you want Control Language Services to supply for the keyword TIME when the keyword is omitted from //EXECUTE statements? Specify a number in the following range:
	1-1439
	Default is 1439 (23 hours, 59 minutes).
1 2	2 4 5 6 7 9 0 10 11 12 12 14 15 10 17 10 10 20 21 22 22 22 22 22 22 22 22 22 22 22 22
	3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24, 25, 26, 27, 28, 29, 30, 31, 32, 33, 34, 35, 36, 37, 38, 39, 40  76, 77, 78, 79, 80
5.	Do you want the keyword USER to be a required keyword on all //JOB statements? Specify one:
	YES
	NO
1	Default is NO.
1.0	2.4.5.0.7.0.0.00.00.00.00.00.00.00.00.00.00.0
5/	3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24, 25, 26, 27, 28, 29, 30, 31, 32, 33, 34, 35, 36, 37, 38, 39, 40  65
-	
6.	Which entry do you want Control Language Services to supply for the keyword SPL when the keyword is omitted from //ROUTE statements? Specify one:
	YES
-	NO
	Default is NO.
1, 2,	3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24, 25, 26, 27, 28, 29, 30, 31, 32, 33, 34, 35, 36, 37, 38, 39, 40
51	Ø 6 76 77 78 79 80

7. What value do you want Control Language Services to supply for the first positions/parameter for the keyword NUM (primary allocation) when the keyword is omitted from the //ROUTE statement? Specify a number in the following range: 1-32767 Default is 1000. Do not include a comma in your response. 1, 2, 3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24, 25, 26, 27, 28, 29, 30, 31, 32, 33, 34, 35, 36, 37, 38, 39, 40 5107 8. What value do you want Control Language Services to supply for the second positions/parameter for the keyword NUM (expand increment) when the keyword or this parameter is omitted from the //ROUTE statement. Specify a number in the following range: 1-32767 Default is 1000. Do not include a comma in your response. 2 3 4 5 6 7 8 9 10 11 12 13 14 15 16 17 18 19 20 21 22 23 24 25 26 27 28 29 30 31 32 33 34 35 36 37 38 39 40 What value do you want Control Language Services to supply for the keyword NUM 9. when the keyword is omitted from //DATA statements? Specify a number in the following range: 1-32767 Default is 1000. Do not include a comma in your response. 3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24, 25, 26, 27, 28, 29, 30, 31, 32, 33, 34, 35, 36, 37, 38, 39, 40

10.	What character set do you want to be the default for the UCS parameter on //ROUTE statements? Answer this question only if you have one or more printers that have the universal character set.
	Default is PN.
1, 2, <b>5,1</b>	3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24, 25, 26, 27, 28, 29, 30, 31, 32, 33, 34, 35, 36, 37, 38, 39, 40  76, 77, 78, 79, 80
ASSE	MBLER LANGUAGE
1.	How many cards are there in your average Assembler Language program? Specify a number in the range given below. Do not include a comma in your answer.
	1-65535
	Default is 1000.
5.2	2 3 4 5 6 7 8 9 10 11 12 13 14 15 16 17 18 19 20 21 22 23 24 25 26 27 28 29 30 31 32 33 34 35 36 37 38 39 40 76 77 78 79 80
2.	In which column do you want the Assembler to quit processing source statements? Specify a number in the following range:
	41-120
	Default is 72.
1, 2 <b>5,2</b>	2, 3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24, 25, 26, 27, 28, 29, 30, 31, 32, 33, 34, 35, 36, 37, 38, 39, 40  76, 77, 78, 79, 80
3.	How many lines per page do you want printed on your Assembler Language listing? Specify a decimal number. The answer to this question depends upon the size of your paper and the number of lines per inch that your printer prints.
	Default is 56.
<u> </u>	2 3 4 5 6 7 8 9 10 11 12 13 14 15 16 17 18 19 20 21 22 23 24 25 26 27 28 29 30 31 32 33 34 35 36 37 38 39 40
	· ·

4. Does your computer have the floating-point hardware feature? Specify o	ne:
YES	
NO	
Default is NO.	
1, 2, 3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24, 25, 26, 27, 28, 29, 30, 31, 32, 33, 34, 35, 36, 37, 38, 39, 4 <b>5264</b>	76 77 78 79 80
COBOL LANGUAGE	
<ol> <li>How many cards are there in your average COBOL program? Specify a the range given below. Do not include a comma in your answer.</li> </ol>	a number in
1-65535	
Default is 1000.	
1, 2, 3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24, 25, 26, 27, 28, 29, 30, 31, 32, 33, 34, 35, 36, 37, 38, 39, 5, 30, 7	, 40 76 77 78 79 80
2. In which column do you want the COBOL compiler to quit process source statements? Specify a number in the range given below.	ing COBOL
41-120	
Default is 72.	
1, 2, 3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24, 25, 26, 27, 28, 29, 30, 31, 32, 33, 34, 35, 36, 37, 38, 39	<del></del>
5.3.0.2	76 77 78 79 80
3. How do you want your USASI COBOL errors handled? Specify one:	
WARNING	
FATAL.	
Default is FATAL.	
1, 2, 3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24, 25, 26, 27, 28, 29, 30, 31, 32, 33, 34, 35, 36, 37, 38, 39, 5, 30, 3	40 76 77 78 79 80

# A. CONTROL LANGUAGE STATEMENTS FOR SYSTEM GENERATION

These are the Control Language statements needed to execute the System Generation programs. Only the statements for JOBONE, JOBTWO, JOB2A, and JOB2B (the formal SYSGEN jobs) are shown here. Insert your input data (answers to Checklist questions) where shown. Refer to Appendix B in the MRX/OS System Generation Reference manual for specific details about keyword parameters. The shaded //CALL statements are valid only for Procedure B. See the MRX/OS System Generation Reference manual, Section 4, for details.

#### **JOBONE CLS**

```
//JOB
          NAME=JOBONE, TYPE=1 [,USER=] [,PRIORITY=]
//CALL
          PROC=SGALLOC, NUCLOC=____, MSGLOC=7, SYSVOL=____
//CALL
          PROC=SGCOPYA, LIST=YES, INFILE=$SYSLODLIB,
//
          OUTFILE=$SYSLODLIB, OCAT=NO, OLOC=____, ONUM=____,
//
          INVOL=___, OUTVOL=_
//CALL
          PROC=SGCPYCAT, INVOL=____, OUTVOL=_
//CALL
          PROC=SGCOPY, INFILE=SYSGEN-MAC-BACKUP,
//
          OUTFILE=$SYSMACLIB
//EXEC
          PGM=LIBUTIL
//PAR
          COMMAND=DELETE, MEM=$OSCEPL, MEM=$OSCEPL2, MTYPE=ABS
          ID=LIST, DEV=PRINTER
//DEF
                                               input
          ID=OUTPUT, STA=(P,O), FIL=$SGOBJ, VOL=volume
//DEF
                                               identifier
//CALL
         PROC=GENPROC1
//DATA
          FIL=CHECKLISTDATA
          Insert input data (answer to Checklist questions) here.
//EOJ
```

<sup>\*</sup>Omit for Procedure B.

<sup>\*\*</sup>Omit for Type 2 and Type 3.

#### **JOBTWO CLS**

Defaults are underlined in the //CALL statements for GENPROC3.

```
NAME=JOBTWO, TYPE=1 [,USER=] [,PRIORITY=]
//JOB
//CALL
               PROC=GENPROC2
               PROC=GENPROC3, SYSVOL=____, DEVADDR=___
//CALL
               \left[ \text{ ,FULLGEN=} \left\{ \frac{\text{YES}}{\text{NO}} \right\} \right] \left[ \text{ ,STDNUC=} \left\{ \frac{\text{YES}}{\text{NO}} \right\} \right] \left[ \text{ ,OBJNAME=} \left\{ \frac{\text{your name}}{\text{\$SGOBJ}} \right\} \right]
//
//
//CALL
               PROC=GENPROC4
//CALL
               PROC=SGMERGE, SYSVOL=____
//CALL
               PROC=SGPURGE, FILE=$SYSLODLIBA
               PROC=SGRTNCAT, INVOL=____, OUTVOL=____
//CALL
//EOJ
```

Omit the //CALL statement to GENPROC3 for Type 3 SYSGENs.

#### **JOB2A CLS**

Insert the second to the last //DEF statement only if you answered YES to question 8 in the Output Spooler section of the Checklist.

```
NAME=JOB2A, TYPE=1 [,USER=] [,PRIORITY=]
//JOB
//EXEC
          PGM=LIBUTIL
//PAR
          COMMAND=COPY
          ID=INPUT, FIL=$SYSPROCLIB, STA=P, VOL=____
//DEF
          ID=OUTPUT, FIL=$SYSPROCLIB, STA=P, SIZ=80, NUM=1560,
//DEF
//
          ORG=S, CON=YES, VOL=____
          ID=CAT, FIL=$SYSELOG, STA=P, ORG=S, CON=YES, NUM=520,
//DEF
          SIZ=40, CSD=NO, BLK=1, CAT=YES, LOC=____
          ID=CAT, FIL=$OSSPLJA, STA=P, ORG=R, CON=YES, NUM=200,
//DEF
                                                                   Optional
          SIZ=54, CSD=NO, BLK=1, CAT=YES [,LOC=___] [,VOL=__
          ID=LIST, DEV=PRINTER
//DEF
//EOJ
```

#### **JOB2B CLS**

This job is not required if you are using Procedure B for your SYSGEN jobs.

```
//JOB NAME=JOB2B, TYPE=1 [,USER=] [,PRIORITY=]

//CALL PROC=SGCOPYA, OSIZ=80, OCSD=YES, OLOC=NO,

// INFILE=$SYSMACLIB, OUTFILE=$SYSMACLIB, ONUM=17550,

// INVOL=____, OUTVOL=____, LIST=YES

//CALL PROC=SGCOPYA, INFILE=$SGOBJ, OUTFILE=$SGOBJ,

// ONUM=8000, INVOL=____, OUTVOL=____ LIST=YES

//EOJ
```

#### **COMMENTS**

- 1. If you specified YES in answer to question 5 in the Control Language Services section of the Checklist, USER= becomes a required parameter for your system generation //JOB statements.
- 2. If you are performing a Type 3 system generation (refer to question 1 in the SYSGEN Control section of the Checklist), omit the //CALL statement to GENPROC3 in JOBTWO.
- 3. Because all of the SYSGEN jobs must be run sequentially, do not put the next job in the card reader until the preceding job has finished executing.

# **B. DEVICE DESCRIPTIONS**

Table B-1. I/O Equipment Table

Generic Name	Equipment Type	Device Type
PRT	132 char, nonbuffered	50
PRT	132 char, buffered	51
PRT	132 char, buffered	59
TAPE8	800 bpi density	60
TAPE16	1600 bpi density	68
DISC	200 cylinder	70
	PRT PRT PRT TAPE8 TAPE16	PRT 132 char, nonbuffered PRT 132 char, buffered PRT 132 char, buffered TAPE8 800 bpi density TAPE16 1600 bpi density

Table B-2. Telecommunications Equipment Table

Modem Name	Generic Name	Trans	Leased/ Switched	Use	Device Type
NONE (Local EIA-RS-232-C)	TP80	ASYNC	L	Switched Manual Dial/Answer	80
WE 103A, E, F WE 113B WE 202C,D 4-Wire	TP84	ASYNC	L	Switched Manual Dial/Answer	84*
WE 103F / Multi- WE 202C,D 4-Wire / point	TP85	ASYNC	L	Switched Manual Dial/Answer	85
WE 103A,E WE 113B	TP86	ASYNC ASYNC	S	Answer (only)	86
WE 202C,D	TP88	ASYNC	L	Switched Manual Dial/Answer	88
2-Wire Secondary Channel	TP8A	ASYNC	s	Answer (only)	8A
WE 202C,D	TP8C	ASYNC	L	Switched Manual Dial/Answer	8C
2-Wire	TP8E	ASYNC	s	Answer (only)	8E
0-11:0	TP98	ASYNC	L	Switched Manual Dial/Answer	98
Split Speed	TP9A	ASYNC	s	Answer (only)	9A
WE 201A,B WE 202C,D WE 203A WE 208A	TPA4	SYNC	L	Switched Manual Dial/Answer	A4
WE 201A,B WE 202C,D WE 203A WE 208A  Multi- point	TPA5	SYNC	L	Switched Manual Dial/Answer	A5
WE 201A WE 202C,D	TPA6	SYNC	S	Answer (only)	A6
WE 202C,D	TPA8	SYNC	L	Switched Manual Dial/Answer	A8
2-Wire Secondary Channel	TPAA	SYNC	S	Answer (only)	AA
WE 201A,B WE 202C,D WE 203A WE 208A	TPB4	SYNC	L	Switched Manual Dial/Answer	B4
WE 201A,B WE 202C,D WE 203A WE 208A  Mutlipoint	ТРВ5	SYNC	L	Switched Manual Dial/Answer	B5
WE 201A WE 202C,D	ТРВ6	SYNC	s	Answer (only)	B6
WE 202C,D 2-Wire	TPB8	SYNC	L	Switched Manual Dial/Answer	B8
Secondary Channel	ТРВА	SYNC	s	Answer (only)	BA

<sup>\*84</sup> is the line type used to describe direct line connections which do not include modems of 10, 15, or 30.

### C. SYSTEM GENERATION EXAMPLES

#### **SAMPLE 1: MINIMUM SYSTEM**

Figure C-1 shows a system generation data deck (answers to Checklist questions) used to generate a Minimum 8KB resident operating system. The hardware environment under which this resident operating system has been designed to operate includes:

- 24KB main memory
- One buffered card reader with the early return feature located at device address 204 and used as the system input device (default accepted for data card 5102)
- One buffered printer located at device address 21E and used as the system output device
- One disc drive located at device address 300

#### Additional features present include:

- Maximum of 4 entries in the job queue
- Value of 60 for the TIME= keyword on //EXEC statements
- 800 cards in the average Assembler Language program

No COBOL compiler is present. Defaults selected include:

- \$SGOBJ is the library containing the file of SYSGEN object modules updated by the SYSGEN programs
- No hardware ECC (error correction feature)
- Single partition system
- No Second Channel feature
- No disc Seek-on-Position software feature
- Priority of 1 for the PRIORITY= keyword on //JOB statements
- NO as the value of the keyword USER= on //JOB statements
- 72 as the column where the assembler should quit processing source language statements
- 56 lines per page on an Assembler Language listing

## **Assembler Coding Form**

OPERAND

	Punchi	ng Inst	ructio	15				Date	e					P	age_		_0	f	<u>/</u>	_
Graphic	-	1	I	7			_	Pro	yram	mer_										
Punch	<b>≇</b> ERO	ONE	CAP.	CAF	?			Pro	gram	5	<u>YS</u>	GE	N	fo	r	M. PV	ZN	17/	M	7
										5	<u> </u>	TE	1	- 7	ZV.	PV	<u> </u>	2	<u> </u>	۷
															IDE	NTIF	:ICA	TIO	N	
46 47 48 49 50 51	52 53 5	54 55	56 57 !	58 59	60 61	62 63	64	65 66	67	68 6	9 70	71	72	73 [	74 7	76	77,	78,7	79	80
				. 1										Ĺ.,						
	,	1	1	T	1															
1	7	7	$\Pi$	4								_								
77)	1	-(	<i>,</i>								•	•	•							
$\forall \vdash \vdash$											-		'ـــــــــــــــــــــــــــــــــــــ							
44.5					<b></b>									-				_		
												4		-					_	_
												-		┝					_	
										_				-				_		
											_		,						_	_

				0 74 75 70 77
			19 20 21 22 23 24 25 26 27 28 29 30 31 32 33 34 35 36 37 38 39 40 41 42 43 44 45 46 47 48 49 50 51 52 53 54 55 56 57 58 59 60 61 62 63 64 65 66 67 68 69 70 71 72 7	3 /4 /5 /6 //
* S Y S G E				
1002	MINI	MUM		
* S Y S T E	MCON	TROL	4010	
	24KB	MAIN	EMORY SIZE	
F.E.E.			.) [1]	
	* * * * *			
*1/0 DE	VICES			
3100	VES	CPDP	ADER SYS STAN INPUT DEVICE	
3200		NO DE	DER/PUNCH	
2 5 01 0	70 2	MA DUE DE	IVE SYSTEM	
ومودو	اح و عرب	UNC. UNC.	14.6. 27.37.6.	
* C O N T F	20114	NGUAGE	S F R V I C F S	
5101			RIES IN JOB QUEUE	
	4 60	MALLENI	OR. TIME PARAMETER ON LIEXEC CARD.	
0193	7 09	V.H.L.U.E.	UK. 11ME. PHRAME. OR. UN. 11EACC. CHR.D.	
* A S S E M	PIED	LANGUAG	F	
	800		NUM CARDS IN ASM LANG PROGRAM	
رطيعان	w.w.	H.V.Z.A.H.OC	H.O.H. CARDS III AS IL EARNO PAROSA A.I.	
<u> </u>	· · · · · · · · · · · · · · · · · · ·	<del> </del>		
<u> </u>				
		<del>   </del>		
		<del> </del>		
		<u> </u>		73 74 75 76 77

<sup>\*</sup>Do not insert these headings in your input deck.

OPERATION

This system does not include clock processing (the timing feature). No entry is shown describing the printer because the default has been selected.

#### SAMPLE 2: RESIDENT EXTENSION SYSTEM

Figure C-2 shows a system generation data deck (answers to Checklist questions) used to generate a Resident Extension (10 KB) operating system. The hardware configuration under which this resident has been designed to operate includes:

- 48KB main memory
- Hardware ECC (error correction feature)
- Two partitions, the first being 13056 bytes
- Performance Option 1
- Output Spooler feature
- Two dedicated printers at device addresses 21E, and 21A
- One dedicated reader/punch at device address 20C
- Printer blocking factor of 4 and reader/punch blocking factor of 2
- Maximum of 100 files in the job queue
- Job Accounting feature
- Second Channel feature
- One buffered card reader with early return feature at device address
   204
- One buffered card reader/punch on device address 20C used as the standard system input device
- Three buffered printers at device addresses 21E, 21A, and 217
- One 800 bpi tape at device address 100
- Two 1600 bpi tapes at device addresses 107 and 10E
- Four discs at device addresses 300, 301, 302, and 303
- One device type 84 communications line at device address 001
- Three device type A4 communications lines at device address 002, 003, and 004

#### Additional features present include:

- Disc Seek-on-Position feature
- Two shared discs on device addresses 302 and 303
- PN on device address 21E and XX on device address 21A (UCS printers)
- Logical communications capability
- Maximum of 12 entries in the job queue
- PN is the default character set on //RTE statements
- Value of 30 for the TIME= keyword on //EXEC statements
- USER= keyword required on //JOB statements
- 120 as the column where the Assembler and the COBOL compiler quite processing source statements
- Floating-point hardware feature
- 1500 cards in the average COBOL program

#### Defaults selected include:

- Type 1 SYSGEN
- Resident Extension system
- \$SGOBJ is the library containing the file of SYSGEN object modules updated by the SYSGEN programs
- SPL=YES on //RTE statements
- NUM=1000 for first and second position parameters on //RTE statements
- NUM=1000 on //DATA statements
- Priority of 1 as the value of the keyword USER= on //JOB statements
- 1000 cards in the average Assembler Language program
- 56 lines per page on an Assembler Language listing
- COBOL USASI errors are treated as fatal.

n n	D/	20	الحار	V7
IMI	NK	少片	(三)	Χ

## **Assembler Coding Form**

	Punchi	ing Inst	ruction	15		DatePage_lof3
Graphic	Ø	2 or	I	Z	.	Programmer
Punch	ZERO	ONE	CAP.	CAP.		Program SYSGEN DATA FOR RESIDEN

		EXTENSION OPERATING SY
NAME OPERATI	ON OPERAND	IDENTIFICATIO
1, 2, 3, 4, 5, 6, 7, 8 9 10, 11, 12, 13, 1	1 15 16 17 18 19 20 21 22 23 24 25 26 27 28 29 30 31 32 33 34 35 36 37 38 39 40 41 42 43 44 45 46	47 48 49 50 51 52 53 54 55 56 57 58 59 60 61 62 63 64 65 66 67 68 69 70 71 72 73 74 75 76 77 78
YSGEN CONTROL		
YSTEM CONTROL		
2001 48KB	MAIN MEMORY SIZE	$C \cap A \cup C \cup$
2002 YES	ERR CORR FEATURE	SAVIII
2063 13056	SIZE PARTITION 1 IN BYTES	
2005 YES	PERFORMANCE OPTION 1	
		$\mathcal{T}(M)$
UTPUT SPOOLER		
25Ø1 YES	OUTPUT SPOOLER FEATURE PRESE	N.T.
2502 2	2 DEDICATED PRINTERS	
2503	1 DEDICATED RDR/PNCH	
2504 21E, 21A	PRINTER ADDRS ASGN TO SPOOLE	i.R
2505 4	PRINTER BLK FACTOR	
2506 2	PUNCH BLK FACTOR	
2507 100	MAX NO OF FILES ON SPOOLER Q	D.U.E. U.E
2508 YES	JOB ACCT FEATURE PRESENT	
		<u>, , , , , , , , , , , , , , , , , , , </u>
O DEVICES		
3000 YES	2ND CHAN FEATURE PRESENT	
3100 YES	BUF CRD. RDR. ON. DEV. ADDR. 204.	
3200 YES	BUF RDR/PCH ON DEV ADDR 20C	
1 2 3 4 5 6 7 8 9 10 11 12 13 1	15 16 17 18 19 20 21 22 23 24 25 26 27 28 29 30 31 32 33 34 35 36 37 38 39 40 41 42 43 44 45 46	6 47 48 49 50 51 52 53 54 55 56 57 58 59 60 61 62 63 64 65 66 67 68 69 70 71 72 73 74 75 76 77 78

<sup>\*</sup>Do not insert these headings in your input deck.

MEMOREX	Assembler	Coding	<b>Form</b>
---------	-----------	--------	-------------

Punching Instructions  Graphic   Oh   10R   T   Z	DatePage_2_ of_3
	Programmer
Punch RERO ONE I Z	Program SYSGEN DATA FOR RESIDENT EXTENSION OPERATING SYSTEM

<del></del>		EXTENSION O	OPERATING S
NAME	OPERATION		IDENTIFICATION
1 2 3 4 5 6 7 8	9 10 11 12 13 14 15 16 17	18 19 20 21 22 23 24 25 26 27 28 29 30 31 32 33 34 35 36 37 38 39 40 41 42 43 44 45 46 47 48 49 50 51 52 53 54 55 56 57 58 59 60 61 62 63 64 65 66 67 68 69 70 71 72 73 74	4 75 76 77 78 79 80
3300 51 2		PRINTER 1	
3301 51 2	21 A	PRINTER 2	
3302 51 2	21.7	PRINTER 3	<del></del>
3400 60 7	100	TAPE 1 800 BPI	
3401 68 1	107	TAPE 2 1600 BPI	
3402 68 1		TAPE 3 1600 BPI	
3500 70, 3	3 Ø Ø	DISC 1	
3501 70 3	3 Ø 1	DISC 2	
3502 70,3	3 Ø. 2.	DISC 3	
3 <i>5ø3 7ø</i>	303	DISC 4	
3601 YES		DISC SEEK ON POSITION FEATURE	
3700 30Z	3.0.3.	SHARED DISCS.	
3800 215,	PN , 21A , X	X	- <b></b>
	<u> </u>		
LECOMMUNI	CATIONS		
1001 4		NUM OF TOOM LINES	
4101 84,0		TCOM LINE 1	
4.102 A.4 , 0	2,00	TCOM LINE 2	
4103 A4,0	0.3	TCOM LINE 3	
4104 A4, 0	ΡΙΦ.Ψ	TCOM LINE 4.	
	GUAGE SERVI	<del></del>	· · · · · · · · · · · · · · · · · · ·
5101 12	1	NUM OF ENTRIES IN JOB QUEUE	
		STAND INPUT DEVICE	
1 2 3 4 5 6 7 8 5	9 10 11 12 13 14 15 16 17	18 19 20 21 22 23 24 25 26 27 28 29 30 31 32 33 34 35 36 37 38 39 40 41 42 43 44 45 46 47 48 49 50 51 52 53 54 55 56 57 58 59 60 61 62 63 64 65 66 67 68 69 70 71 72 73 74	75 76 77 78 79 80

<sup>\*</sup>Do not insert these headings in your input deck.

Tr\ /41	[□] <sub>1</sub> \	/10		<u>-</u> \\//
TVAVI		MIN J	LEXIE	- /∧\

## **Assembler Coding Form**

Punching Instructions  Graphic   Ø	DatePage3of3_
Punch TERO ONE CAP. CAP.	Program SYSGEN DATA FOR RESIDENT EXTENSION OPERATING SYSTEM

		EXTENSION	OPERATING .
NAME	OPERATION	OPERAND	IDENTIFICATION
	0 11 12 13 14 15 16 1	7 18 19 20 21 22 23 24 25 26 27 28 29 30 31 32 33 34 35 36 37 38 39 40 41 42 43 44 45 46 47 48 49 50 51 52 53 54 55 56 57 58 59 60 61 62 63 64 65 66 67 68 69 70 71 72	73,74,75,76,77,78,79
164 36		VALUE OF TIME PARM ON //JOB STMTS	
105 YES		USER = PARM ON //JOB STMTS	
106 YES		SPL = PARM DEFAULT ON //RTE STMTS.	
SEMBLER LAN	NGUAGE		<u> </u>
202 120		COL WHERE ASSM QUITS PROCESSING SOURCE: TOOM LIMIT	
204 YES		FLOAT PT HOWE FEATURE	
BOL LANGUA	<u> </u>		
BOL LANGUA	GE		
301 1500		NUM OF CARDS IN AVG COBOL PROGRAM	
302 120		COL WHERE COBOL QUITS PROCESSING SOURCE: TCOM LIMIT	
		T MO	
11			_
· · · · · · · · · · · · · · · · · · ·	* * * * * * * * * * * * * * * * * * * *		
<del></del>			
<del></del>			
			<u> </u>
1 2 3 4 5 6 7 8 9 1	0 11 12 13 14 15 16 1	17 18 19 20 21 22 23 24 25 26 27 28 29 30 31 32 33 34 35 36 37 38 39 40 41 42 43 44 45 46 47 48 49 50 51 52 53 54 55 56 57 58 59 60 61 62 63 64 65 66 67 68 69 70 71 72	73 74 75 76 77 78 7

<sup>\*</sup>Do not insert these headings in your input deck.

## D. BYTE REQUIREMENTS FOR OPTIONAL FEATURES

The byte requirements for the various options that are available under both MRX operating systems are within 10% of the actual byte requirements.

Table D-1. Byte Requirements for Available Options

Option Name	Byte Requirement
Error Correction Feature (ECC Log)	160
Performance Option 1 (Resident Extension system only)	270
Performance Option 2 (Resident Extension system only)	250+X+Y+Z*
Job Accounting Feature (Resident Extension system only)	250
Output Spooler (Resident Extension system only)	4096**
Spooler Punch (Resident Extension System only)	220+142 x punch blocking factor
Second Selector Channel Feature	150
Additional Line Printers (each)	18
Magnetic Tape Controller, including One Tape Drive	462
Additional Tape Drives (each)	14
Additional Disc Drives (each)	14
Disc Seek-on-Position Feature	30
Logical Communications Feature (Resident Extension system only)	1650
Floating-point Hardware Feature	8K control storage

<sup>\*</sup>Where X = nominal associative list length, Y = TCOM associative list length, and Z = Spooler associative list length.

<sup>\*\*</sup>An additional 452 bytes are required for system labels and default buffers.

Table D-2. Printer Spooler Blocking Factors

Number of Printers*	Blocking Factor Range .
1	1-14
2	1-14
3	1-7
4	1-5
5	1-3
6	1-3
7	1-2
8	1-2
9-14	1

<sup>\*</sup>Byte requirements for spooled printer = 220 + 142 x blocking factor.

Use Table D-3 to calculate the byte requirements for each line type in your configuration. The basic driver byte requirement is 2046.

Table D-3. Byte Requirements for Telecommunications Lines


Line (Device) Type	Byte Requirement
Line (Bovice, Type	byte Requirement
80	2180
84	2354
85	2502
86	2442
88	2354
8A	2442
8C	2502
8E	2590
98	2406
9A	2494
A4	2850
A5	2850
A6	2938
A8	2706
AA	2794
В4	2980
B5	2980
В6	3068
B8	2836
ВА	2924

## **COMMENTS FORM**

MRX/OS System Generation Checklist (2260.003-01)

Please send us your comments, to help us produce better publications. Use the space below to qualify your responses to the following questions, if you wish, or to comment on other aspects of the publication. Please use specific page and paragraph/line references where appropriate. All comments become the property of the Memorex Corporation.

		Yes	
ls the	e material:		
	Easy to understand?		
	Conveniently organized?		
	Complete?		
	Well illustrated?		
	Accurate?		
	Suitable for its intended audience?		
	Adequately indexed?		
FOI V	what purpose did you use this publication? (reference, general interest		
	e state your department's function:e check specific criticism(s), give page number(s), and explain below:		
Please	e check specific criticism(s), give page number(s), and explain below:  Clarification on page(s)		
Please	e check specific criticism(s), give page number(s), and explain below:  Clarification on page(s)		
Please	e check specific criticism(s), give page number(s), and explain below:  Clarification on page(s)  Addition on page(s)  Deletion on page(s)		
Please	e check specific criticism(s), give page number(s), and explain below:  Clarification on page(s)  Addition on page(s)  Deletion on page(s)		
Please	e check specific criticism(s), give page number(s), and explain below:  Clarification on page(s)  Addition on page(s)  Deletion on page(s)		
Please	e check specific criticism(s), give page number(s), and explain below:  Clarification on page(s)  Addition on page(s)  Deletion on page(s)		
Please	e check specific criticism(s), give page number(s), and explain below:  Clarification on page(s)  Addition on page(s)  Deletion on page(s)		
Please	e check specific criticism(s), give page number(s), and explain below:  Clarification on page(s)  Addition on page(s)  Deletion on page(s)		
Please	e check specific criticism(s), give page number(s), and explain below:  Clarification on page(s)  Addition on page(s)  Deletion on page(s)		
Please	e check specific criticism(s), give page number(s), and explain below:  Clarification on page(s)  Addition on page(s)  Deletion on page(s)		



First Class

Permit No. 14831 Minneapolis, Minnesota 55427



Thank you for your information.....

Our goal is to provide better, more useful manuals, and your comments will help us to do so.

.........Memorex Publications